The Pyramid Web Application Development Framework

Version 1.1

Chris McDonough

CONTENTS

Fr	ont Matter	i
Co	pyright, Trademarks, and Attributions	iii
	Attributions	
	Print Production	
	Contacting The Publisher	
	HTML Version and Source Code	iv
Туј	pographical Conventions	v
Au	thor Introduction	vii
	Audience	. vii
	Book Content	
	The Genesis of repoze.bfg	. viii
	The Genesis of Pyramid	ix
	Thanks	ix
Ι	Narrative Documentation	1
1	Pyramid Introduction	3
	1.1 What Is The Pylons Project?	
	1.2 Pyramid and Other Web Frameworks	
2	Installing Pyramid	7
	2.1 Before You Install	
	2.1.1 If You Don't Yet Have A Python Interpreter (UNIX)	
	2.1.2 If You Don't Yet Have A Python Interpreter (Windows)	
	2.2 Installing Pyramid on a UNIX System	9

		2.2.2 Creating the Virtual Python Environment	10 10
			11
	2.3		11
	2.4		12
	2.5		12
	2.6	What Gets Installed	12
3	App	lication Configuration	13
	3.1	Imperative Configuration	13
	3.2	Declarative Configuration	14
	3.3		15
4	Crea	ating Your First Pyramid Application	17
	4.1		17
			18
		1	18
			19
			20
			20
		6 6	21
			22
			22
	4.2		22
_	C	ding a Demonsial Deviced	22
5	Cre 2	8 . 9	23 23
	5.2		23 24
	5.2 5.3		24 26
	5.3 5.4		20 26
	5.4 5.5	0 11	20 27
	5.6		28
	5.0 5.7	6 11	20 30
	5.8	5	31
	5.0	1 5 5	31
		-	35
			35
			35
			33 37
	5.0	1 5	
	5.9	11 5 0	38
			39 40
			40
			41 41

		5.9.5 templates/mytemplate.pt 41
		5.9.6 tests.py
	5.10	Modifying Package Structure
	5.11	Using the Interactive Shell
6		Dispatch 45
	6.1	High-Level Operational Overview
	6.2	Route Configuration 45
		6.2.1 Configuring a Route to Match a View
		6.2.2 Route Pattern Syntax
		6.2.3 Route Declaration Ordering 50
		6.2.4 Route Factories
		6.2.5 Route Configuration Arguments
		6.2.6 Custom Route Predicates
	6.3	Route Matching
		6.3.1 The Matchdict
		6.3.2 The Matched Route
	6.4	Routing Examples
		6.4.1 Example 1
		6.4.2 Example 2
		6.4.3 Example 3
	6.5	Matching the Root URL
	6.6	Generating Route URLs
	6.7	Static Routes
	6.8	Redirecting to Slash-Appended Routes
		6.8.1 Custom Not Found View With Slash Appended Routes 60
	6.9	Cleaning Up After a Request
	6.10	Using Pyramid Security With URL Dispatch
		Debugging Route Matching
	6.12	Route View Callable Registration and Lookup Details
	6.13	References
_		
7	View	
	7.1	View Callables
	7.2	Defining a View Callable as a Function
	7.3	Defining a View Callable as a Class
	7.4	View Callable Responses
	7.5	Using Special Exceptions In View Callables
		7.5.1 HTTP Exceptions
		7.5.2 How Pyramid Uses HTTP Exceptions
	7.6	Custom Exception Views
	7.7	Using a View Callable to Do an HTTP Redirect
	7.8	Handling Form Submissions in View Callables (Unicode and Character Set Issues) 71
	7.9	Alternate View Callable Argument/Calling Conventions

	7.10	Pylons-1.0-Style "Controller" Dispatch	74
8		Pylons-1.0-Style "Controller" Dispatch lerers Writing View Callables Which Use a Renderer Built-In Renderers	74 75 76 77 77 78 78 80 81 82 83 84
	8.7	8.6.1 Adding a New Renderer 8.6.2 Changing an Existing Renderer Overriding A Renderer At Runtime	84 86 87
9	9.1 9.2 9.3 9.4 9.5 9.6 9.7 9.8 9.9 9.10	platesUsing Templates DirectlySystem Values Used During RenderingTemplates Used as Renderers via ConfigurationTemplates Used as Renderers via Configuration <i>Chameleon</i> ZPT Templates9.4.1A Sample ZPT Template9.4.2Using ZPT Macros in PyramidTemplating with Chameleon Text TemplatesSide Effects of Rendering a Chameleon TemplateNicer Exceptions in Chameleon Templates <i>Chameleon</i> Template InternationalizationTemplating With Mako Templates9.9.1A Sample Mako TemplatesAutomatically Reloading TemplatesAvailable Add-On Template System Bindings	 89 89 93 94 95 96 97 98 99 100 100 101 102 102
10	10.1	A Configuration Mapping a Resource or URL Pattern to a View Callable 10.1.1 View Configuration Parameters 10.1.2 Adding View Configuration Using the @view_config Decorator 10.1.3 Adding View Configuration Using add_view() 10.1.4 Configuring View Security 10.1.5 NotFound Errors Influencing HTTP Caching Debugging View Configuration	103 103 104 110 113 114 114 114 115

	11.1	Understanding Asset Specifications	17			
	11.2	.2 Serving Static Assets				
	11.2.1 Generating Static Asset URLs					
	11.3	Advanced: Serving Static Assets Using a View Callable	21			
			22			
			23			
	11.4		23			
			24			
12	Requ	est and Response Objects 1	27			
	12.1	Request	28			
		12.1.1 Special Attributes Added to the Request by Pyramid	29			
		12.1.2 URLs	29			
		12.1.3 Methods	30			
			30			
			30			
			31			
			32			
	12.2		32			
			33			
			33			
			34			
			34			
			51			
13	Sessi	ons 1	35			
	13.1	Using The Default Session Factory	35			
			36			
	13.3		37			
			37			
		• •	38			
	10.0	-	38			
			39			
			39			
	13.6		40			
	15.0		40			
		6 5 = =	40			
		13.0.2 Using the session.new_csii_coken Method	40			
14	Usin	g Events 1	43			
			43			
			44			
			45			
			-			
15			47			
	15.1	Reloading Templates	47			

15.2 Reloading Assets	. 148
15.3 Debugging Authorization	. 148
15.4 Debugging Not Found Errors	. 148
15.5 Debugging Route Matching	. 148
15.6 Preventing HTTP Caching	. 149
15.7 Debugging All	. 149
15.8 Reloading All	. 149
15.9 Default Locale Name	. 149
15.10Mako Template Render Settings	
15.10.1 Mako Directories	. 150
15.10.2 Mako Module Directory	
15.10.3 Mako Input Encoding	
15.10.4 Mako Error Handler	. 151
15.10.5 Mako Default Filters	. 151
15.10.6 Mako Import	. 151
15.10.7 Mako Strict Undefined	. 151
15.10.8 Mako Preprocessor	. 152
15.11Examples	. 152
15.12Understanding the Distinction Between reload_templates and reload_assets	153
15.13Adding A Custom Setting	. 154
 16.1 Displaying Matching Views for a Given URL 16.2 The Interactive Shell 16.2.1 Extending the Shell 16.2.2 IPython 16.3 Displaying All Application Routes 16.4 Writing a Script 16.4.1 Changing the Request 16.4.2 Cleanup 	. 159 . 160 . 161 . 161 . 162 . 164 . 165
16.4.3 Setting Up Logging	. 165
 17 Internationalization and Localization 17.1 Creating a Translation String	. 167 . 169
 17.2.1 Installing Babel and Lingua	. 171 . 172 . 174

		76
		77
		78
		78
	17.7 Mako Pyramid I18N Support	79
	17.8 Localization-Related Deployment Settings	79
	0 00	80
	17.10Activating Translation	81
		81
	e	82
	e	82
	8	82
	17.11.2 Using a Custom Locale Negotiator	83
10	T70 / 1TT /1	~ =
18	8	85 95
		85
	II	86 07
	18.3 Further Documentation and Examples	87
19	Unit, Integration, and Functional Testing	89
		90
	1	92
		92
		94
		95
20		97
	e	98
		99
	0	00
	\mathcal{B}	02
		02
		03
	8 8	04
		04
	6	05
		05
	· · · · · · · · · · · · · · · · · · ·	07
	20.11Pyramid API Functions That Act Against Resources	08
71	Much Ado About Theyencel	09
41	Much Ado About Traversal 20 21.1 URL Dispatch 21	
	1	10 10
	21.2 Firstofical Refresher 21 21.3 Traversal (aka Resource Location) 21	
	21.5 Have sat (and resource Location) $\ldots \ldots \ldots$	11

	21.4 What Is a "Resource"?	212
	21.5 View Lookup	213
	21.6 Use Cases	214
22	Traversal	217
	22.1 Traversal Details	
	22.2 The Resource Tree	
	22.3 The Traversal Algorithm	
	22.3.1 A Description of The Traversal Algorithm	
	22.3.2 Traversal Algorithm Examples	
	22.3.3 Using Resource Interfaces In View Configuration	226
	22.4 References	228
23	Security	229
	23.1 Enabling an Authorization Policy	
	23.1.1 Enabling an Authorization Policy Imperatively	
	23.2 Protecting Views with Permissions	
	23.2.1 Setting a Default Permission	
	23.3 Assigning ACLs to your Resource Objects	
	23.4 Elements of an ACL	
	23.5 Special Principal Names	235
	23.6 Special Permissions	
	23.7 Special ACEs	
	23.8 ACL Inheritance and Location-Awareness	236
	23.9 Changing the Forbidden View	237
	23.10Debugging View Authorization Failures	237
	23.11Debugging Imperative Authorization Failures	237
	23.12Creating Your Own Authentication Policy	
	23.13Creating Your Own Authorization Policy	
24	Combining Traversal and URL Dispatch	241
	24.1 A Review of Non-Hybrid Applications	
	24.1.1 URL Dispatch Only	241
	24.1.2 Traversal Only	242
	24.2 Hybrid Applications	242
	24.2.1 The Root Object for a Route Match	244
	24.2.2 Using *traverse In a Route Pattern	244
	24.2.3 Using the traverse Argument In a Route Definition	247
	24.2.4 Using * subpath in a Route Pattern	
	24.3 Corner Cases	
	24.3.1 Registering a Default View for a Route That Has a view Attribute	
	24.3.2 Binding Extra Views Against a Route Configuration that Doesn't Have	
	*traverse Element In Its Pattern	

25	Using Hooks	251
	25.1 Changing the Not Found View	251
	25.2 Changing the Forbidden View	252
	25.3 Changing the Request Factory	253
	6	254
		255
		256
	6	256
	8.8	257
		259
		260
	6 11	262
	25.12Registering Configuration Decorators	263
26	Advanced Configuration	267
20	8	267
		269
		209
		272
		272
		273
		273
	2011 Having House to the comparator for add_arrester to the terms	27.
27		277
27	27.1 The Difference Between "Extensible" and "Pluggable" Applications	277
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 279
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 279 280
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 279 280 281
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 280 281 282
27	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 279 280 281
	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 	277 278 279 279 279 280 281 282 282
	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 280 281 282 282 282 283
	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 280 281 282 282 282 283
	 27.1 The Difference Between "Extensible" and "Pluggable" Applications	277 278 279 279 279 280 281 282 282 282 283
28	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 28.1 The Startup Process 28.2 Deployment Settings 	277 278 279 279 280 281 282 282 283 283
28	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 28.1 The Startup Process 28.2 Deployment Settings 27.3 Extends 	 277 278 279 279 280 281 282 283 283 287
28	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 28.1 The Startup Process 28.2 Deployment Settings 27.3 Extends 29.1 Why and How Pyramid Uses Thread Local Variables 	 277 278 279 279 280 281 282 283 283 287 289
28 29	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 28.1 The Startup Process 28.2 Deployment Settings 28.1 The Startup Process 28.2 Deployment Settings 29.1 Why and How Pyramid Uses Thread Local Variables 29.2 Why You Shouldn't Abuse Thread Locals 	 277 278 279 279 279 280 281 282 283 283 287 289 290
28 29	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 28.1 The Startup Process 28.2 Deployment Settings 29.1 Why and How Pyramid Uses Thread Local Variables 29.2 Why You Shouldn't Abuse Thread Locals 29.2 Why You Shouldn't Abuse Thread Locals 29.3 Using the Zope Component Architecture in Pyramid 	 277 278 279 279 279 280 281 282 283 283 287 289 289 290 293
28 29	 27.1 The Difference Between "Extensible" and "Pluggable" Applications 27.2 Rules for Building An Extensible Application 27.2.1 Fundamental Plugpoints 27.3 Extending an Existing Application 27.3.1 If The Application Has Configuration Decorations 27.3.2 Extending the Application 27.3.3 Overriding Views 27.3.4 Overriding Routes 27.3.5 Overriding Assets 28.1 The Startup Process 28.2 Deployment Settings 29.1 Why and How Pyramid Uses Thread Local Variables 29.2 Why You Shouldn't Abuse Thread Locals 29.3 Why You Shouldn't Abuse Thread Locals 29.4 Why You Shouldn't Abuse Thread Locals 	 277 278 279 279 279 280 281 282 283 283 287 289 290

30.1.1	Disusing the Global ZCA API	294
30.1.2	Enabling the ZCA Global API by Using hook_zca	295
30.1.3	Enabling the ZCA Global API by Using The ZCA Global Registry	296

II Tutorials

31	ZOD	B + Tra	aversal Wiki Tutorial	301
	31.1	Backgr	ound	301
	31.2	Installa	tion	302
		31.2.1	Preparation	302
		31.2.2	Making a Project	304
		31.2.3	Installing the Project in "Development Mode"	305
			Running the Tests	305
		31.2.5	Starting the Application	305
			Exposing Test Coverage Information	306
			Visit the Application in a Browser	306
		31.2.8	Decisions the pyramid_zodb Scaffold Has Made For You	306
	31.3	Basic L	Layout	307
		31.3.1	App Startup withinitpy	307
			Resources and Models with models.py	308
			Views With views.py	309
			The WSGI Pipeline in development.ini	310
	31.4		ng the Domain Model	312
			Deleting the Database	313
			Making Edits to models.py	313
			Looking at the Result of Our Edits to models.py	314
			Viewing the Application in a Browser	314
	31.5		ng Views	314
			Declaring Dependencies in Our setup.py File	315
			Adding View Functions	316
			Viewing the Result of all Our Edits to views.py	319
			Adding Templates	321
			Viewing the Application in a Browser	325
	31.6			326
			Adding Authentication and Authorization Policies	326
			Adding security.py	327
			Giving Our Root Resource an ACL	
			Adding Login and Logout Views	
		31.6.5	Changing Existing Views	331
			Adding permission Declarations to our view_config Decorators	331
			Adding the login.pt Template	
			Change view.pt and edit.pt	
		31.6.9	Seeing Our Changes To views.py and our Templates	334

	31.6.10 Viewing the Application in a Browser	338
31.7		339
	31.7.1 Testing the Models	339
		339
		339
		340
	•	344
31.8	•	346
		347
	8	347
32.2		348
	<u>1</u>	348
		349
		350
	32.2.4 Running the Tests	350
	32.2.5 Starting the Application	350
	32.2.6 Exposing Test Coverage Information	351
	32.2.7 Visit the Application in a Browser	352
	32.2.8 Decisions the pyramid_routesalchemy Scaffold Has Made For You	352
32.3	Basic Layout	352
	32.3.1 App Startup withinitpy	352
		355
32.4		357
		358
		359
	6 11	360
32.5		360
0210	e	361
		362
	e	366
		368
		371
		373
32.6		373
52.0		374
		374 377
	0 111	378
	6 6 6	379
		380
		381
	32.6.7 Seeing Our Changes To views.py and our Templates	
	32.6.8 Viewing the Application in a Browser	386

	 32.7 Adding Tests 32.7.1 Testing the Models 32.7.2 Testing the Views 32.7.3 Functional tests 32.7.4 Viewing the results of all our edits to tests.py 32.7.5 Running the Tests 32.8 Distributing Your Application 	387 387
33	Converting a repoze.bfg Application to Pyramid	397
34	Running Pyramid on Google's App Engine 34.1 Zipping Files Via Pip	401 404
35	Running a Pyramid Application under mod_wsgi	407
II	I API Reference	411
36	pyramid.authorization	413
37	pyramid.authentication37.1 Authentication Policies37.2 Helper Classes	415 415 418
38	pyramid.chameleon_text	421
39	pyramid.chameleon_zpt	423
40	pyramid.config	425
41	pyramid.events 41.1 Functions 41.2 Event Types	455 455 456
42	pyramid.exceptions	459
43	pyramid.httpexceptions 43.1 HTTP Exceptions	461 461
44	pyramid.i18n	473
45	pyramid.interfaces 45.1 Event-Related Interfaces 45.2 Other Interfaces	477 477 479
46	pyramid.location	491

47	pyramid.paster	493
48	pyramid.registry	495
49	pyramid.renderers	497
50	pyramid.request	501
51	pyramid.response	521
52	pyramid.scripting	527
	pyramid.security53.1 Authentication API Functions53.2 Authorization API Functions53.3 Constants53.4 Return Values	529 529 530 531 531
54	pyramid.settings	533
55	pyramid.testing	535
56	pyramid.threadlocal	539
57	pyramid.traversal	541
58	pyramid.url	549
59	pyramid.view	557
60	pyramid.wsgi	561
IV	Glossary and Index	563
Glo	ossary	565
Ind	lex	579

Front Matter

COPYRIGHT, TRADEMARKS, AND ATTRIBUTIONS

The Pyramid Web Application Development Framework, Version 1.1

by Chris McDonough

Copyright © 2008-2011, Agendaless Consulting.

ISBN-10: 0615445675

ISBN-13: 978-0615445670

First print publishing: February, 2011

All rights reserved. This material may be copied or distributed only subject to the terms and conditions set forth in the Creative Commons Attribution-Noncommercial-Share Alike 3.0 United States License. You must give the original author credit. You may not use this work for commercial purposes. If you alter, transform, or build upon this work, you may distribute the resulting work only under the same or similar license to this one.

While the Pyramid documentation is offered under the Creative Commons Attribution-Nonconmmercial-Share Alike 3.0 United States License, the Pyramid *software* is offered under a less restrictive (BSD-like) license.

All terms mentioned in this book that are known to be trademarks or service marks have been appropriately capitalized. However, use of a term in this book should not be regarded as affecting the validity of any trademark or service mark.

Every effort has been made to make this book as complete and as accurate as possible, but no warranty or fitness is implied. The information provided is on as "as-is" basis. The author and the publisher shall have neither liability nor responsibility to any person or entity with respect to any loss or damages arising from the information contained in this book. No patent liability is assumed with respect to the use of the information contained herein.

Attributions

Editor: Casey Duncan

Contributors: Ben Bangert, Blaise Laflamme, Rob Miller, Mike Orr, Carlos de la Guardia, Paul Everitt, Tres Seaver, John Shipman, Marius Gedminas, Chris Rossi, Joachim Krebs, Xavier Spriet, Reed O'Brien, William Chambers, Charlie Choiniere, Jamaludin Ahmad, Graham Higgins, Patricio Paez, Michael Merickel, Eric Ongerth, Niall O'Higgins, Christoph Zwerschke, John Anderson, Atsushi Odagiri, Kirk Strauser, JD Navarro, Joe Dallago, Savoir-Faire Linux, Łukasz Fidosz, Christopher Lambacher, Claus Conrad, Chris Beelby, and a number of people with only psuedonyms on GitHub.

Cover Designer: Hugues Laflamme of Kemeneur.

Used with permission:

The *Request and Response Objects* chapter is adapted, with permission, from documentation originally written by Ian Bicking.

The *Much Ado About Traversal* chapter is adapted, with permission, from an article written by Rob Miller.

Print Production

The print version of this book was produced using the Sphinx documentation generation system and the LaTeX typesetting system.

Contacting The Publisher

Please send documentation licensing inquiries, translation inquiries, and other business communications to Agendaless Consulting. Please send software and other technical queries to the Pylons-devel maillist.

HTML Version and Source Code

An HTML version of this book is freely available via http://docs.pylonsproject.org

The source code for the examples used in this book are available within the Pyramid software distribution, always available via https://github.com/Pylons/pyramid

TYPOGRAPHICAL CONVENTIONS

Literals, filenames and function arguments are presented using the following style:

argument1

Warnings, which represent limitations and need-to-know information related to a topic or concept are presented in the following style:

This is a warning.

Notes, which represent additional information related to a topic or concept are presented in the following style:

This is a note.

We present Python method names using the following style:

pyramid.config.Configurator.add_view()

We present Python class names, module names, attributes and global variables using the following style:

pyramid.config.Configurator.registry

References to glossary terms are presented using the following style:

Pylons

URLs are presented using the following style:

Pylons

References to sections and chapters are presented using the following style:

Traversal

Code and configuration file blocks are presented in the following style:

```
1 def foo(abc):
2     pass
```

When a command that should be typed on one line is too long to fit on a page, the backslash \setminus is used to indicate that the following printed line should actually be part of the command:

A sidebar, which presents a concept tangentially related to content discussed on a page, is rendered like so:

This is a sidebar

Sidebar information.

AUTHOR INTRODUCTION

Welcome to "The Pyramid Web Application Framework". In this introduction, I'll describe the audience for this book, I'll describe the book content, I'll provide some context regarding the genesis of Pyramid, and I'll thank some important people.

I hope you enjoy both this book and the software it documents. I've had a blast writing both.

Audience

This book is aimed primarily at a reader that has the following attributes:

- At least a moderate amount of *Python* experience.
- A familiarity with web protocols such as HTTP and CGI.

If you fit into both of these categories, you're in the direct target audience for this book. But don't worry, even if you have no experience with Python or the web, both are easy to pick up "on the fly".

Python is an *excellent* language in which to write applications; becoming productive in Python is almost mind-blowingly easy. If you already have experience in another language such as Java, Visual Basic, Perl, Ruby, or even C/C++, learning Python will be a snap; it should take you no longer than a couple of days to become modestly productive. If you don't have previous programming experience, it will be slightly harder, and it will take a little longer, but you'd be hard-pressed to find a better "first language."

Web technology familiarity is assumed in various places within the book. For example, the book doesn't try to define common web-related concepts like "URL" or "query string." Likewise, the book describes various interactions in terms of the HTTP protocol, but it does not describe how the HTTP protocol works in detail. Like any good web framework, though, Pyramid shields you from needing to know most of the gory details of web protocols and low-level data structures. As a result, you can usually avoid becoming "blocked" while you read this book even if you don't yet deeply understand web technologies.

Book Content

This book is divided into three major parts:

Narrative Documentation

This is documentation which describes Pyramid concepts in narrative form, written in a largely conversational tone. Each narrative documentation chapter describes an isolated Pyramid concept. You should be able to get useful information out of the narrative chapters if you read them out-of-order, or when you need only a reminder about a particular topic while you're developing an application.

Tutorials

Each tutorial builds a sample application or implements a set of concepts with a sample; it then describes the application or concepts in terms of the sample. You should read the tutorials if you want a guided tour of Pyramid.

API Reference

Comprehensive reference material for every public API exposed by Pyramid. The API documentation is organized alphabetically by module name.

The Genesis of repoze.bfg

Before the end of 2010, Pyramid was known as repoze.bfg.

I wrote repoze.bfg after many years of writing applications using *Zope*. Zope provided me with a lot of mileage: it wasn't until almost a decade of successfully creating applications using it that I decided to write a different web framework. Although repoze.bfg takes inspiration from a variety of web frameworks, it owes more of its core design to Zope than any other.

The Repoze "brand" existed before repoze.bfg was created. One of the first packages developed as part of the Repoze brand was a package named repoze.zope2. This was a package that allowed Zope 2 applications to run under a *WSGI* server without modification. Zope 2 did not have reasonable WSGI support at the time.

During the development of the repoze.zope2 package, I found that replicating the Zope 2 "publisher" – the machinery that maps URLs to code – was time-consuming and fiddly. Zope 2 had evolved over many years, and emulating all of its edge cases was extremely difficult. I finished the repoze.zope2

package, and it emulates the normal Zope 2 publisher pretty well. But during its development, it became clear that Zope 2 had simply begun to exceed my tolerance for complexity, and I began to look around for simpler options.

I considered using the Zope 3 application server machinery, but it turned out that it had become more indirect than the Zope 2 machinery it aimed to replace, which didn't fulfill the goal of simplification. I also considered using Django and Pylons, but neither of those frameworks offer much along the axes of traversal, contextual declarative security, or application extensibility; these were features I had become accustomed to as a Zope developer.

I decided that in the long term, creating a simpler framework that retained features I had become accustomed to when developing Zope applications was a more reasonable idea than continuing to use any Zope publisher or living with the limitations and unfamiliarities of a different framework. The result is what is now Pyramid.

The Genesis of Pyramid

What was repoze.bfg has become Pyramid as the result of a coalition built between the *Repoze* and *Pylons* community throughout the year 2010. By merging technology, we're able to reduce duplication of effort, and take advantage of more of each others' technology.

Thanks

This book is dedicated to my grandmother, who gave me my first typewriter (a Royal), and my mother, who bought me my first computer (a VIC-20).

Thanks to the following people for providing expertise, resources, and software. Without the help of these folks, neither this book nor the software which it details would exist: Paul Everitt, Tres Seaver, Andrew Sawyers, Malthe Borch, Carlos de la Guardia, Chris Rossi, Shane Hathaway, Daniel Holth, Wichert Akkerman, Georg Brandl, Blaise Laflamme, Ben Bangert, Casey Duncan, Hugues Laflamme, Mike Orr, John Shipman, Chris Beelby, Patricio Paez, Simon Oram, Nat Hardwick, Ian Bicking, Jim Fulton, Michael Merickel, Tom Moroz of the Open Society Institute, and Todd Koym of Environmental Health Sciences.

Thanks to Guido van Rossum and Tim Peters for Python.

Special thanks to Tricia for putting up with me.

Part I

Narrative Documentation

CHAPTER

ONE

PYRAMID INTRODUCTION

Pyramid is a general, open source, Python web application development *framework*. Its primary goal is to make it easier for a Python developer to create web applications.

Frameworks vs. Libraries

A *framework* differs from a *library* in one very important way: library code is always *called* by code that you write, while a framework always *calls* code that you write. Using a set of libraries to create an application is usually easier than using a framework initially, because you can choose to cede control to library code you have not authored very selectively. But when you use a framework, you are required to cede a greater portion of control to code you have not authored: code that resides in the framework itself. You needn't use a framework at all to create a web application using Python. A rich set of libraries already exists for the platform. In practice, however, using a framework to create an application is often more practical than rolling your own via a set of libraries if the framework provides a set of facilities that fits your application requirements.

Pyramid attempts to follow follow these design and engineering principles:

- **Simplicity** Pyramid takes a "*pay only for what you eat*" approach. You can get results even if you have only a partial understanding of Pyramid. It doesn't force you to use any particular technology to produce an application, and we try to keep the core set of concepts that you need to understand to a minimum.
- **Minimalism** Pyramid tries to solve only the fundamental problems of creating a web application: the mapping of URLs to code, templating, security and serving static assets. We consider these to be the core activities that are common to nearly all web applications.

- **Documentation** Pyramid's minimalism means that it is easier for us to maintain complete and up-to-date documentation. It is our goal that no aspect of Pyramid is undocumented.
- **Speed** Pyramid is designed to provide noticeably fast execution for common tasks such as templating and simple response generation. Although "hardware is cheap", the limits of this approach become painfully evident when one finds him or herself responsible for managing a great many machines.
- **Reliability** Pyramid is developed conservatively and tested exhaustively. Where Pyramid source code is concerned, our motto is: "If it ain't tested, it's broke". Every release of Pyramid has 100% statement coverage via unit tests.

Openness As with Python, the Pyramid software is distributed under a permissive open source license.

1.1 What Is The Pylons Project?

Pyramid is a member of the collection of software published under the Pylons Project. Pylons software is written by a loose-knit community of contributors. The Pylons Project website includes details about how Pyramid relates to the Pylons Project.

1.2 Pyramid and Other Web Frameworks

The first release of Pyramid's predecessor (named repoze.bfg) was made in July of 2008. At the end of 2010, we changed the name of repoze.bfg to Pyramid. It was merged into the Pylons project as Pyramid in November of that year.

Pyramid was inspired by *Zope*, *Pylons* (version 1.0) and *Django*. As a result, Pyramid borrows several concepts and features from each, combining them into a unique web framework.

Many features of Pyramid trace their origins back to *Zope*. Like Zope applications, Pyramid applications can be easily extended: if you obey certain constraints, the application you produce can be reused, modified, re-integrated, or extended by third-party developers without forking the original application. The concepts of *traversal* and declarative security in Pyramid were pioneered first in Zope.

The Pyramid concept of *URL dispatch* is inspired by the *Routes* system used by *Pylons* version 1.0. Like Pylons version 1.0, Pyramid is mostly policy-free. It makes no assertions about which database you should use, and its built-in templating facilities are included only for convenience. In essence, it only supplies a mechanism to map URLs to *view* code, along with a set of conventions for calling those views. You are free to use third-party components that fit your needs in your applications.

The concept of *view* is used by Pyramid mostly as it would be by Django. Pyramid has a documentation culture more like Django's than like Zope's.

Like *Pylons* version 1.0, but unlike *Zope*, a Pyramid application developer may use completely imperative code to perform common framework configuration tasks such as adding a view or a route. In Zope, *ZCML* is typically required for similar purposes. In *Grok*, a Zope-based web framework, *decorator* objects and class-level declarations are used for this purpose. Pyramid supports *ZCML* and decorator-based *declarative configuration*, but does not require either. See *Application Configuration* for more information.

Also unlike *Zope* and unlike other "full-stack" frameworks such as *Django*, Pyramid makes no assumptions about which persistence mechanisms you should use to build an application. Zope applications are typically reliant on *ZODB*; Pyramid allows you to build *ZODB* applications, but it has no reliance on the ZODB software. Likewise, *Django* tends to assume that you want to store your application's data in a relational database. Pyramid makes no such assumption; it allows you to use a relational database but doesn't encourage or discourage the decision.

Other Python web frameworks advertise themselves as members of a class of web frameworks named model-view-controller frameworks. Insofar as this term has been claimed to represent a class of web frameworks, Pyramid also generally fits into this class.

You Say Pyramid is MVC, But Where's The Controller?

The Pyramid authors believe that the MVC pattern just doesn't really fit the web very well. In a Pyramid application, there is a resource tree, which represents the site structure, and views, which tend to present the data stored in the resource tree and a user-defined "domain model". However, no facility provided *by the framework* actually necessarily maps to the concept of a "controller" or "model". So if you had to give it some acronym, I guess you'd say Pyramid is actually an "RV" framework rather than an "MVC" framework. "MVC", however, is close enough as a general classification moniker for purposes of comparison with other web frameworks.

1. PYRAMID INTRODUCTION

CHAPTER

TWO

INSTALLING PYRAMID

2.1 Before You Install

You will need Python version 2.5 or better to run Pyramid.

Python Versions

As of this writing, Pyramid has been tested under Python 2.5.5, Python 2.6.6, and Python 2.7.2. Pyramid does not run under any version of Python before 2.5, and does not yet run under Python 3.X.

Pyramid is known to run on all popular Unix-like systems such as Linux, MacOS X, and FreeBSD as well as on Windows platforms. It is also known to run on Google's App Engine, *PyPy* (1.5), and *Jython* (2.5.2).

Pyramid installation does not require the compilation of any C code, so you need only a Python interpreter that meets the requirements mentioned.

2.1.1 If You Don't Yet Have A Python Interpreter (UNIX)

If your system doesn't have a Python interpreter, and you're on UNIX, you can either install Python using your operating system's package manager *or* you can install Python from source fairly easily on any UNIX system that has development tools.

Package Manager Method

You can use your system's "package manager" to install Python. Every system's package manager is slightly different, but the "flavor" of them is usually the same.

For example, on an Ubuntu Linux system, to use the system package manager to install a Python 2.6 interpreter, use the following command:

```
$ sudo apt-get install python2.6-dev
```

Once these steps are performed, the Python interpreter will usually be invokable via python2.6 from a shell prompt.

Source Compile Method

It's useful to use a Python interpreter that *isn't* the "system" Python interpreter to develop your software. The authors of Pyramid tend not to use the system Python for development purposes; always a self-compiled one. Compiling Python is usually easy, and often the "system" Python is compiled with options that aren't optimal for web development.

To compile software on your UNIX system, typically you need development tools. Often these can be installed via the package manager. For example, this works to do so on an Ubuntu Linux system:

```
$ sudo apt-get install build-essential
```

On Mac OS X, installing XCode has much the same effect.

Once you've got development tools installed on your system, you can install a Python 2.6 interpreter from *source*, on the same system, using the following commands:

Once these steps are performed, the Python interpreter will be invokable via \$HOME/opt/Python-2.6.4/bin/python from a shell prompt.

2.1.2 If You Don't Yet Have A Python Interpreter (Windows)

If your Windows system doesn't have a Python interpreter, you'll need to install it by downloading a Python 2.6-series interpreter executable from python.org's download section (the files labeled "Windows Installer"). Once you've downloaded it, double click on the executable and accept the defaults during the installation process. You may also need to download and install the Python for Windows extensions.

After you install Python on Windows, you may need to add the C:\Python26 directory to your environment's Path in order to make it possible to invoke Python from a command prompt by typing python. To do so, right click My Computer, select Properties -> Advanced Tab -> Environment Variables and add that directory to the end of the Path environment variable.

2.2 Installing Pyramid on a UNIX System

It is best practice to install Pyramid into a "virtual" Python environment in order to obtain isolation from any "system" packages you've got installed in your Python version. This can be done by using the *virtualenv* package. Using a virtualenv will also prevent Pyramid from globally installing versions of packages that are not compatible with your system Python.

To set up a virtualenv in which to install Pyramid, first ensure that *setuptools* is installed. Invoke import setuptools within the Python interpreter you'd like to run Pyramid under:

```
[chrism@vitaminf pyramid]$ python
Python 2.6.5 (r265:79063, Apr 29 2010, 00:31:32)
[GCC 4.4.3] on linux2
Type "help", "copyright", "credits" or "license" for more information.
>>> import setuptools
```

If running import setuptools does not raise an ImportError, it means that setuptools is already installed into your Python interpreter. If import setuptools fails, you will need to install setuptools manually. Note that above we're using a Python 2.6-series interpreter on Mac OS X; your output may differ if you're using a later Python version or a different platform.

If you are using a "system" Python (one installed by your OS distributor or a 3rd-party packager such as Fink or MacPorts), you can usually install the setuptools package by using your system's package manager. If you cannot do this, or if you're using a self-installed version of Python, you will need to install setuptools "by hand". Installing setuptools "by hand" is always a reasonable thing to do, even if your package manager already has a pre-chewed version of setuptools for installation.

To install setuptools by hand, first download ez_setup.py then invoke it using the Python interpreter into which you want to install setuptools.

2. INSTALLING PYRAMID

\$ python ez_setup.py

Once this command is invoked, setuptools should be installed on your system. If the command fails due to permission errors, you may need to be the administrative user on your system to successfully invoke the script. To remediate this, you may need to do:

```
$ sudo python ez_setup.py
```

2.2.1 Installing the virtualenv Package

Once you've got setuptools installed, you should install the *virtualenv* package. To install the *virtualenv* package into your setuptools-enabled Python interpreter, use the <code>easy_install</code> command.

\$ easy_install virtualenv

This command should succeed, and tell you that the virtualenv package is now installed. If it fails due to permission errors, you may need to install it as your system's administrative user. For example:

```
$ sudo easy_install virtualenv
```

2.2.2 Creating the Virtual Python Environment

Once the *virtualenv* package is installed in your Python, you can then create a virtual environment. To do so, invoke the following:

```
$ virtualenv --no-site-packages env
New python executable in env/bin/python
Installing setuptools.....done.
```

Using --no-site-packages when generating your virtualenv is *very important*. This flag provides the necessary isolation for running the set of packages required by Pyramid. If you do not specify --no-site-packages, it's possible that Pyramid will not install properly into the virtualenv, or, even if it does, may not run properly, depending on the packages you've already got installed into your Python's "main" site-packages dir.

If you're on UNIX, *do not* use sudo to run the virtualenv script. It's perfectly acceptable (and desirable) to create a virtualenv as a normal user.

You should perform any following commands that mention a "bin" directory from within the env virtualenv dir.

2.2.3 Installing Pyramid Into the Virtual Python Environment

After you've got your env virtualenv installed, you may install Pyramid itself using the following commands from within the virtualenv (env) directory you created in the last step:

```
$ cd env
$ bin/easy_install pyramid
```

The easy_install command will take longer than the previous ones to complete, as it downloads and installs a number of dependencies.

2.3 Installing Pyramid on a Windows System

- 1. Install, or find Python 2.6 for your system.
- 2. Install the Python for Windows extensions. Make sure to pick the right download for Python 2.6 and install it using the same Python installation from the previous step.
- 3. Install latest *setuptools* distribution into the Python you obtained/installed/found in the step above: download ez_setup.py and run it using the python interpreter of your Python 2.6 installation using a command prompt:

c:\> c:\Python26\python ez_setup.py

4. Use that Python's *bin/easy_install* to install *virtualenv*:

c:\> c:\Python26\Scripts\easy_install virtualenv

5. Use that Python's virtualenv to make a workspace:

c:\> c:\Python26\Scripts\virtualenv --no-site-packages env

6. Switch to the env directory:

c:\> cd env

- 7. (Optional) Consider using Scripts\activate.bat to make your shell environment wired to use the virtualenv.
- 8. Use easy_install pointed at the "current" index to get Pyramid and its direct dependencies installed:

c:\env> Scripts\easy_install pyramid

2.4 Installing Pyramid on Google App Engine

Running Pyramid on Google's App Engine documents the steps required to install a Pyramid application on Google App Engine.

2.5 Installing Pyramid on Jython

Pyramid is known to work under *Jython* version 2.5.1. Install *Jython*, and then follow the installation steps for Pyramid on your platform described in one of the sections entitled *Installing Pyramid on a UNIX System* or *Installing Pyramid on a Windows System* above, replacing the python command with jython as necessary. The steps are exactly the same except you should use the jython command name instead of the python command name.

One caveat exists to using Pyramid under Jython: the *Chameleon* templating engine does not work on Jython. However, the *Mako* templating system, which is also included with Pyramid, does work under Jython; use it instead.

2.6 What Gets Installed

When you easy_install Pyramid, various Zope libraries, various Chameleon libraries, WebOb, Paste, PasteScript, and PasteDeploy libraries are installed.

Additionally, as chronicled in *Creating a Pyramid Project*, scaffolds will be registered, which make it easy to start a new Pyramid project.

CHAPTER

THREE

APPLICATION CONFIGURATION

Most people already understand "configuration" as settings that influence the operation of an application. For instance, it's easy to think of the values in a .ini file parsed at application startup time as "configuration". However, if you're reasonably open-minded, it's easy to think of *code* as configuration too. Since Pyramid, like most other web application platforms, is a *framework*, it calls into code that you write (as opposed to a *library*, which is code that exists purely for you to call). The act of plugging application code that you've written into Pyramid is also referred to within this documentation as "configuration"; you are configuring Pyramid to call the code that makes up your application.

There are two ways to configure a Pyramid application: *imperative configuration* and *declarative configuration*. Both are described below.

3.1 Imperative Configuration

"Imperative configuration" just means configuration done by Python statements, one after the next. Here's one of the simplest Pyramid applications, configured imperatively:

```
from paste.httpserver import serve
1
  from pyramid.config import Configurator
2
  from pyramid.response import Response
3
4
  def hello_world(request):
5
      return Response('Hello world!')
6
7
  if __name__ == '__main__':
8
      config = Configurator()
9
      config.add_view(hello_world)
10
      app = config.make_wsgi_app()
11
      serve(app, host='0.0.0.0')
12
```

We won't talk much about what this application does yet. Just note that the "configuration' statements take place underneath the if ____name___ == '___main___': stanza in the form of method calls on a *Configurator* object (e.g. config.add_view(...)). These statements take place one after the other, and are executed in order, so the full power of Python, including conditionals, can be employed in this mode of configuration.

3.2 Declarative Configuration

It's sometimes painful to have all configuration done by imperative code, because often the code for a single application may live in many files. If the configuration is centralized in one place, you'll need to have at least two files open at once to see the "big picture": the file that represents the configuration, and the file that contains the implementation objects referenced by the configuration. To avoid this, Pyramid allows you to insert *configuration decoration* statements very close to code that is referred to by the declaration itself. For example:

```
from pyramid.response import Response
from pyramid.view import view_config

deview_config(name='hello', request_method='GET')
def hello(request):
    return Response('Hello')
```

The mere existence of configuration decoration doesn't cause any configuration registration to be performed. Before it has any effect on the configuration of a Pyramid application, a configuration decoration within application code must be found through a process known as a *scan*.

For example, the pyramid.view.view_config decorator in the code example above adds an attribute to the hello function, making it available for a *scan* to find it later.

A *scan* of a *module* or a *package* and its subpackages for decorations happens when the pyramid.config.Configurator.scan() method is invoked: scanning implies searching for configuration declarations in a package and its subpackages. For example:

```
Starting A Scan
```

```
1
  from paste.httpserver import serve
  from pyramid.response import Response
2
  from pyramid.view import view_config
3
4
  @view_config()
5
  def hello(request):
6
      return Response('Hello')
7
8
  if __name__ == '__main__':
9
      from pyramid.config import Configurator
10
      config = Configurator()
11
      config.scan()
12
      app = config.make_wsgi_app()
13
      serve(app, host='0.0.0.0')
14
```

The scanning machinery imports each module and subpackage in a package or module recursively, looking for special attributes attached to objects defined within a module. These special attributes are typically attached to code via the use of a *decorator*. For example, the view_config decorator can be attached to a function or instance method.

Once scanning is invoked, and *configuration decoration* is found by the scanner, a set of calls are made to a *Configurator* on your behalf: these calls replace the need to add imperative configuration statements that don't live near the code being configured.

The combination of *configuration decoration* and the invocation of a *scan* is collectively known as *declar-ative configuration*.

In the example above, the scanner translates the arguments to view_config into a call to the pyramid.config.Configurator.add_view() method, effectively:

```
config.add_view(hello)
```

3.3 Summary

There are two ways to configure a Pyramid application: declaratively and imperatively. You can choose the mode you're most comfortable with; both are completely equivalent. Examples in this documentation will use both modes interchangeably.

3. APPLICATION CONFIGURATION

CHAPTER

FOUR

CREATING YOUR FIRST PYRAMID APPLICATION

In this chapter, we will walk through the creation of a tiny Pyramid application. After we're finished creating the application, we'll explain in more detail how it works.

4.1 Hello World, Goodbye World

Here's one of the very simplest Pyramid applications:

```
from pyramid.config import Configurator
1
2
  from pyramid.response import Response
  from paste.httpserver import serve
3
4
  def hello_world(request):
5
      return Response('Hello world!')
6
7
  def goodbye_world(request):
8
      return Response('Goodbye world!')
9
10
  if __name__ == '__main__':
11
      config = Configurator()
12
      config.add_view(hello_world)
13
      config.add_view(goodbye_world, name='goodbye')
14
      app = config.make_wsgi_app()
15
      serve(app, host='0.0.0.0')
16
```

When this code is inserted into a Python script named helloworld.py and executed by a Python interpreter which has the Pyramid software installed, an HTTP server is started on TCP port 8080:

```
$ python helloworld.py
serving on 0.0.0.0:8080 view at http://127.0.0.1:8080
```

When port 8080 is visited by a browser on the root URL (/), the server will simply serve up the text "Hello world!" When visited by a browser on the URL /goodbye, the server will serve up the text "Goodbye world!"

Press Ctrl-C to stop the application.

Now that we have a rudimentary understanding of what the application does, let's examine it piece-bypiece.

4.1.1 Imports

The above helloworld.py script uses the following set of import statements:

```
1 from pyramid.config import Configurator
2 from pyramid.response import Response
3 from paste.httpserver import serve
```

The script imports the Configurator class from the pyramid.config module. An instance of the Configurator class is later used to configure your Pyramid application.

The script uses the pyramid.response.Response class later in the script to create a *response* object.

Like many other Python web frameworks, Pyramid uses the WSGI protocol to connect an application and a web server together. The paste.httpserver server is used in this example as a WSGI server for convenience, as the paste package is a dependency of Pyramid itself.

4.1.2 View Callable Declarations

The above script, beneath its set of imports, defines two functions: one named hello_world and one named goodbye_world.

```
1 def hello_world(request):
2 return Response('Hello world!')
3 
4 def goodbye_world(request):
5 return Response('Goodbye world!')
```

These functions don't do anything very difficult. Both functions accept a single argument (request). The hello_world function does nothing but return a response instance with the body Hello world!. The goodbye_world function returns a response instance with the body Goodbye world!.

Each of these functions is known as a *view callable*. A view callable accepts a single argument, request. It is expected to return a *response* object. A view callable doesn't need to be a function; it can be represented via another type of object, like a class or an instance, but for our purposes here, a function serves us well.

A view callable is always called with a *request* object. A request object is a representation of an HTTP request sent to Pyramid via the active *WSGI* server.

A view callable is required to return a *response* object because a response object has all the information necessary to formulate an actual HTTP response; this object is then converted to text by the upstream *WSGI* server and sent back to the requesting browser. To return a response, each view callable creates an instance of the Response class. In the hello_world function, the string 'Hello world!' is passed to the Response constructor as the *body* of the response. In the goodbye_world function, the string 'Goodbye world!' is passed.

As we'll see in later chapters, returning a literal *response* object from a view callable is not always required; we can instead use a *renderer* in our view configurations. If we use a renderer, our view callable is allowed to return a value that the renderer understands, and the renderer generates a response on our behalf.

4.1.3 Application Configuration

In the above script, the following code represents the *configuration* of this simple application. The application is configured using the previously defined imports and function definitions, placed within the confines of an if statement:

if name == 'main':
config = Configurator()
config.add_view(hello_world)
<pre>config.add_view(goodbye_world, name='goodbye')</pre>
app = config.make_wsgi_app()
serve(app, host='0.0.0.0')

Let's break this down this piece-by-piece.

4.1.4 Configurator Construction

```
1 if __name__ == '__main__':
2 config = Configurator()
```

The if __name__ == '__main__': line in the code sample above represents a Python idiom: the code inside this if clause is not invoked unless the script containing this code is run directly from the command line. For example, if the file named helloworld.py contains the entire script body, the code within the if statement will only be invoked when python helloworld.py is executed from the operating system command line.

helloworld.py in this case is a Python *module*. Using the if clause is necessary – or at least best practice – because code in any Python module may be imported by another Python module. By using this idiom, the script is indicating that it does not want the code within the if statement to execute if this module is imported; the code within the if block should only be run during a direct script execution.

The config = Configurator() line above creates an instance of the Configurator class. The resulting config object represents an API which the script uses to configure this particular Pyramid application. Methods called on the Configurator will cause registrations to be made in a *application registry* associated with the application.

4.1.5 Adding Configuration

```
1 config.add_view(hello_world)
2 config.add_view(goodbye_world, name='goodbye')
```

Each of these lines calls the pyramid.config.Configurator.add_view() method. The add_view method of a configurator registers a *view configuration* within the *application registry*. A *view configuration* represents a set of circumstances related to the *request* that will cause a specific *view callable* to be invoked. This "set of circumstances" is provided as one or more keyword arguments to the add_view method. Each of these keyword arguments is known as a view configuration predicate.

The line config.add_view (hello_world) registers the hello_world function as a view callable. The add_view method of a Configurator must be called with a view callable object or a *dotted Python name* as its first argument, so the first argument passed is the hello_world function. This line calls add_view with a *default* value for the *predicate* argument, named name. The name predicate defaults to a value equalling the empty string ("). This means that we're instructing Pyramid to invoke the hello_world view callable when the *view name* is the empty string. We'll learn in later chapters what a *view name* is, and under which circumstances a request will have a view name that is the empty string; in this particular application, it means that the hello_world view callable will be invoked when the root URL / is visited by a browser.

The line config.add_view(goodbye_world, name='goodbye') registers the goodbye_world function as a view callable. The line calls add_view with the view callable as the first required positional argument, and a *predicate* keyword argument name with the value 'goodbye'. The name argument supplied in this *view configuration* implies that only a request that has a *view name* of goodbye should cause the goodbye_world view callable to be invoked. In this particular application, this means that the goodbye_world view callable will be invoked when the URL /goodbye is visited by a browser.

Each invocation of the add_view method registers a *view configuration*. Each *predicate* provided as a keyword argument to the add_view method narrows the set of circumstances which would cause the view configuration's callable to be invoked. In general, a greater number of predicates supplied along with a view configuration will more strictly limit the applicability of its associated view callable. When Pyramid processes a request, the view callable with the *most specific* view configuration (the view configuration that matches the most specific set of predicates) is always invoked.

In this application, Pyramid chooses the most specific view callable based only on view *predicate* applicability. The ordering of calls to add_view() is never very important. We can register goodbye_world first and hello_world second; Pyramid will still give us the most specific callable when a request is dispatched to it.

4.1.6 WSGI Application Creation

app = config.make_wsgi_app()

After configuring views and ending configuration, the script creates a WSGI *application* via the pyramid.config.Configurator.make_wsgi_app() method. A call to make_wsgi_app implies that all configuration is finished (meaning all method calls to the configurator which set up views, and various other configuration settings have been performed). The make_wsgi_app method returns a *WSGI* application object that can be used by any WSGI server to present an application to a requestor. *WSGI* is a protocol that allows servers to talk to Python applications. We don't discuss *WSGI* in any depth within this book, however, you can learn more about it by visiting wsgi.org.

The Pyramid application object, in particular, is an instance of a class representing a Pyramid *router*. It has a reference to the *application registry* which resulted from method calls to the configurator used to configure it. The *router* consults the registry to obey the policy choices made by a single application. These policy choices were informed by method calls to the *Configurator* made earlier; in our case, the only policy choices made were implied by two calls to its add_view method.

4.1.7 WSGI Application Serving

```
serve(app, host='0.0.0.0')
```

Finally, we actually serve the application to requestors by starting up a WSGI server. We happen to use the paste.httpserver.serve() WSGI server runner, passing it the app object (a *router*) as the application we wish to serve. We also pass in an argument host=='0.0.0.0', meaning "listen on all TCP interfaces." By default, the Paste HTTP server listens only on the 127.0.0.1 interface, which is problematic if you're running the server on a remote system and you wish to access it with a web browser from a local system. We don't specify a TCP port number to listen on; this means we want to use the default TCP port, which is 8080.

When this line is invoked, it causes the server to start listening on TCP port 8080. It will serve requests forever, or at least until we stop it by killing the process which runs it (usually by pressing Ctrl-C in the terminal we used to start it).

4.1.8 Conclusion

Our hello world application is one of the simplest possible Pyramid applications, configured "imperatively". We can see that it's configured imperatively because the full power of Python is available to us as we perform configuration tasks.

4.2 References

For more information about the API of a Configurator object, see Configurator.

For more information about view configuration, see View Configuration.

CHAPTER

FIVE

CREATING A PYRAMID PROJECT

As we saw in *Creating Your First Pyramid Application*, it's possible to create a Pyramid application completely manually. However, it's usually more convenient to use a *scaffold* to generate a basic Pyramid *project*.

A project is a directory that contains at least one Python *package*. You'll use a scaffold to create a project, and you'll create your application logic within a package that lives inside the project. Even if your application is extremely simple, it is useful to place code that drives the application within a package, because: 1) a package is more easily extended with new code and 2) an application that lives inside a package can also be distributed more easily than one which does not live within a package.

Pyramid comes with a variety of scaffolds that you can use to generate a project. Each scaffold makes different configuration assumptions about what type of application you're trying to construct.

These scaffolds are rendered using the *PasteDeploy* paster script.

5.1 Scaffolds Included with Pyramid

The convenience scaffolds included with Pyramid differ from each other on a number of axes:

- the persistence mechanism they offer (no persistence mechanism, ZODB, or SQLAlchemy).
- the mechanism they use to map URLs to code (traversal or URL dispatch).
- whether or not the pyramid_beaker library is relied upon as the sessioning implementation (as opposed to no sessioning or default sessioning).

The included scaffolds are these:

pyramid_starter URL mapping via *traversal* and no persistence mechanism.

pyramid_zodb URL mapping via *traversal* and persistence via ZODB.

pyramid_routesalchemy URL mapping via URL dispatch and persistence via SQLAlchemy

pyramid_alchemy URL mapping via traversal and persistence via SQLAlchemy

• At this time, each of these scaffolds uses the *Chameleon* templating system, which is incompatible with Jython. To use scaffolds to build applications which will run on Jython, you can try the pyramid_jinja2_starter scaffold which ships as part of the *pyramid_jinja2* package. You can also just use any above scaffold and replace the Chameleon template it includes with a *Mako* analogue.

Rather than use any of the above scaffolds, Pylons 1 users may feel more comfortable installing the *Akhet* development environment, which provides a scaffold named akhet. This scaffold configures a Pyramid application in a "Pylons-esque" way, including the use of a *view handler* to map URLs to code (a handler is much like a Pylons "controller").

5.2 Creating the Project

In *Installing Pyramid*, you created a virtual Python environment via the virtualenv command. To start a Pyramid *project*, use the paster facility installed within the virtualenv. In *Installing Pyramid* we called the virtualenv directory env; the following command assumes that our current working directory is that directory.

We'll choose the pyramid_starter scaffold for this purpose.

```
$ bin/paster create -t pyramid_starter
```

The above command uses the paster command to create a project using the pyramid_starter scaffold. The paster create command creates project from a scaffold. To use a different scaffold, such as pyramid_routesalchemy, you'd just change the last argument. For example:

\$ bin/paster create -t pyramid_routesalchemy

paster create will ask you a single question: the *name* of the project. You should use a string without spaces and with only letters in it. Here's sample output from a run of paster create for a project we name MyProject:

```
$ bin/paster create -t pyramid_starter
Selected and implied templates:
    pyramid#pyramid_starter pyramid starter project
Enter project name: MyProject
Variables:
    egg: MyProject
    package: myproject
    project: MyProject
Creating template pyramid
Creating directory ./MyProject
# ... more output ...
Running /Users/chrism/projects/pyramid/bin/python setup.py egg_info
```

● You can skip the interrogative question about a project name during paster create by adding the project name to the command line, e.g. paster create -t pyramid_starter MyProject.

Vou may encounter an error when using paster create if a dependent Python package is not installed. This will result in a traceback ending in pkg_resources.DistributionNotFound: <package name>. Simply run bin/easy_install, with the missing package name from the error message to work around this issue.

As a result of invoking the paster create command, a project is created in a directory named MyProject. That directory is a *project* directory. The setup.py file in that directory can be used to distribute your application, or install your application for deployment or development.

A *PasteDeploy* .ini file named development.ini will be created in the project directory. You will use this .ini file to configure a server, to run your application, and to debug your application. It sports configuration that enables an interactive debugger and settings optimized for development.

5. CREATING A PYRAMID PROJECT

Another *PasteDeploy* .ini file named production.ini will also be created in the project directory. It sports configuration that disables any interactive debugger (to prevent inappropriate access and disclosure), and turns off a number of debugging settings. You can use this file to put your application into production, and you can modify it to do things like send email when an exception occurs.

The MyProject project directory contains an additional subdirectory named myproject (note the case difference) representing a Python *package* which holds very simple Pyramid sample code. This is where you'll edit your application's Python code and templates.

5.3 Installing your Newly Created Project for Development

To install a newly created project for development, you should cd to the newly created project directory and use the Python interpreter from the *virtualenv* you created during *Installing Pyramid* to invoke the command python setup.py develop

The file named setup.py will be in the root of the paster-generated project directory. The python you're invoking should be the one that lives in the bin directory of your virtual Python environment. Your terminal's current working directory *must* the the newly created project directory. For example:

\$../bin/python setup.py develop

Elided output from a run of this command is shown below:

```
$ ../bin/python setup.py develop
...
Finished processing dependencies for MyProject==0.0
```

This will install a *distribution* representing your project into the interpreter's library set so it can be found by import statements and by *PasteDeploy* commands such as paster serve, paster pshell, paster proutes and paster pviews.

5.4 Running The Tests For Your Application

To run unit tests for your application, you should invoke them using the Python interpreter from the *virtualenv* you created during *Installing Pyramid* (the python command that lives in the bin directory of your virtualenv):

\$../bin/python setup.py test -q

Here's sample output from a test run:

```
$ python setup.py test -q
running test
running egg_info
writing requirements to MyProject.egg-info/requires.txt
writing MyProject.egg-info/PKG-INFO
writing top-level names to MyProject.egg-info/top_level.txt
writing dependency_links to MyProject.egg-info/dependency_links.txt
writing entry points to MyProject.egg-info/soURCES.txt'
reading manifest file 'MyProject.egg-info/SOURCES.txt'
writing manifest file 'MyProject.egg-info/SOURCES.txt'
running build_ext
...
Ran 1 test in 0.108s
OK
```

U The -q option is passed to the setup.py test command to limit the output to a stream of dots. If you don't pass -q, you'll see more verbose test result output (which normally isn't very useful).

The tests themselves are found in the tests.py module in your paster create -generated project. Within a project generated by the pyramid_starter scaffold, a single sample test exists.

5.5 Running The Project Application

Once a project is installed for development, you can run the application it represents using the paster serve command against the generated configuration file. In our case, this file is named development.ini:

\$../bin/paster serve development.ini

Here's sample output from a run of paster serve:

```
$ ../bin/paster serve development.ini
Starting server in PID 16601.
serving on 0.0.0.0:6543 view at http://127.0.0.1:6543
```

By default, Pyramid applications generated from a scaffold will listen on TCP port 6543. You can shut down a server started this way by pressing Ctrl-C.

During development, it's often useful to run paster serve using its --reload option. When --reload is passed to paster serve, changes to any Python module your project uses will cause the server to restart. This typically makes development easier, as changes to Python code made within a Pyramid application is not put into effect until the server restarts.

For example:

```
$ ../bin/paster serve development.ini --reload
Starting subprocess with file monitor
Starting server in PID 16601.
serving on 0.0.0.0:6543 view at http://127.0.0.1:6543
```

For more detailed information about the startup process, see *Startup*. For more information about environment variables and configuration file settings that influence startup and runtime behavior, see *Environment Variables and .ini File Settings*.

5.6 Viewing the Application

Once your application is running via paster serve, you may visit http://localhost:6543/ in your browser. You will see something in your browser like what is displayed in the following image:

The Pyramid Web Application Development Framework		
	n application generated by on development framework. Pyramid links Pylons Website Narrative Documentation API Documentation Tutorials Change History Sample Applications Support and Development IRC Channel	

© Copyright 2008-2010, Agendaless Consulting.

This is the page shown by default when you visit an unmodified paster create -generated pyramid_starter application in a browser.

Using an Alternate WSGI Server

The code generated by a Pyramid scaffold assumes that you will be using the paster serve command to start your application while you do development. However, paster serve is by no means the only way to start up and serve a Pyramid application. As we saw in *Creating Your First Pyramid Application*, paster serve needn't be invoked at all to run a Pyramid application. The use of paster serve to run a Pyramid application is purely conventional based on the output of its scaffold.

Any WSGI server is capable of running a Pyramid application. Some WSGI servers don't require the *PasteDeploy* framework's paster serve command to do server process management at all. Each WSGI server has its own documentation about how it creates a process to run an application, and there are many of them, so we cannot provide the details for each here. But the concepts are largely the same, whatever server you happen to use.

One popular production alternative to a paster-invoked server is *mod_wsgi*. You can also use *mod_wsgi* to serve your Pyramid application using the Apache web server rather than any "pure-Python" server that is started as a result of paster serve. See *Running a Pyramid Application under mod_wsgi* for details. However, it is usually easier to *develop* an application using a paster serve -invoked webserver, as exception and debugging output will be sent to the console.

5.7 The Project Structure

The pyramid_starter scaffold generated a *project* (named MyProject), which contains a Python *package*. The package is *also* named myproject, but it's lowercased; the scaffold generates a project which contains a package that shares its name except for case.

All Pyramid paster -generated projects share a similar structure. The MyProject project we've generated has the following directory structure:

```
MyProject/
|-- CHANGES.txt
|-- development.ini
|-- MANIFEST.in
|-- myproject
    |-- __init__.py
    |-- resources.py
    |-- static
|-- favicon.ico
        |-- logo.png
'-- pylons.css
|-- templates
'-- mytemplate.pt
```

```
| |-- tests.py
| `-- views.py
|-- production.ini
|-- README.txt
|-- setup.cfg
`-- setup.py
```

5.8 The MyProject Project

The MyProject *project* directory is the distribution and deployment wrapper for your application. It contains both the myproject *package* representing your application as well as files used to describe, run, and test your application.

- 1. CHANGES.txt describes the changes you've made to the application. It is conventionally written in *ReStructuredText* format.
- 2. README.txt describes the application in general. It is conventionally written in *ReStructuredText* format.
- 3. development.ini is a *PasteDeploy* configuration file that can be used to execute your application during development.
- 4. production.ini is a *PasteDeploy* configuration file that can be used to execute your application in a production configuration.
- 5. setup.cfg is a *setuptools* configuration file used by setup.py.
- 6. MANIFEST.in is a *distutils* "manifest" file, naming which files should be included in a source distribution of the package when python setup.py sdist is run.
- 7. setup.py is the file you'll use to test and distribute your application. It is a standard *setuptools* setup.py file.

5.8.1 development.ini

The development.ini file is a *PasteDeploy* configuration file. Its purpose is to specify an application to run when you invoke paster serve, as well as the deployment settings provided to that application.

The generated development.ini file looks like so:

```
[app:MyProject]
use = egg:MyProject
reload_templates = true
debug_authorization = false
debug_notfound = false
debug_routematch = false
debug_templates = true
default_locale_name = en
[pipeline:main]
pipeline =
    egg:WebError#evalerror
    MyProject
[server:main]
use = eqq:Paste#http
host = 0.0.0.0
port = 6543
# Begin logging configuration
[loggers]
keys = root, myproject
[handlers]
keys = console
[formatters]
keys = generic
[logger_root]
level = INFO
handlers = console
[logger_myproject]
level = DEBUG
handlers =
qualname = myproject
[handler console]
class = StreamHandler
args = (sys.stderr,)
level = NOTSET
formatter = generic
[formatter_generic]
```

format = %(asctime)s %(levelname)-5.5s [%(name)s] %(message)s
End logging configuration

This file contains several "sections" including [app:MyProject], [pipeline:main], [server:main] and several other sections related to logging configuration.

The [app:MyProject] section represents configuration for your application. This section name represents the MyProject application (and it's an app -lication, thus app:MyProject)

The use setting is required in the [app:MyProject] section. The use setting points at a *setuptools entry point* named MyProject (the egg: prefix in egg:MyProject indicates that this is an entry point *URI* specifier, where the "scheme" is "egg"). egg:MyProject is actually shorthand for a longer spelling: egg:MyProject#main. The #main part is omitted for brevity, as it is the default.

setuptools Entry Points and PasteDeploy .ini Files

This part of configuration can be confusing so let's try to clear things up a bit. Take a look at the generated setup.py file for this project. Note that the entry_point line in setup.py points at a string which looks a lot like an .ini file. This string representation of an .ini file has a section named [paste.app_factory]. Within this section, there is a key named main (the entry point name) which has a value myproject:main. The key main is what our egg:MyProject#main value of the use section in our config file is pointing at (although it is actually shortened to egg:MyProject there). The value represents a *dotted Python name* path, which refers to a callable in our myproject package's __init__.py module. In English, this entry point can thus be referred to as a "Paste application factory in the MyProject project which has the entry point named main where the entry point refers to a main function in the mypackage module". If indeed if you open up the __init__.py module generated within the myproject package, you'll see a main function. This is the function called by *PasteDeploy* when the paster serve command is invoked against our application. It accepts a global configuration object and *returns* an instance of our application.

The use setting is the only setting *required* in the [app:MyProject] section unless you've changed the callable referred to by the egg:MyProject entry point to accept more arguments: other settings you add to this section are passed as keywords arguments to the callable represented by this entry point (main in our __init__.py module). You can provide startup-time configuration parameters to your application by adding more settings to this section.

The reload_templates setting in the [app:MyProject] section is a Pyramid -specific setting which is passed into the framework. If it exists, and its value is true, *Chameleon* and *Mako* template

5. CREATING A PYRAMID PROJECT

changes will not require an application restart to be detected. See *Automatically Reloading Templates* for more information.

The debug_templates setting in the [app:MyProject] section is a Pyramid -specific setting which is passed into the framework. If it exists, and its value is true, *Chameleon* template exceptions will contained more detailed and helpful information about the error than when this value is false. See *Nicer Exceptions in Chameleon Templates* for more information.

The reload_templates and debug_templates options should be turned off for production applications, as template rendering is slowed when either is turned on.

Various other settings may exist in this section having to do with debugging or influencing runtime behavior of a Pyramid application. See *Environment Variables and .ini File Settings* for more information about these settings.

[pipeline:main], has the name main signifying that this is the default 'application' (although it's actually a pipeline of middleware and an application) run by paster serve when it is invoked against this configuration file. The name main is a convention used by PasteDeploy signifying that it is the default application.

The [server:main] section of the configuration file configures a WSGI server which listens on TCP port 6543. It is configured to listen on all interfaces (0.0.0.0). The Paste#http server will create a new thread for each request.

I In general, Pyramid applications generated from scaffolds should be threading-aware. It is not required that a Pyramid application be nonblocking as all application code will run in its own thread, provided by the server you're using.

The sections that live between the markers # Begin logging configuration and # End logging configuration represent Python's standard library logging module configuration for your application. The sections between these two markers are passed to the logging module's config file configuration engine when the paster serve or paster pshell commands are executed. The default configuration sends application logging output to the standard error output of your terminal.

See the *PasteDeploy* documentation for more information about other types of things you can put into this .ini file, such as other applications, *middleware* and alternate *WSGI* server implementations.

Vou can add a [DEFAULT] section to your development.ini file. Such a section should consists of global parameters that are shared by all the applications, servers and *middleware* defined within the configuration file. The values in a [DEFAULT] section will be passed to your application's main function as global_config (see the reference to the main function in __init__.py).

5.8.2 production.ini

The production.ini file is a *PasteDeploy* configuration file with a purpose much like that of development.ini. However, it disables the WebError interactive debugger, replacing it with a logger which outputs exception messages to stderr by default. It also turns off template development options such that templates are not automatically reloaded when changed, and turns off all debugging options. You can use this file instead of development.ini when you put your application into production.

5.8.3 MANIFEST.in

The MANIFEST.in file is a *distutils* configuration file which specifies the non-Python files that should be included when a *distribution* of your Pyramid project is created when you run python setup.py sdist. Due to the information contained in the default MANIFEST.in, an sdist of your Pyramid project will include .txt files, .ini files, .rst files, graphics files, and template files, as well as .py files. See http://docs.python.org/distutils/sourcedist.html#the-manifest-in-template for more information about the syntax and usage of MANIFEST.in.

5.8.4 setup.py

The setup.py file is a *setuptools* setup file. It is meant to be run directly from the command line to perform a variety of functions, such as testing your application, packaging, and distributing your application.

U setup.py is the defacto standard which Python developers use to distribute their reusable code. You can read more about setup.py files and their usage in the Setuptools documentation.

Our generated setup.py looks like this:

```
import os
import os
from setuptools import setup, find_packages
kere = os.path.abspath(os.path.dirname(__file__))
README = open(os.path.join(here, 'README.txt')).read()
CHANGES = open(os.path.join(here, 'CHANGES.txt')).read()
requires = ['pyramid', 'WebError']
setup(name='MyProject',
```

```
12
         version='0.0',
         description='MyProject',
13
         long_description=README + '\n\n' + CHANGES,
14
         classifiers=[
15
           "Programming Language :: Python",
16
           "Framework :: Pylons",
17
           "Topic :: Internet :: WWW/HTTP",
18
           "Topic :: Internet :: WWW/HTTP :: WSGI :: Application",
19
           ],
20
         author='',
21
         author_email='',
22
         url='',
23
         keywords='web pyramid pylons',
24
         packages=find_packages(),
25
         include_package_data=True,
26
         zip_safe=False,
27
         install_requires=requires,
28
         tests_require=requires,
29
         test_suite="myproject",
30
         entry_points = """\
31
         [paste.app factory]
32
         main = myproject:main
33
         .....
34
         paster_plugins=['pyramid'],
35
         )
36
```

The setup.py file calls the setuptools setup function, which does various things depending on the arguments passed to setup.py on the command line.

Within the arguments to this function call, information about your application is kept. While it's beyond the scope of this documentation to explain everything about setuptools setup files, we'll provide a whirlwind tour of what exists in this file in this section.

Your application's name can be any string; it is specified in the name field. The version number is specified in the version value. A short description is provided in the description field. The long_description is conventionally the content of the README and CHANGES file appended together. The classifiers field is a list of Trove classifiers describing your application. author and author_email are text fields which probably don't need any description. url is a field that should point at your application project's URL (if any). packages=find_packages() causes all packages within the project to be found when packaging the application. include_package_data will include non-Python files when the application is packaged if those files are checked into version control. zip_safe indicates that this package is not safe to use as a zipped egg; instead it will always unpack as a directory, which is more convenient. install_requires and tests_require indicate that this package depends on the pyramid package. test_suite points at the package for our application,

which means all tests found in the package will be run when setup.py test is invoked. We examined entry_points in our discussion of the development.ini file; this file defines the main entry point that represents our project's application.

Usually you only need to think about the contents of the setup.py file when distributing your application to other people, or when versioning your application for your own use. For fun, you can try this command now:

```
$ python setup.py sdist
```

This will create a tarball of your application in a dist subdirectory named MyProject-0.1.tar.gz. You can send this tarball to other people who want to use your application.

Without the presence of a MANIFEST.in file or without checking your source code into a version control repository, setup.py sdist places only *Python source files* (files ending with a .py extension) into tarballs generated by python setup.py sdist. This means, for example, if your project was not checked into a setuptools-compatible source control system, and your project directory didn't contain a MANIFEST.in file that told the sdist machinery to include *.pt files, the myproject/templates/mytemplate.pt file would not be included in the generated tarball. Projects generated by Pyramid scaffolds include a default MANIFEST.in file. The MANIFEST.in file contains declarations which tell it to include files like *.pt, *.css and *.js in the generated tarball. If you include files with extensions other than the files named in the project's MANIFEST.in and you don't make use of a setuptools-compatible version control system, you'll need to edit the MANIFEST.in file and include the statements necessary to include your new files. See http://docs.python.org/distutils/sourcedist.html#principle for more information about how to do this.

You can also delete MANIFEST.in from your project and rely on a setuptools feature which simply causes all files checked into a version control system to be put into the generated tarball. To allow this to happen, check all the files that you'd like to be distributed along with your application's Python files into Subversion. After you do this, when you rerun setup.py sdist, all files checked into the version control system will be included in the tarball. If you don't use Subversion, and instead use a different version control system, you may need to install a setuptools add-on such as setuptools-git or setuptools-hg for this behavior to work properly.

5.8.5 setup.cfg

The setup.cfg file is a *setuptools* configuration file. It contains various settings related to testing and internationalization:

Our generated setup.cfg looks like this:

5. CREATING A PYRAMID PROJECT

```
[nosetests]
1
2 match = ^test
3 nocapture = 1
4 cover-package = myproject
s with-coverage = 1
 cover-erase = 1
6
7
8 [compile_catalog]
9 directory = myproject/locale
 domain = MyProject
10
11
 statistics = true
12
13 [extract_messages]
14 add_comments = TRANSLATORS:
 output_file = myproject/locale/MyProject.pot
15
  width = 80
16
17
18 [init_catalog]
19 domain = MyProject
20 input_file = myproject/locale/MyProject.pot
21 output_dir = myproject/locale
22
23 [update_catalog]
24 domain = MyProject
25 input_file = myproject/locale/MyProject.pot
26 output_dir = myproject/locale
27 previous = true
```

The values in the default setup file allow various commonly-used internationalization commands and testing commands to work more smoothly.

5.9 The myproject Package

The myproject *package* lives inside the MyProject *project*. It contains:

- 1. An __init__.py file signifies that this is a Python *package*. It also contains code that helps users run the application, including a main function which is used as a Paste entry point.
- 2. A resources.py module, which contains resource code.
- 3. A templates directory, which contains Chameleon (or other types of) templates.

- 4. A tests.py module, which contains unit test code for the application.
- 5. A views.py module, which contains view code for the application.

These are purely conventions established by the scaffold: Pyramid doesn't insist that you name things in any particular way. However, it's generally a good idea to follow Pyramid standards for naming, so that other Pyramid developers can get up to speed quickly on your code when you need help.

5.9.1 __init__.py

We need a small Python module that configures our application and which advertises an entry point for use by our *PasteDeploy* .ini file. This is the file named __init__.py. The presence of an __init__.py also informs Python that the directory which contains it is a *package*.

```
from pyramid.config import Configurator
1
  from myproject.resources import Root
2
3
  def main(global_config, **settings):
4
      """ This function returns a Pyramid WSGI application.
5
      .....
6
      config = Configurator(root_factory=Root, settings=settings)
7
      config.add_view('myproject.views.my_view',
8
                       context='myproject.resources.Root',
9
                       renderer='myproject:templates/mytemplate.pt')
10
      config.add_static_view('static', 'myproject:static')
11
      return config.make_wsgi_app()
12
```

- 1. Line 1 imports the *Configurator* class from pyramid.config that we use later.
- 2. Line 2 imports the Root class from myproject.resources that we use later.
- 3. Lines 4-12 define a function named main that returns a Pyramid WSGI application. This function is meant to be called by the *PasteDeploy* framework as a result of running paster serve.

Within this function, application configuration is performed.

Lines 8-10 register a "default view" (a view that has no name attribute). It is registered so that it will be found when the *context* of the request is an instance of the myproject.resources.Root class. The first argument to add_view points at a Python function that does all the work for this view, also known as a *view callable*, via a *dotted Python name*. The view declaration also names a renderer, which in this case is a template that will be used to render the result of the view callable. This particular view declaration points at myproject:template.pt, which is a *asset specification* that specifies the mytemplate.pt file within the templates directory of the myproject package. The template file it actually points to is a *Chameleon* ZPT template file.

Line 11 registers a static view, which will serve up the files from the mypackage: static *asset specification* (the static directory of the mypackage package).

Line 12 returns a WSGI application to the caller of the function (Paste).

5.9.2 views.py

Much of the heavy lifting in a Pyramid application is done by *view callables*. A *view callable* is the main tool of a Pyramid web application developer; it is a bit of code which accepts a *request* and which returns a *response*.

```
1 def my_view(request):
2     return {'project':'MyProject'}
```

This bit of code was registered as the view callable within __init__.py (via add_view). add_view said that the default URL for instances that are of the class myproject.resources.Root should run this myproject.views.my_view() function.

This view callable function is handed a single piece of information: the *request*. The *request* is an instance of the *WebOb* Request class representing the browser's request to our server.

This view returns a dictionary. When this view is invoked, a *renderer* converts the dictionary returned by the view into HTML, and returns the result as the *response*. This view is configured to invoke a renderer which uses a *Chameleon* ZPT template (mypackage:templates/my_template.pt, as specified in the __init__.py file call to add_view).

See Writing View Callables Which Use a Renderer for more information about how views, renderers, and templates relate and cooperate.

U Because our development.ini has a reload_templates = true directive indicating that templates should be reloaded when they change, you won't need to restart the application server to see changes you make to templates. During development, this is handy. If this directive had been false (or if the directive did not exist), you would need to restart the application server for each template change. For production applications, you should set your project's reload_templates to false to increase the speed at which templates may be rendered.

5.9.3 resources.py

The resources.py module provides the *resource* data and behavior for our application. Resources are objects which exist to provide site structure in applications which use *traversal* to map URLs to code. We write a class named Root that provides the behavior for the root resource.

```
1 class Root(object):
2 def __init__(self, request):
3 self.request = request
```

1. Lines 1-3 define the Root class. The Root class is a "root resource factory" function that will be called by the Pyramid *Router* for each request when it wants to find the root of the resource tree.

In a "real" application, the Root object would likely not be such a simple object. Instead, it might be an object that could access some persistent data store, such as a database. Pyramid doesn't make any assumption about which sort of data storage you'll want to use, so the sample application uses an instance of myproject.resources.Root to represent the root.

5.9.4 static

This directory contains static assets which support the mytemplate.pt template. It includes CSS and images.

5.9.5 templates/mytemplate.pt

The single *Chameleon* template exists in the project. Its contents are too long to show here, but it displays a default page when rendered. It is referenced by the call to add_view as the renderer attribute in the __init__ file. See *Writing View Callables Which Use a Renderer* for more information about renderers.

Templates are accessed and used by view configurations and sometimes by view functions themselves. See *Using Templates Directly* and *Templates Used as Renderers via Configuration*.

5.9.6 tests.py

The tests.py module includes unit tests for your application.

```
import unittest
2
  from pyramid import testing
3
4
  class ViewTests(unittest.TestCase):
5
      def setUp(self):
6
           self.config = testing.setUp()
7
8
      def tearDown(self):
9
          testing.tearDown()
10
11
      def test_my_view(self):
12
           from myproject.views import my_view
13
           request = testing.DummyRequest()
14
          info = my_view(request)
15
           self.assertEqual(info['project'], 'MyProject')
16
```

This sample tests.py file has a single unit test defined within it. This test is executed when you run python setup.py test. You may add more tests here as you build your application. You are not required to write tests to use Pyramid, this file is simply provided as convenience and example.

See Unit, Integration, and Functional Testing for more information about writing Pyramid unit tests.

5.10 Modifying Package Structure

It is best practice for your application's code layout to not stray too much from accepted Pyramid scaffold defaults. If you refrain from changing things very much, other Pyramid coders will be able to more quickly understand your application. However, the code layout choices made for you by a scaffold are in no way magical or required. Despite the choices made for you by any scaffold, you can decide to lay your code out any way you see fit.

For example, the configuration method named add_view() requires you to pass a *dotted Python name* or a direct object reference as the class or function to be used as a view. By default, the pyramid_starter scaffold would have you add view functions to the views.py module in your package. However, you might be more comfortable creating a views *directory*, and adding a single file for each view.

If your project package name was myproject and you wanted to arrange all your views in a Python subpackage within the myproject *package* named views instead of within a single views.py file, you might:

- Create a views directory inside your mypackage package directory (the same directory which holds views.py).
- *Move* the existing views.py file to a file inside the new views directory named, say, blog.py.
- Create a file within the new views directory named __init__.py (it can be empty, this just tells Python that the views directory is a *package*.

Then change the <u>__init__</u>.py of your myproject project (*not* the <u>__init__</u>.py you just created in the views directory, the one in its parent directory). For example, from something like:

```
1 config.add_view('myproject.views.my_view',
2 renderer='myproject:templates/mytemplate.pt')
```

To this:

```
1 config.add_view('myproject.views.blog.my_view',
2 renderer='myproject:templates/mytemplate.pt')
```

You can then continue to add files to the views directory, and refer to view classes or functions within those files via the dotted name passed as the first argument to add_view. For example, if you added a file named anothermodule.py to the views subdirectory, and added a view callable named my_view to it:

This pattern can be used to rearrage code referred to by any Pyramid API argument which accepts a *dotted Python name* or direct object reference.

5.11 Using the Interactive Shell

It is possible to use a Python interpreter prompt loaded with a similar configuration as would be loaded if you were running your Pyramid application via paster serve. This can be a useful debugging tool. See *The Interactive Shell* for more details.

5. CREATING A PYRAMID PROJECT

CHAPTER

SIX

URL DISPATCH

URL dispatch provides a simple way to map URLs to *view* code using a simple pattern matching language. An ordered set of patterns is checked one-by-one. If one of the patterns matches the path information associated with a request, a particular *view callable* is invoked. A view callable is a specific bit of code, defined in your application, that receives the *request* and returns a *response* object.

6.1 High-Level Operational Overview

If route configuration is present in an application, the Pyramid *Router* checks every incoming request against an ordered set of URL matching patterns present in a *route map*.

If any route pattern matches the information in the *request*, Pyramid will invoke *view lookup* to find a matching view.

If no route pattern in the route map matches the information in the *request* provided in your application, Pyramid will fail over to using *traversal* to perform resource location and view lookup.

6.2 Route Configuration

Route configuration is the act of adding a new *route* to an application. A route has a *name*, which acts as an identifier to be used for URL generation. The name also allows developers to associate a view configuration with the route. A route also has a *pattern*, meant to match against the PATH_INFO portion of a URL (the portion following the scheme and port, e.g. /foo/bar in the URL http://localhost:8080/foo/bar). It also optionally has a factory and a set of *route predicate* attributes.

6.2.1 Configuring a Route to Match a View

The pyramid.config.Configurator.add_route() method adds a single *route configuration* to the *application registry*. Here's an example:

```
# "config" below is presumed to be an instance of the
# pyramid.config.Configurator class; "myview" is assumed
# to be a "view callable" function
from views import myview
config.add_route('myroute', '/prefix/{one}/{two}')
config.add_view(myview, route_name='myroute')
```

When a *view callable* added to the configuration by way of add_view() bcomes associated with a route via its route_name predicate, that view callable will always be found and invoked when the associated route pattern matches during a request.

More commonly, you will not use any add_view statements in your project's "setup" code, instead only using add_route statements using a *scan* for to associate view callables with routes. For example, if this is a portion of your project's __init__.py:

```
# in your project's __init__.py (mypackage.__init__)
config.add_route('myroute', '/prefix/{one}/{two}')
config.scan('mypackage')
```

Note that we don't call add_view() in this setup code. However, the above *scan* execution config.scan('mypackage') will pick up all *configuration decoration*, including any objects decorated with the pyramid.view.view_config decorator in the mypackage Python pakage. For example, if you have a views.py in your package, a scan will pick up any of its configuration decorators, so we can add one there that that references myroute as a route_name parameter:

```
# in your project's views.py module (mypackage.views)
from pyramid.view import view_config
from pyramid.response import Response
@view_config(route_name='myroute')
def myview(request):
    return Response('OK')
```

The above combination of add_route and scan is completely equivalent to using the previous combination of add_route and add_view.

6.2.2 Route Pattern Syntax

The syntax of the pattern matching language used by Pyramid URL dispatch in the *pattern* argument is straightforward; it is close to that of the *Routes* system used by *Pylons*.

The *pattern* used in route configuration may start with a slash character. If the pattern does not start with a slash character, an implicit slash will be prepended to it at matching time. For example, the following patterns are equivalent:

{foo}/bar/baz

and:

/{foo}/bar/baz

A pattern segment (an individual item between / characters in the pattern) may either be a literal string (e.g. foo) or it may be a replacement marker (e.g. $\{foo\}$) or a certain combination of both. A replacement marker does not need to be preceded by a / character.

A replacement marker is in the format {name}, where this means "accept any characters up to the next slash character and use this as the name *matchdict* value." A matchdict is the dictionary representing the dynamic parts extracted from a URL based on the routing pattern. It is available as request.matchdict. For example, the following pattern defines one literal segment (foo) and two replacement markers (baz, and bar):

```
foo/{baz}/{bar}
```

The above pattern will match these URLs, generating the following matchdicts:

```
foo/1/2 -> {'baz':u'1', 'bar':u'2'}
foo/abc/def -> {'baz':u'abc', 'bar':u'def'}
```

It will not match the following patterns however:

foo/1/2/ -> No match (trailing slash)
bar/abc/def -> First segment literal mismatch

The match for a segment replacement marker in a segment will be done only up to the first nonalphanumeric character in the segment in the pattern. So, for instance, if this route pattern was used:

6. URL DISPATCH

foo/{name}.html

The literal path /foo/biz.html will match the above route pattern, and the match result will be {'name':u'biz'}. However, the literal path /foo/biz will not match, because it does not contain a literal .html at the end of the segment represented by {name}.html (it only contains biz, not biz.html).

To capture both segments, two replacement markers can be used:

foo/{name}.{ext}

The literal path /foo/biz.html will match the above route pattern, and the match result will be {'name': 'biz', 'ext': 'html'}. This occurs because there is a literal part of . (period) between the two replacement markers {name} and {ext}.

Replacement markers can optionally specify a regular expression which will be used to decide whether a path segment should match the marker. To specify that a replacement marker should match only a specific set of characters as defined by a regular expression, you must use a slightly extended form of replacement marker syntax. Within braces, the replacement marker name must be followed by a colon, then directly thereafter, the regular expression. The *default* regular expression associated with a replacement marker $[^/]$ + matches one or more characters which are not a slash. For example, under the hood, the replacement marker $\{ \text{foo} \}$ can more verbosely be spelled as $\{ \text{foo}: [^/]+ \}$. You can change this to be an arbitrary regular expression to match an arbitrary sequence of characters, such as $\{ \text{foo}: \d+ \}$ to match only digits.

It is possible to use two replacement markers without any literal characters between them, for instance $/\{foo\}\{bar\}$. However, this would be a nonsensical pattern without specifying a custom regular expression to restrict what each marker captures.

Segments must contain at least one character in order to match a segment replacement marker. For example, for the URL /abc/:

- /abc/{foo} will not match.
- / { foo } / will match.

Note that values representing matched path segments will be url-unquoted and decoded from UTF-8 into Unicode within the matchdict. So for instance, the following pattern:

foo/{bar}

When matching the following URL:

foo/La%20Pe%C3%B1a

The matchdict will look like so (the value is URL-decoded / UTF-8 decoded):

```
{'bar':u'La Pe\xf1a'}
```

If the pattern has a \star in it, the name which follows it is considered a "remainder match". A remainder match *must* come at the end of the pattern. Unlike segment replacement markers, it does not need to be preceded by a slash. For example:

```
foo/{baz}/{bar}*fizzle
```

The above pattern will match these URLs, generating the following matchdicts:

```
foo/1/2/ ->
{'baz':u'1', 'bar':u'2', 'fizzle':()}
foo/abc/def/a/b/c ->
{'baz':u'abc', 'bar':u'def', 'fizzle':(u'a', u'b', u'c')}
```

Note that when a **stararg* remainder match is matched, the value put into the matchdict is turned into a tuple of path segments representing the remainder of the path. These path segments are url-unquoted and decoded from UTF-8 into Unicode. For example, for the following pattern:

foo/*fizzle

When matching the following path:

```
/foo/La%20Pe%C3%B1a/a/b/c
```

Will generate the following matchdict:

```
{'fizzle':(u'La Pe\xfla', u'a', u'b', u'c')}
```

By default, the **stararg* will parse the remainder sections into a tuple split by segment. Changing the regular expression used to match a marker can also capture the remainder of the URL, for example:

foo/{baz}/{bar}{fizzle:.*}

The above pattern will match these URLs, generating the following matchdicts:

```
foo/1/2/ -> {'baz':u'1', 'bar':u'2', 'fizzle':()}
foo/abc/def/a/b/c -> {'baz':u'abc', 'bar':u'def', 'fizzle': u'a/b/c')}
```

This occurs because the default regular expression for a marker is $[^/]$ + which will match everything up to the first /, while {fizzle:.*} will result in a regular expression match of .* capturing the remainder into a single value.

6.2.3 Route Declaration Ordering

Route configuration declarations are evaluated in a specific order when a request enters the system. As a result, the order of route configuration declarations is very important. The order that routes declarations are evaluated is the order in which they are added to the application at startup time. (This is unlike a different way of mapping URLs to code that Pyramid provides, named *traversal*, which does not depend on pattern ordering).

For routes added via the add_route method, the order that routes are evaluated is the order in which they are added to the configuration imperatively.

For example, route configuration statements with the following patterns might be added in the following order:

```
members/{def}
members/abc
```

In such a configuration, the members/abc pattern would *never* be matched. This is because the match ordering will always match members/{def} first; the route configuration with members/abc will never be evaluated.

6.2.4 Route Factories

A "route" configuration declaration can mention a "factory". When that route matches a request, and a factory is attached to a route, the *root factory* passed at startup time to the *Configurator* is ignored; instead the factory associated with the route is used to generate a *root* object. This object will usually be used as the *context* resource of the view callable ultimately found via *view lookup*.

```
1 config.add_route('abc', '/abc',
2 factory='myproject.resources.root_factory')
3 config.add_view('myproject.views.theview', route_name='abc')
```

The factory can either be a Python object or a *dotted Python name* (a string) which points to such a Python object, as it is above.

In this way, each route can use a different factory, making it possible to supply a different *context* resource object to the view related to each particular route.

Supplying a different resource factory for each route is useful when you're trying to use a Pyramid *au-thorization policy* to provide declarative, "context sensitive" security checks; each resource can maintain a separate *ACL*, as documented in *Using Pyramid Security With URL Dispatch*. It is also useful when you wish to combine URL dispatch with *traversal* as documented within *Combining Traversal and URL Dispatch*.

6.2.5 Route Configuration Arguments

Route configuration add_route statements may specify a large number of arguments. They are documented as part of the API documentation at pyramid.config.Configurator.add_route().

Many of these arguments are *route predicate* arguments. A route predicate argument specifies that some aspect of the request must be true for the associated route to be considered a match during the route matching process. Examples of route predicate arguments are pattern, xhr, and request_method.

Other arguments are name and factory. These arguments represent neither predicates nor view configuration information.

Some arguments are view-configuration related arguments, such as view_renderer. These only have an effect when the route configuration names a view and these arguments have been deprecated as of Pyramid 1.1.

6.2.6 Custom Route Predicates

Each of the predicate callables fed to the custom_predicates argument of add_route() must be a callable accepting two arguments. The first argument passed to a custom predicate is a dictionary conventionally named info. The second argument is the current *request* object.

The info dictionary has a number of contained values: match is a dictionary: it represents the arguments matched in the URL by the route. route is an object representing the route which was matched (see pyramid.interfaces.IRoute for the API of such a route object).

info['match'] is useful when predicates need access to the route match. For example:

```
def any_of(segment_name, *allowed):
1
      def predicate(info, request):
2
          if info['match'][segment name] in allowed:
3
              return True
4
      return predicate
5
  num_one_two_or_three = any_of('num', 'one', 'two', 'three')
7
  config.add_route('route_to_num', '/{num}',
9
                    custom_predicates=(num_one_two_or_three,))
10
```

The above any_of function generates a predicate which ensures that the match value named segment_name is in the set of allowable values represented by allowed. We use this any_of function to generate a predicate function named num_one_two_or_three, which ensures that the num segment is one of the values one, two, or three, and use the result as a custom predicate by feeding it inside a tuple to the custom_predicates argument to add_route().

A custom route predicate may also *modify* the match dictionary. For instance, a predicate might do some type conversion of values:

```
def integers(*segment_names):
1
2
       def predicate(info, request):
           match = info['match']
3
            for segment_name in segment_names:
4
5
                try:
                    match[segment_name] = int(match[segment_name])
6
                except (TypeError, ValueError):
7
                    pass
8
            return True
9
       return predicate
10
11
   ymd_to_int = integers('year', 'month', 'day')
12
```

```
13
14 config.add_route('ymd', '/{year}/{month}/{day}',
15 custom_predicates=(ymd_to_int,))
```

Note that a conversion predicate is still a predicate so it must return True or False; a predicate that does *only* conversion, such as the one we demonstrate above should unconditionally return True.

To avoid the try/except uncertainty, the route pattern can contain regular expressions specifying requirements for that marker. For instance:

```
def integers(*segment names):
2
       def predicate(info, request):
           match = info['match']
3
            for segment_name in segment_names:
4
                match[segment_name] = int(match[segment_name])
5
           return True
6
       return predicate
7
8
   ymd_to_int = integers('year', 'month', 'day')
9
10
   config.add_route('ymd', '/{year:\d+}/{month:\d+}/{day:\d+}',
11
                     custom_predicates=(ymd_to_int,))
12
```

Now the try/except is no longer needed because the route will not match at all unless these markers match d+ which requires them to be valid digits for an int type conversion.

The match dictionary passed within info to each predicate attached to a route will be the same dictionary. Therefore, when registering a custom predicate which modifies the match dict, the code registering the predicate should usually arrange for the predicate to be the *last* custom predicate in the custom predicate list. Otherwise, custom predicates which fire subsequent to the predicate which performs the match modification will receive the *modified* match dictionary.

It is a poor idea to rely on ordering of custom predicates to build a conversion pipeline, where one predicate depends on the side effect of another. For instance, it's a poor idea to register two custom predicates, one which handles conversion of a value to an int, the next which handles conversion of that integer to some custom object. Just do all that in a single custom predicate.

The route object in the info dict is an object that has two useful attributes: name and pattern. The name attribute is the route name. The pattern attribute is the route pattern. An example of using the route in a set of route predicates:

The above predicate, when added to a number of route configurations ensures that the year match argument is '2010' if and only if the route name is 'ymd', 'ym', or 'y'.

See also pyramid.interfaces.IRoute for more API documentation about route objects.

6.3 Route Matching

The main purpose of route configuration is to match (or not match) the PATH_INFO present in the WSGI environment provided during a request against a URL path pattern. PATH_INFO represents the path portion of the URL that was requested.

The way that Pyramid does this is very simple. When a request enters the system, for each route configuration declaration present in the system, Pyramid checks the request's PATH_INFO against the pattern declared. This checking happens in the order that the routes were declared via pyramid.config.Configurator.add_route().

When a route configuration is declared, it may contain *route predicate* arguments. All route predicates associated with a route declaration must be True for the route configuration to be used for a given request during a check. If any predicate in the set of *route predicate* arguments provided to a route configuration returns False during a check, that route is skipped and route matching continues through the ordered set of routes.

If any route matches, the route matching process stops and the *view lookup* subsystem takes over to find the most reasonable view callable for the matched route. Most often, there's only one view that will match (a view configured with a route_name argument matching the matched route). To gain a better understanding of how routes and views are associated in a real application, you can use the paster pviews command, as documented in *Displaying Matching Views for a Given URL*.

If no route matches after all route patterns are exhausted, Pyramid falls back to *traversal* to do *resource location* and *view lookup*.

6.3.1 The Matchdict

When the URL pattern associated with a particular route configuration is matched by a request, a dictionary named matchdict is added as an attribute of the *request* object. Thus, request.matchdict will contain the values that match replacement patterns in the pattern element. The keys in a matchdict will be strings. The values will be Unicode objects.

If no route URL pattern matches, the matchdict object attached to the request will be None.

6.3.2 The Matched Route

When the URL pattern associated with a particular route configuration is matched by a request, an object named matched_route is added as an attribute of the *request* object. Thus, request.matched_route will be an object implementing the IRoute interface which matched the request. The most useful attribute of the route object is name, which is the name of the route that matched.

■ If no route URL pattern matches, the matched_route object attached to the request will be None.

6.4 Routing Examples

Let's check out some examples of how route configuration statements might be commonly declared, and what will happen if they are matched by the information present in a request.

6.4.1 Example 1

The simplest route declaration which configures a route match to *directly* result in a particular view callable being invoked:

```
1 config.add_route('idea', 'site/{id}')
2 config.add_view('mypackage.views.site_view', route_name='idea')
```

6. URL DISPATCH

When a route configuration with a view attribute is added to the system, and an incoming request matches the *pattern* of the route configuration, the *view callable* named as the view attribute of the route configuration will be invoked.

In the case of the above example, when the URL of a request matches /site/{id}, the view callable at the Python dotted path name mypackage.views.site_view will be called with the request. In other words, we've associated a view callable directly with a route pattern.

When the /site/{id} route pattern matches during a request, the site_view view callable is invoked with that request as its sole argument. When this route matches, a matchdict will be generated and attached to the request as request.matchdict. If the specific URL matched is /site/1, the matchdict will be a dictionary with a single key, id; the value will be the string '1', ex.: {'id':'1'}.

The mypackage.views module referred to above might look like so:

```
1 from pyramid.response import Response
2
3 def site_view(request):
4 return Response(request.matchdict['id'])
```

The view has access to the matchdict directly via the request, and can access variables within it that match keys present as a result of the route pattern.

See Views, and View Configuration for more information about views.

6.4.2 Example 2

Below is an example of a more complicated set of route statements you might add to your application:

```
1 config.add_route('idea', 'ideas/{idea}')
2 config.add_route('user', 'users/{user}')
3 config.add_route('tag', 'tags/{tags}')
4
5 config.add_view('mypackage.views.idea_view', route_name='idea')
6 config.add_view('mypackage.views.user_view', route_name='user')
7 config.add_view('mypackage.views.tag_view', route_name='tag')
```

The above configuration will allow Pyramid to service URLs in these forms:

```
/ideas/{idea}
/users/{user}
/tags/{tag}
```

- When a URL matches the pattern /ideas/{idea}, the view callable available at the dotted Python pathname mypackage.views.idea_view will be called. For the specific URL /ideas/1, the matchdict generated and attached to the *request* will consist of {'idea':'1'}.
- When a URL matches the pattern /users/{user}, the view callable available at the dotted Python pathname mypackage.views.user_view will be called. For the specific URL /users/1, the matchdict generated and attached to the *request* will consist of {'user':'1'}.
- When a URL matches the pattern /tags/{tag}, the view callable available at the dotted Python pathname mypackage.views.tag_view will be called. For the specific URL /tags/1, the matchdict generated and attached to the *request* will consist of {'tag':'1'}.

In this example we've again associated each of our routes with a *view callable* directly. In all cases, the request, which will have a matchdict attribute detailing the information found in the URL by the process will be passed to the view callable.

6.4.3 Example 3

The *context* resource object passed in to a view found as the result of URL dispatch will, by default, be an instance of the object returned by the *root factory* configured at startup time (the root_factory argument to the *Configurator* used to configure the application).

You can override this behavior by passing in a factory argument to the add_route() method for a particular route. The factory should be a callable that accepts a *request* and returns an instance of a class that will be the context resource used by the view.

An example of using a route with a factory:

```
1 config.add_route('idea', 'ideas/{idea}', factory='myproject.resources.Idea'
2 config.add_view('myproject.views.idea_view', route_name='idea')
```

The above route will manufacture an Idea resource as a *context*, assuming that mypackage.resources.Idea resolves to a class that accepts a request in its __init__. For example:

```
1 class Idea(object):
2 def __init__(self, request):
3 pass
```

In a more complicated application, this root factory might be a class representing a SQLAlchemy model.

6.5 Matching the Root URL

It's not entirely obvious how to use a route pattern to match the root URL ("/"). To do so, give the empty string as a pattern in a call to add_route():

```
config.add_route('root', '')
```

Or provide the literal string / as the pattern:

```
config.add_route('root', '/')
```

6.6 Generating Route URLs

Use the pyramid.url.route_url() function to generate URLs based on route patterns. For example, if you've configured a route with the name "foo" and the pattern " $\{a\}/\{b\}/\{c\}$ ", you might do this.

```
1 from pyramid.url import route_url
2 url = route_url('foo', request, a='1', b='2', c='3')
```

This would return something like the string http://example.com/1/2/3 (at least if the current protocol and hostname implied http://example.com). See the route_url() API documentation for more information.

6.7 Static Routes

Routes may be added with a static keyword argument. For example:

```
1 config = Configurator()
2 config.add_route('page', '/page/{action}', static=True)
```

Routes added with a True static keyword argument will never be considered for matching at request time. Static routes are useful for URL generation purposes only. As a result, it is usually nonsensical to provide other non-name and non-pattern arguments to add_route() when static is passed as True, as none of the other arguments will ever be employed. A single exception to this rule is use of the pregenerator argument, which is not ignored when static is True.

the static argument to add_route() is new as of Pyramid 1.1.

6.8 Redirecting to Slash-Appended Routes

For behavior like Django's APPEND_SLASH=True, use the append_slash_notfound_view() view as the *Not Found view* in your application. Defining this view as the *Not Found view* is a way to automatically redirect requests where the URL lacks a trailing slash, but requires one to match the proper route. When configured, along with at least one other route in your application, this view will be invoked if the value of PATH_INFO does not already end in a slash, and if the value of PATH_INFO *plus* a slash matches any route's pattern. In this case it does an HTTP redirect to the slash-appended PATH_INFO.

Let's use an example, because this behavior is a bit magical. If the append_slash_notfound_view is configured in your application and your route configuration looks like so:

```
1 config.add_route('noslash', 'no_slash')
2 config.add_route('hasslash', 'has_slash/')
3 
4 config.add_view('myproject.views.no_slash', route_name='noslash')
5 config.add_view('myproject.views.has_slash', route_name='hasslash')
```

If a request enters the application with the PATH_INFO value of /has_slash/, the second route will match. If a request enters the application with the PATH_INFO value of /has_slash, a route will be found by the slash-appending not found view. An HTTP redirect to /has_slash/ will be returned to the user's browser.

If a request enters the application with the PATH_INFO value of /no_slash, the first route will match. However, if a request enters the application with the PATH_INFO value of /no_slash/, *no* route will match, and the slash-appending not found view will *not* find a matching route with an appended slash. You should not rely on this mechanism to redirect POST requests. The redirect of the slashappending not found view will turn a POST request into a GET, losing any POST data in the original request.

To configure the slash-appending not found view in your application, change the application's startup configuration, adding the following stanza:

```
1 config.add_view('pyramid.view.append_slash_notfound_view',
2 context='pyramid.httpexceptions.HTTPNotFound')
```

See *pyramid.view* and *Changing the Not Found View* for more information about the slash-appending not found view and for a more general description of how to configure a not found view.

6.8.1 Custom Not Found View With Slash Appended Routes

There can only be one *Not Found view* in any Pyramid application. Even if you use append_slash_notfound_view() as the Not Found view, Pyramid still must generate a 404 Not Found response when it cannot redirect to a slash-appended URL; this not found response will be visible to site users.

If you don't care what this 404 response looks like, and only you need redirections to slashappended route URLs, you may use the append_slash_notfound_view() object as the Not Found view as described above. However, if you wish to use a *custom* notfound view callable when a URL cannot be redirected to a slash-appended URL, you may wish to use an instance of the AppendSlashNotFoundViewFactory class as the Not Found view, supplying a *view callable* to be used as the custom notfound view as the first argument to its constructor. For instance:

```
from pyramid.httpexceptions import HTTPNotFound
from pyramid.view import AppendSlashNotFoundViewFactory
def notfound_view(context, request):
    return HTTPNotFound('It aint there, stop trying!')
custom_append_slash = AppendSlashNotFoundViewFactory(notfound_view)
config.add_view(custom_append_slash, context=HTTPNotFound)
```

The notfound_view supplied must adhere to the two-argument view callable calling convention of (context, request) (context will be the exception object).

6.9 Cleaning Up After a Request

Sometimes it's required that some cleanup be performed at the end of a request when a database connection is involved.

For example, let's say you have a mypackage Pyramid application package that uses SQLAlchemy, and you'd like the current SQLAlchemy database session to be removed after each request. Put the following in the mypackage.___init___ module:

```
from mypackage.models import DBSession
2
  from pyramid.events import subscriber
3
  from pyramid.events import NewRequest
4
5
  def cleanup_callback(request):
6
      DBSession.remove()
7
8
  (subscriber (NewRequest)
9
10
  def add_cleanup_callback(event):
      event.request.add_finished_callback(cleanup_callback)
11
```

Registering the cleanup_callback finished callback at the start of a request (by causing the add_cleanup_callback to receive a pyramid.events.NewRequest event at the start of each request) will cause the DBSession to be removed whenever request processing has ended. Note that in the example above, for the pyramid.events.subscriber decorator to "work", the pyramid.config.Configurator.scan() method must be called against your mypackage package during application initialization.

This is only an example. In particular, it is not necessary to cause DBSession.remove to be called in an application generated from any Pyramid scaffold, because these all use the repoze.tm2 middleware. The cleanup done by DBSession.remove is unnecessary when repoze.tm2 middleware is in the WSGI pipeline.

6.10 Using Pyramid Security With URL Dispatch

Pyramid provides its own security framework which consults an *authorization policy* before allowing any application code to be called. This framework operates in terms of an access control list, which is stored as an __acl__ attribute of a resource object. A common thing to want to do is to attach an __acl__ to

the resource object dynamically for declarative security purposes. You can use the factory argument that points at a factory which attaches a custom ___acl___ to an object at its creation time.

Such a factory might look like so:

```
class Article(object):
    def __init__(self, request):
        matchdict = request.matchdict
        article = matchdict.get('article', None)
        if article == '1':
            self.__acl__ = [ (Allow, 'editor', 'view') ]
```

If the route archives/{article} is matched, and the article number is 1, Pyramid will generate an Article *context* resource with an ACL on it that allows the editor principal the view permission. Obviously you can do more generic things than inspect the routes match dict to see if the article argument matches a particular string; our sample Article factory class is not very ambitious.

See Security for more information about Pyramid security and ACLs.

6.11 Debugging Route Matching

It's useful to be able to take a peek under the hood when requests that enter your application arent matching your routes as you expect them to. To debug route matching, use the PYRAMID_DEBUG_ROUTEMATCH environment variable or the debug_routematch configuration file setting (set either to true). Details of the route matching decision for a particular request to the Pyramid application will be printed to the stderr of the console which you started the application from. For example:

```
[chrism@thinko pylonsbasic]$ PYRAMID_DEBUG_ROUTEMATCH=true \
                                 bin/paster serve development.ini
2
3
   Starting server in PID 13586.
   serving on 0.0.0.0:6543 view at http://127.0.0.1:6543
4
   2010-12-16 14:45:19,956 no route matched for url \
5
                                        http://localhost:6543/wontmatch
6
   2010-12-16 14:45:20,010 no route matched for url \
7
                                http://localhost:6543/favicon.ico
8
   2010-12-16 14:41:52,084 route matched for url \
9
                                http://localhost:6543/static/logo.png; \
10
                                route_name: 'static/', ....
11
```

See Environment Variables and .ini File Settings for more information about how, and where to set these values.

You can also use the paster proutes command to see a display of all the routes configured in your application; for more information, see *Displaying All Application Routes*.

6.12 Route View Callable Registration and Lookup Details

When a request enters the system which matches the pattern of the route, the usual result is simple: the view callable associated with the route is invoked with the request that caused the invocation.

For most usage, you needn't understand more than this; how it works is an implementation detail. In the interest of completeness, however, we'll explain how it *does* work in the this section. You can skip it if you're uninterested.

When a view is associated with a route configuration, Pyramid ensures that a *view configuration* is registered that will always be found when the route pattern is matched during a request. To do so:

- A special route-specific *interface* is created at startup time for each route configuration declaration.
- When an add_view statement mentions a route name attribute, a *view configuration* is registered at startup time. This view configuration uses a route-specific interface as a *request* type.
- At runtime, when a request causes any route to match, the *request* object is decorated with the route-specific interface.
- The fact that the request is decorated with a route-specific interface causes the *view lookup* machinery to always use the view callable registered using that interface by the route configuration to service requests that match the route pattern.

As we can see from the above description, technically, URL dispatch doesn't actually map a URL pattern directly to a view callable. Instead, URL dispatch is a *resource location* mechanism. A Pyramid *resource location* subsystem (i.e., *URL dispatch* or *traversal*) finds a *resource* object that is the *context* of a *request*. Once the *context* is determined, a separate subsystem named *view lookup* is then responsible for finding and invoking a *view callable* based on information available in the context and the request. When URL dispatch is used, the resource location and view lookup subsystems provided by Pyramid are still being utilized, but in a way which does not require a developer to understand either of them in detail.

If no route is matched using URL dispatch, Pyramid falls back to traversal to handle the request.

6.13 References

A tutorial showing how URL dispatch can be used to create a Pyramid application exists in SQLAlchemy + URL Dispatch Wiki Tutorial.

CHAPTER

SEVEN

VIEWS

One of the primary jobs of Pyramid is to find and invoke a *view callable* when a *request* reaches your application. View callables are bits of code which do something interesting in response to a request made to your application. They are the "meat" of any interesting web application.

• A Pyramid *view callable* is often referred to in conversational shorthand as a *view*. In this documentation, however, we need to use less ambiguous terminology because there are significant differences between view *configuration*, the code that implements a view *callable*, and the process of view *lookup*.

This chapter describes how view callables should be defined. We'll have to wait until a following chapter (entitled *View Configuration*) to find out how we actually tell Pyramid to wire up view callables to particular URL patterns and other request circumstances.

7.1 View Callables

View callables are, at the risk of sounding obvious, callable Python objects. Specifically, view callables can be functions, classes, or instances that implement an <u>______</u>method (making the instance callable).

View callables must, at a minimum, accept a single argument named request. This argument represents a Pyramid *Request* object. A request object represents a *WSGI* environment provided to Pyramid by the upstream WSGI server. As you might expect, the request object contains everything your application needs to know about the specific HTTP request being made.

A view callable's ultimate responsibility is to create a Pyramid *Response* object. This can be done by creating a *Response* object in the view callable code and returning it directly or by raising special kinds of exceptions from within the body of a view callable.

7.2 Defining a View Callable as a Function

One of the easiest way to define a view callable is to create a function that accepts a single argument named request, and which returns a *Response* object. For example, this is a "hello world" view callable implemented as a function:

```
1 from pyramid.response import Response
2
3 def hello_world(request):
4 return Response('Hello world!')
```

7.3 Defining a View Callable as a Class

A view callable may also be represented by a Python class instead of a function. When a view callable is a class, the calling semantics are slightly different than when it is a function or another non-class callable. When a view callable is a class, the class' ____init___ method is called with a request parameter. As a result, an instance of the class is created. Subsequently, that instance's ___call__ method is invoked with no parameters. Views defined as classes must have the following traits:

- an ___init___ method that accepts a request argument.
- a __call__ (or other) method that accepts no parameters and which returns a response.

For example:

```
from pyramid.response import Response
class MyView(object):
def __init__(self, request):
    self.request = request
def __call__(self):
    return Response('hello')
```

The request object passed to _______ is the same type of request object described in *Defining a View Callable as a Function*.

If you'd like to use a different attribute than __call___ to represent the method expected to return a response, you can use an attr value as part of the configuration for the view. See *View Configuration Parameters*. The same view callable class can be used in different view configuration statements with different attr values, each pointing at a different method of the class if you'd like the class to represent a collection of related view callables.

7.4 View Callable Responses

A view callable may return an object that implements the Pyramid *Response* interface. The easiest way to return something that implements the *Response* interface is to return a pyramid.response.Response object instance directly. For example:

```
1 from pyramid.response import Response
2
3 def view(request):
4 return Response('OK')
```

different inherit Pyramid provides of "exception" classes which from а range pyramid.response.Response. For example, an instance of the class pyramid.httpexceptions.HTTPFound is also a valid response object because it inherits from Response. For examples, see HTTP Exceptions and Using a View Callable to Do an HTTP Redirect.

• You can also return objects from view callables that aren't instances of pyramid.response.Response in various circumstances. This can be helpful when writing tests and when attempting to share code between view callables. See *Renderers* for the common way to allow for this. A much less common way to allow for view callables to return non-Response objects is documented in *Changing How Pyramid Treats View Responses*.

7.5 Using Special Exceptions In View Callables

Usually when a Python exception is raised within a view callable, Pyramid allows the exception to propagate all the way out to the *WSGI* server which invoked the application. It is usually caught and logged there.

However, for convenience, a special set of exceptions exists. When one of these exceptions is raised within a view callable, it will always cause Pyramid to generate a response. These are known as *HTTP exception* objects.

7.5.1 HTTP Exceptions

All classes documented in the pyramid.httpexceptions module documented as inheriting from the pryamid.httpexceptions.HTTPException are *http exception* objects. An instances of an HTTP exception object may either be *returned* or *raised* from within view code. In either case (return or raise) the instance will be used as as the view's response.

For example, the pyramid.httpexceptions.HTTPUnauthorized exception can be raised. This will cause a response to be generated with a 401 Unauthorized status:

```
1 from pyramid.httpexceptions import HTTPUnauthorized
2
3 def aview(request):
4 raise HTTPUnauthorized()
```

An HTTP exception, instead of being raised, can alternately be *returned* (HTTP exceptions are also valid response objects):

```
1 from pyramid.httpexceptions import HTTPUnauthorized
2
3 def aview(request):
4 return HTTPUnauthorized()
```

A shortcut for creating an HTTP exception is the pyramid.httpexceptions.exception_response() function. This function accepts an HTTP status code and returns the corresponding HTTP exception. For example, instead of importing and constructing a HTTPUnauthorized response object, you can use the exception_response() function to construct and return the same object.

```
from pyramid.httpexceptions import exception_response
def aview(request):
    raise exception_response(401)
```

This is the case because 401 is the HTTP status code for "HTTP Unauthorized". Therefore, raise exception_response(401) is functionally equivalent to raise HTTPUnauthorized(). Documentation which maps each HTTP response code to its purpose and its associated HTTP exception object is provided within pyramid.httpexceptions.

The exception_response() function is new as of Pyramid 1.1.

7.5.2 How Pyramid Uses HTTP Exceptions

HTTP exceptions to be used directly by application application develare meant opers. However, Pyramid itself will raise two HTTP exceptions at various points during normal operations: pyramid.httpexceptions.HTTPNotFound and Pyramid will raise the HTTPNotFound pyramid.httpexceptions.HTTPForbidden. exception are raised when it cannot find a view to service a request. Pyramid will raise the Forbidden exception or when authorization was forbidden by a security policy.

If HTTPNotFound is raised by Pyramid itself or within view code, the result of the *Not Found View* will be returned to the user agent which performed the request.

If HTTPForbidden is raised by Pyramid itself within view code, the result of the *Forbidden View* will be returned to the user agent which performed the request.

7.6 Custom Exception Views

The machinery which allows HTTP exceptions to be raised and caught by specialized views as described in *Using Special Exceptions In View Callables* can also be used by application developers to convert arbitrary exceptions to responses.

To register a view that should be called whenever a particular exception is raised from with Pyramid view code, use the exception class or one of its superclasses as the context of a view configuration which points at a view callable you'd like to generate a response.

For example, given the following exception class in a module named helloworld.exceptions:

```
class ValidationFailure(Exception):
    def __init__(self, msg):
        self.msg = msg
```

You can wire a view callable to be called whenever any of your *other* code raises a helloworld.exceptions.ValidationFailure exception:

```
from pyramid.view import view_config
from helloworld.exceptions import ValidationFailure

def failed_validation(exc, request):
    response = Response('Failed validation: %s' % exc.msg)
    response.status_int = 500
    return response
```

Assuming that a *scan* was run to pick up this view registration, this view callable will be invoked whenever a helloworld.exceptions.ValidationFailure is raised by your application's view code. The same exception raised by a custom root factory, a custom traverser, or a custom view or route predicate is also caught and hooked.

Other normal view predicates can also be used in combination with an exception view registration:

```
from pyramid.view import view_config
from helloworld.exceptions import ValidationFailure

(@view_config(context=ValidationFailure, route_name='home')
def failed_validation(exc, request):
    response = Response('Failed validation: %s' % exc.msg)
    response.status_int = 500
    return response
```

The above exception view names the route_name of home, meaning that it will only be called when the route matched has a name of home. You can therefore have more than one exception view for any given exception in the system: the "most specific" one will be called when the set of request circumstances match the view registration.

The only view predicate that cannot be used successfully when creating an exception view configuration is name. The name used to look up an exception view is always the empty string. Views registered as exception views which have a name will be ignored.

• Normal (i.e., non-exception) views registered against a context resource type which inherits from Exception will work normally. When an exception view configuration is processed, *two* views are registered. One as a "normal" view, the other as an "exception" view. This means that you can use an exception as context for a normal view.

Exception views can be configured with any view registration mechanism: @view_config decorator or imperative add_view styles.

7.7 Using a View Callable to Do an HTTP Redirect

You can issue an HTTP redirect by using the pyramid.httpexceptions.HTTPFound class. Raising or returning an instance of this class will cause the client to receive a "302 Found" response.

To do so, you can return a pyramid.httpexceptions.HTTPFound instance.

```
from pyramid.httpexceptions import HTTPFound
def myview(request):
    return HTTPFound(location='http://example.com')
```

Alternately, you can raise an HTTPFound exception instead of returning one.

```
1 from pyramid.httpexceptions import HTTPFound
2 
3 def myview(request):
4 raise HTTPFound(location='http://example.com')
```

When the instance is raised, it is caught by the default *exception response* handler and turned into a response.

7.8 Handling Form Submissions in View Callables (Unicode and Character Set Issues)

Most web applications need to accept form submissions from web browsers and various other clients. In Pyramid, form submission handling logic is always part of a *view*. For a general overview of how to handle form submission data using the *WebOb* API, see *Request and Response Objects* and "Query and POST variables" within the WebOb documentation. Pyramid defers to WebOb for its request and response implementations, and handling form submission data is a property of the request implementation. Understanding WebOb's request API is the key to understanding how to process form submission data.

There are some defaults that you need to be aware of when trying to handle form submission data in a Pyramid view. Having high-order (i.e., non-ASCII) characters in data contained within form submissions is exceedingly common, and the UTF-8 encoding is the most common encoding used on the web for character data. Since Unicode values are much saner than working with and storing bytestrings, Pyramid configures the *WebOb* request machinery to attempt to decode form submission values into Unicode from UTF-8 implicitly. This implicit decoding happens when view code obtains form field values via the request.params, request.GET, or request.POST APIs (see *pyramid.request* for details about these APIs).

Many people find the difference between Unicode and UTF-8 confusing. Unicode is a standard for representing text that supports most of the world's writing systems. However, there are many ways that Unicode data can be encoded into bytes for transit and storage. UTF-8 is a specific encoding for Unicode, that is backwards-compatible with ASCII. This makes UTF-8 very convenient for encoding data where a large subset of that data is ASCII characters, which is largely true on the web. UTF-8 is also the standard character encoding for URLs.

As an example, let's assume that the following form page is served up to a browser client, and its action points at some Pyramid view code:

```
<html xmlns="http://www.w3.org/1999/xhtml">
1
    <head>
2
       <meta http-equiv="Content-Type" content="text/html; charset=UTF-8"/>
3
    </head>
4
    <form method="POST" action="myview">
5
      <div>
6
         <input type="text" name="firstname"/>
7
      </div>
8
       <div>
9
        <input type="text" name="lastname"/>
10
      </div>
11
      <input type="submit" value="Submit"/>
12
    </form>
13
  </html>
14
```

The myview view code in the Pyramid application *must* expect that the values returned by request.params will be of type unicode, as opposed to type str. The following will work to accept a form post from the above form:

```
1 def myview(request):
2     firstname = request.params['firstname']
3     lastname = request.params['lastname']
```

But the following myview view code *may not* work, as it tries to decode already-decoded (unicode) values obtained from request.params:

```
def myview(request):
    # the .decode('utf-8') will break below if there are any high-order
    # characters in the firstname or lastname
    firstname = request.params['firstname'].decode('utf-8')
    lastname = request.params['lastname'].decode('utf-8')
```

For implicit decoding to work reliably, you should ensure that every form you render that posts to a Pyramid view explicitly defines a charset encoding of UTF-8. This can be done via a response that has a ; charset=UTF-8 in its Content-Type header; or, as in the form above, with a meta http-equiv tag that implies that the charset is UTF-8 within the HTML head of the page containing the form. This must be done explicitly because all known browser clients assume that they should encode form data in the same character set implied by Content-Type value of the response containing the form when subsequently submitting that form. There is no other generally accepted way to tell browser clients which charset to use to encode form data. If you do not specify an encoding explicitly, the browser

client will choose to encode form data in its default character set before submitting it, which may not be UTF-8 as the server expects. If a request containing form data encoded in a non-UTF8 charset is handled by your view code, eventually the request code accessed within your view will throw an error when it can't decode some high-order character encoded in another character set within form data, e.g., when request.params['somename'] is accessed.

If you are using the Response class to generate a response, or if you use the render_template_* templating APIs, the UTF-8 charset is set automatically as the default via the Content-Type header. If you return a Content-Type header without an explicit charset, a request will add a ; charset=utf-8 trailer to the Content-Type header value for you, for response content types that are textual (e.g. text/html, application/xml, etc) as it is rendered. If you are using your own response object, you will need to ensure you do this yourself.

• Only the *values* of request params obtained via request.params, request.GET or request.POST are decoded to Unicode objects implicitly in the Pyramid default configuration. The keys are still (byte) strings.

7.9 Alternate View Callable Argument/Calling Conventions

Usually, view callables are defined to accept only a single argument: request. However, view callables may alternately be defined as classes, functions, or any callable that accept *two* positional arguments: a *context* resource as the first argument and a *request* as the second argument.

The *context* and *request* arguments passed to a view function defined in this style can be defined as follows:

context

The resource object found via tree traversal or URL dispatch.

request A Pyramid Request object representing the current WSGI request.

The following types work as view callables in this style:

1. Functions that accept two arguments: context, and request, e.g.:

```
1 from pyramid.response import Response
2
3 def view(context, request):
4 return Response('OK')
```

 Classes that have an __init__ method that accepts context, request and a __call__ method which accepts no arguments, e.g.:

3. Arbitrary callables that have a ____call___ method that accepts context, request, e.g.:

```
1 from pyramid.response import Response
2
3 class View(object):
4 def __call__(self, context, request):
5 return Response('OK')
6 view = View() # this is the view callable
```

This style of calling convention is most useful for *traversal* based applications, where the context object is frequently used within the view callable code itself.

No matter which view calling convention is used, the view code always has access to the context via request.context.

7.10 Pylons-1.0-Style "Controller" Dispatch

A package named *pyramid_handlers* (available from PyPI) provides an analogue of *Pylons* -style "controllers", which are a special kind of view class which provides more automation when your application uses *URL dispatch* solely.

CHAPTER

EIGHT

RENDERERS

A view callable needn't *always* return a *Response* object. If a view happens to return something which does not implement the Pyramid Response interface, Pyramid will attempt to use a *renderer* to construct a response. For example:

```
from pyramid.view import view_config

def hello_world(request):
    return {'content':'Hello!'}
```

The above example returns a *dictionary* from the view callable. A dictionary does not implement the Pyramid response interface, so you might believe that this example would fail. However, since a renderer is associated with the view callable through its *view configuration* (in this case, using a renderer argument passed to view_config()), if the view does *not* return a Response object, the renderer will attempt to convert the result of the view to a response on the developer's behalf.

Of course, if no renderer is associated with a view's configuration, returning anything except an object which implements the Response interface will result in an error. And, if a renderer *is* used, whatever is returned by the view must be compatible with the particular kind of renderer used, or an error may occur during view invocation.

One exception exists: it is *always* OK to return a Response object, even when a renderer is configured. If a view callable returns a response object from a view that is configured with a renderer, the renderer is bypassed entirely.

Various types of renderers exist, including serialization renderers and renderers which use templating systems. See also *Writing View Callables Which Use a Renderer*.

8.1 Writing View Callables Which Use a Renderer

As we've seen, view callables needn't always return a Response object. Instead, they may return an arbitrary Python object, with the expectation that a *renderer* will convert that object into a response instance on your behalf. Some renderers use a templating system; other renderers use object serialization techniques.

View configuration can vary the renderer associated with a view callable via the renderer attribute. For example, this call to add_view() associates the json renderer with a view callable:

config.add_view('myproject.views.my_view', renderer='json')

When this configuration is added to an application, the myproject.views.my_view view callable will now use a json renderer, which renders view return values to a *JSON* response serialization.

Other built-in renderers include renderers which use the *Chameleon* templating language to render a dictionary to a response. Additional renderers can be added by developers to the system as necessary (see *Adding and Changing Renderers*).

Views which use a renderer and return a non-Response value can vary non-body response attributes (such as headers and the HTTP status code) by attaching a property to the request.response attribute See *Varying Attributes of Rendered Responses*.

If the *view callable* associated with a *view configuration* returns a Response object directly, any renderer associated with the view configuration is ignored, and the response is passed back to Pyramid unchanged. For example, if your view callable returns an instance of the pyramid.response.Response class as a response, no renderer will be employed.

```
1 from pyramid.response import Response
2 from pyramid.view import view_config
3
4 @view_config(renderer='json')
5 def view(request):
6 return Response('OK') # json renderer avoided
```

Likewise for an HTTP exception response:

```
1 from pyramid.httpexceptions import HTTPNotFound
2 from pyramid.view import view_config
3
4 @view_config(renderer='json')
5 def view(request):
6 return HTTPFound(location='http://example.com') # json renderer avoided
```

You can of course also return the request .response attribute instead to avoid rendering:

```
from pyramid.view import view_config

view_config(renderer='json')

def view(request):
    request.response.body = 'OK'
    return request.response # json renderer avoided
```

8.2 Built-In Renderers

Several built-in renderers exist in Pyramid. These renderers can be used in the renderer attribute of view configurations.

8.2.1 string: String Renderer

The string renderer is a renderer which renders a view callable result to a string. If a view callable returns a non-Response object, and the string renderer is associated in that view's configuration, the result will be to run the object through the Python str function to generate a string. Note that if a Unicode object is returned by the view callable, it is not str() -ified.

Here's an example of a view that returns a dictionary. If the string renderer is specified in the configuration for this view, the view will render the returned dictionary to the str() representation of the dictionary:

```
1 from pyramid.response import Response
2 from pyramid.view import view_config
3
4 @view_config(renderer='string')
5 def hello_world(request):
6 return {'content':'Hello!'}
```

The body of the response returned by such a view will be a string representing the str() serialization of the return value:

```
1 {'content': 'Hello!'}
```

Views which use the string renderer can vary non-body response attributes by using the API of the request.response attribute. See *Varying Attributes of Rendered Responses*.

8.2.2 json: JSON Renderer

The json renderer renders view callable results to *JSON*. It passes the return value through the json.dumps standard library function, and wraps the result in a response object. It also sets the response content-type to application/json.

Here's an example of a view that returns a dictionary. Since the json renderer is specified in the configuration for this view, the view will render the returned dictionary to a JSON serialization:

```
1 from pyramid.response import Response
2 from pyramid.view import view_config
3
4 @view_config(renderer='json')
5 def hello_world(request):
6 return {'content':'Hello!'}
```

The body of the response returned by such a view will be a string representing the JSON serialization of the return value:

```
1 '{"content": "Hello!"}'
```

The return value needn't be a dictionary, but the return value must contain values serializable by json.dumps().

You can configure a view to use the JSON renderer by naming json as the renderer argument of a view configuration, e.g. by using add_view():

Views which use the JSON renderer can vary non-body response attributes by using the api of the request.response attribute. See Varying Attributes of Rendered Responses.

8.3 JSONP Renderer

This feature is new in Pyramid 1.1.

pyramid.renderers.JSONP is a JSONP renderer factory helper which implements a hybrid json/jsonp renderer. JSONP is useful for making cross-domain AJAX requests.

Unlike other renderers, a JSONP renderer needs to be configured at startup time "by hand". Configure a JSONP renderer using the pyramid.config.Configurator.add_renderer() method:

```
from pyramid.config import Configurator
config = Configurator()
config.add_renderer('jsonp', JSONP(param_name='callback'))
```

Once this renderer is registered via add renderer() as above. you can use jsonp as the renderer= parameter to Qview config or pyramid.config.Configurator.add_view`():

```
from pyramid.view import view_config
@view_config(renderer='jsonp')
def myview(request):
    return {'greeting':'Hello world'}
```

When a view is called that uses a JSONP renderer:

- If there is a parameter in the request's HTTP query string (aka request.GET) that matches the param_name of the registered JSONP renderer (by default, callback), the renderer will return a JSONP response.
- If there is no callback parameter in the request's query string, the renderer will return a 'plain' JSON response.

Javscript library AJAX functionality will help you make JSONP requests. For example, JQuery has a getJSON function, and has equivalent (but more complicated) functionality in its ajax function.

For example (Javascript):

The string callback=? above in the url param to the JQuery getAjax function indicates to jQuery that the query should be made as a JSONP request; the callback parameter will be automatically filled in for you and used.

8.3.1 *.pt or *.txt: Chameleon Template Renderers

Two built-in renderers exist for Chameleon templates.

If the renderer attribute of a view configuration is an absolute path, a relative path or *asset specification* which has a final path element with a filename extension of .pt, the Chameleon ZPT renderer is used. See *Chameleon ZPT Templates* for more information about ZPT templates.

If the renderer attribute of a view configuration is an absolute path or a *asset specification* which has a final path element with a filename extension of .txt, the *Chameleon* text renderer is used. See *Templating with Chameleon Text Templates* for more information about Chameleon text templates.

The behavior of these renderers is the same, except for the engine used to render the template.

When a renderer attribute that names a template path or *asset specification* (e.g. myproject:templates/foo.pt or myproject:templates/foo.txt) is used, the view must return a *Response* object or a Python *dictionary*. If the view callable with an associated template returns a Python dictionary, the named template will be passed the dictionary as its keyword arguments, and the template renderer implementation will return the resulting rendered template in a response to the user. If the view callable returns anything but a Response object or a dictionary, an error will be raised.

Before passing keywords to the template, the keyword arguments derived from the dictionary returned by the view are augmented. The callable object – whatever object was used to define the view – will be automatically inserted into the set of keyword arguments passed to the template as the view keyword. If the view callable was a class, the view keyword will be an instance of that class. Also inserted into the keywords passed to the template are renderer_name (the string used in the renderer attribute of the directive), renderer_info (an object containing renderer-related information), context (the context resource of the view used to render the template), and request (the request passed to the view used to render the template).

Here's an example view configuration which uses a Chameleon ZPT renderer:

Here's an example view configuration which uses a Chameleon text renderer:

```
config.add_view('myproject.views.hello_world',
                name='hello',
                context='myproject.resources.Hello',
                renderer='myproject:templates/foo.txt')
```

1

2

3

4

1

3

4

Views which use a Chameleon renderer can vary response attributes by using the API of the request.response attribute. See Varying Attributes of Rendered Responses.

8.3.2 *.mak or *.mako: Mako Template Renderer

The Mako template renderer renders views using a Mako template. When used, the view must return a Response object or a Python *dictionary*. The dictionary items will then be used in the global template space. If the view callable returns anything but a Response object or a dictionary, an error will be raised.

When using a renderer argument to a view configuration to specify a Mako template, the value of the renderer may be a path relative to the mako.directories setting (e.g. some/template.mak) or, alternately, it may be a *asset specification* (e.g. apackage:templates/sometemplate.mak). Mako templates may internally inherit other Mako templates using a relative filename or a *asset specification* as desired.

Here's an example view configuration which uses a relative path:

```
# config is an instance of pyramid.config.Configurator
1
2
   config.add_view('myproject.views.hello_world',
3
                   name='hello',
4
                   context='myproject.resources.Hello',
5
                   renderer='foo.mak')
6
```

It's important to note that in Mako's case, the 'relative' path name foo.mak above is not relative to the package, but is relative to the directory (or directories) configured for Mako via the mako.directories configuration file setting.

The renderer can also be provided in *asset specification* format. Here's an example view configuration which uses one:

```
config.add_view('myproject.views.hello_world',
                   name='hello',
2
                   context='myproject.resources.Hello',
                   renderer='mypackage:templates/foo.mak')
```

The above configuration will use the file named foo.mak in the templates directory of the mypackage package.

The Mako template renderer can take additional arguments beyond the standard reload_templates setting, see the *Environment Variables and .ini File Settings* for additional *Mako Template Render Settings*.

8.4 Varying Attributes of Rendered Responses

Before a response constructed by a *renderer* is returned to Pyramid, several attributes of the request are examined which have the potential to influence response behavior.

View callables that don't directly return a response should use the API of the pyramid.response.Response attribute available as request.response during their execution, to influence associated response behavior.

For example, if you need to change the response status from within a view callable that uses a renderer, assign the status attribute to the response attribute of the request before returning a result:

```
from pyramid.view import view_config

view_config(name='gone', renderer='templates/gone.pt')

def myview(request):
    request.response.status = '404 Not Found'
    return {'URL':request.URL}
```

Note that mutations of request.response in views which return a Response object directly will have no effect unless the response object returned *is* request.response. For example, the following example calls request.response.set_cookie, but this call will have no effect, because a different Response object is returned.

```
from pyramid.response import Response
def view(request):
request.response.set_cookie('abc', '123') # this has no effect
return Response('OK') # because we're returning a different response
```

If you mutate request.response and you'd like the mutations to have an effect, you must return request.response:

```
1 def view(request):
2 request.response.set_cookie('abc', '123')
3 return request.response
```

For more information on attributes of the request, see the API documentation in *pyramid.request*. For more information on the API of request.response, see pyramid.request.Request.response.

8.5 Deprecated Mechanism to Vary Attributes of Rendered Responses

This section describes behavior deprecated in Pyramid 1.1.

In previous releases of Pyramid (1.0 and before), the request.response attribute did not exist. Instead, Pyramid required users to set special response_-prefixed attributes of the request to influence response behavior. As of Pyramid 1.1, those request attributes are deprecated and their use will cause a deprecation warning to be issued when used. Until their existence is removed completely, we document them below, for benefit of people with older code bases.

response_content_type Defines the content-type of the resulting response, e.g. text/xml.

response_headerlist A sequence of tuples describing header values that should be set in the response, e.g. [('Set-Cookie', 'abc=123'), ('X-My-Header', 'foo')].

response_status A WSGI-style status code (e.g. 200 OK) describing the status of the response.

response_charset The character set (e.g. UTF-8) of the response.

response_cache_for A value in seconds which will influence Cache-Control and Expires
headers in the returned response. The same can also be achieved by returning various values in the
response_headerlist, this is purely a convenience.

8.6 Adding and Changing Renderers

New templating systems and serializers can be associated with Pyramid renderer names. To this end, configuration declarations can be made which change an existing *renderer factory*, and which add a new renderer factory.

Renderers can be registered imperatively using the pyramid.config.Configurator.add_renderer() API.

For example, to add a renderer which renders views which have a renderer attribute that is a path that ends in .jinja2:

```
config.add_renderer('.jinja2', 'mypackage.MyJinja2Renderer')
```

The first argument is the renderer name. The second argument is a reference to an implementation of a *renderer factory* or a *dotted Python name* referring to such an object.

8.6.1 Adding a New Renderer

You may add a new renderer by creating and registering a renderer factory.

A renderer factory implementation is typically a class with the following interface:

```
class RendererFactory:
1
      def __init__(self, info):
2
          """ Constructor: info will be an object having the
3
          following attributes: name (the renderer name), package
4
          (the package that was 'current' at the time the
5
          renderer was registered), type (the renderer type
6
          name), registry (the current application registry) and
7
          settings (the deployment settings dictionary). """
8
9
      def __call__(self, value, system):
10
          """ Call the renderer implementation with the value
11
          and the system value passed in as arguments and return
12
          the result (a string or unicode object). The value is
13
          the return value of a view. The system value is a
14
          dictionary containing available system values
15
          (e.g. view, context, and request). """
16
```

The formal interface definition of the info object passed to a renderer factory constructor is available as pyramid.interfaces.IRendererInfo.

There are essentially two different kinds of renderer factories:

- A renderer factory which expects to accept an *asset specification*, or an absolute path, as the name attribute of the info object fed to its constructor. These renderer factories are registered with a name value that begins with a dot (.). These types of renderer factories usually relate to a file on the filesystem, such as a template.
- A renderer factory which expects to accept a token that does not represent a filesystem path or an asset specification in the name attribute of the info object fed to its constructor. These renderer factories are registered with a name value that does not begin with a dot. These renderer factories are typically object serializers.

Asset Specifications

An asset specification is a colon-delimited identifier for an *asset*. The colon separates a Python *package* name from a package subpath. For example, the asset specification my.package:static/baz.css identifies the file named baz.css in the static subdirectory of the my.package Python *package*.

Here's an example of the registration of a simple renderer factory via add_renderer():

```
1 # config is an instance of pyramid.config.Configurator
2 
3 config.add_renderer(name='amf', factory='my.package.MyAMFRenderer')
```

Adding the above code to your application startup configuration will allow you to use the my.package.MyAMFRenderer renderer factory implementation in view configurations. Your application can use this renderer by specifying amf in the renderer attribute of a view configuration:

```
1 from pyramid.view import view_config
2
3 @view_config(renderer='amf')
4 def myview(request):
5 return {'Hello':'world'}
```

At startup time, when a *view configuration* is encountered, which has a name attribute that does not contain a dot, the full name value is used to construct a renderer from the associated renderer factory. In this case, the view configuration will create an instance of an MyAMFRenderer for each view configuration

8. RENDERERS

which includes amf as its renderer value. The name passed to the MyAMFRenderer constructor will always be amf.

Here's an example of the registration of a more complicated renderer factory, which expects to be passed a filesystem path:

```
1 config.add_renderer(name='.jinja2',
2 factory='my.package.MyJinja2Renderer')
```

Adding the above code to your application startup will allow you to use the my.package.MyJinja2Renderer renderer factory implementation in view configurations by referring to any renderer which *ends in*.jinja in the renderer attribute of a *view configuration*:

```
1 from pyramid.view import view_config
2
3 @view_config(renderer='templates/mytemplate.jinja2')
4 def myview(request):
5 return {'Hello':'world'}
```

When a *view configuration* is encountered at startup time, which has a name attribute that does contain a dot, the value of the name attribute is split on its final dot. The second element of the split is typically the filename extension. This extension is used to look up a renderer factory for the configured view. Then the value of renderer is passed to the factory to create a renderer for the view. In this case, the view configuration will create an instance of a MyJinja2Renderer for each view configuration which includes anything ending with .jinja2 in its renderer value. The name passed to the MyJinja2Renderer constructor will be the full value that was set as renderer= in the view configuration.

8.6.2 Changing an Existing Renderer

You can associate more than one filename extension with the same existing renderer implementation as necessary if you need to use a different file extension for the same kinds of templates. For example, to associate the .zpt extension with the Chameleon ZPT renderer factory, use the pyramid.config.Configurator.add_renderer() method:

config.add_renderer('.zpt', 'pyramid.chameleon_zpt.renderer_factory')

After you do this, Pyramid will treat templates ending in both the .pt and .zpt filename extensions as Chameleon ZPT templates.

To change the default mapping in which files with a .pt extension are rendered via a Chameleon ZPT page template renderer, use a variation on the following in your application's startup code:

```
config.add_renderer('.pt', 'mypackage.pt_renderer')
```

After you do this, the *renderer factory* in mypackage.pt_renderer will be used to render templates which end in .pt, replacing the default Chameleon ZPT renderer.

To associate a *default* renderer with *all* view configurations (even ones which do not possess a renderer attribute), pass None as the name attribute to the renderer tag:

```
config.add_renderer(None, 'mypackage.json_renderer_factory')
```

8.7 Overriding A Renderer At Runtime

This is an advanced feature, not typically used by "civilians".

In some circumstances, it is necessary to instruct the system to ignore the static renderer declaration provided by the developer in view configuration, replacing the renderer with another *after a request starts*. For example, an "omnipresent" XML-RPC implementation that detects that the request is from an XML-RPC client might override a view configuration statement made by the user instructing the view to use a template renderer with one that uses an XML-RPC renderer. This renderer would produce an XML-RPC representation of the data returned by an arbitrary view callable.

To use this feature, create a NewRequest *subscriber* which sniffs at the request data and which conditionally sets an override_renderer attribute on the request itself, which is the *name* of a registered renderer. For example:

```
from pyramid.event import subscriber
1
 from pyramid.event import NewRequest
2
3
  @subscriber(NewRequest)
4
  def set_xmlrpc_params(event):
5
      request = event.request
6
      if (request.content_type == 'text/xml'
7
               and request.method == 'POST'
8
               and not 'soapaction' in request.headers
9
               and not 'x-pyramid-avoid-xmlrpc' in request.headers):
10
          params, method = parse_xmlrpc_request(request)
11
          request.xmlrpc_params, request.xmlrpc_method = params, method
12
          request.is_xmlrpc = True
13
          request.override_renderer = 'xmlrpc'
14
          return True
15
```

8. RENDERERS

The result of such a subscriber will be to replace any existing static renderer configured by the developer with a (notional, nonexistent) XML-RPC renderer if the request appears to come from an XML-RPC client.

CHAPTER

NINE

TEMPLATES

A *template* is a file on disk which can be used to render dynamic data provided by a *view*. Pyramid offers a number of ways to perform templating tasks out of the box, and provides add-on templating support through a set of bindings packages.

Out of the box, Pyramid provides templating via the *Chameleon* and *Mako* templating libraries. *Chameleon* provides support for two different types of templates: *ZPT* templates, and text templates.

Before discussing how built-in templates are used in detail, we'll discuss two ways to render templates within Pyramid in general: directly, and via renderer configuration.

9.1 Using Templates Directly

The most straightforward way to use a template within Pyramid is to cause it to be rendered directly within a *view callable*. You may use whatever API is supplied by a given templating engine to do so.

Pyramid provides various APIs that allow you to render templates directly from within a view callable. For example, if there is a *Chameleon* ZPT template named foo.pt in a directory named templates in your application, you can render the template from within the body of a view callable like so:

Earlier iterations of this documentation (pre-version-1.3) encouraged the application developer to use **ZPT-specific** APIs such as pyramid.chameleon zpt.render template to response() and pyramid.chameleon zpt.render template() to render templates directly. This style of rendering still works, but at least for purposes of this documentation, those functions are deprecated. Application developers are encouraged instead to use the functions available in the pyramid.renderers module to perform rendering tasks. This set of functions works to render templates for all renderer extensions registered with Pyramid.

The sample_view *view callable* function above returns a *response* object which contains the body of the templates/foo.pt template. In this case, the templates directory should live in the same directory as the module containing the sample_view function. The template author will have the names foo and bar available as top-level names for replacement or comparison purposes.

In the example above, the path templates/foo.pt is relative to the directory containing the file which defines the view configuration. In this case, this is the directory containing the file that defines the sample_view function. Although a renderer path is usually just a simple relative pathname, a path named as a renderer can be absolute, starting with a slash on UNIX or a drive letter prefix on Windows.

Only *Chameleon* templates support defining a renderer for a template relative to the location of the module where the view callable is defined. Mako templates, and other templating system bindings work differently. In particular, Mako templates use a "lookup path" as defined by the mako.directories configuration file instead of treating relative paths as relative to the current view module. See *Templating With Mako Templates*.

The path can alternately be a *asset specification* in the form some.dotted.package_name:relative/path. This makes it possible to address template assets which live in another package. For example:

An asset specification points at a file within a Python *package*. In this case, it points at a file named foo.pt within the templates directory of the mypackage package. Using a asset specification instead of a relative template name is usually a good idea, because calls to render_to_response using asset specifications will continue to work properly if you move the code containing them around.

Make templating system bindings also respect absolute asset specifications as an argument to any of the render* commands. If a template name defines a : (colon) character and is not an absolute path, it is treated as an absolute asset specification.

In the examples above we pass in a keyword argument named request representing the current Pyramid request. Passing a request keyword argument will cause the render_to_response function to supply the renderer with more correct system values (see *System Values Used During Rendering*), because most of the information required to compose proper system values is present in the request. If your template relies on the name request or context, or if you've configured special *renderer globals*, make sure to pass request as a keyword argument in every call to to a pyramid.renderers.render_* function.

Every view must return a *response* object, except for views which use a *renderer* named via view configuration (which we'll see shortly). The pyramid.renderers.render_to_response() function is a shortcut function that actually returns a response object. This allows the example view above to simply return the result of its call to render_to_response() directly.

Obviously not all APIs you might call to get response data will return a response object. For example, you might render one or more templates to a string that you want to use as response data. The pyramid.renderers.render() API renders a template to a string. We can manufacture a *response* object directly, and use that string as the body of the response:

```
from pyramid.renderers import render
1
 from pyramid.response import Response
2
3
 def sample_view(request):
4
      result = render('mypackage:templates/foo.pt',
5
                       {'foo':1, 'bar':2},
6
                      request=request)
7
      response = Response(result)
8
      return response
```

Because *view callable* functions are typically the only code in Pyramid that need to know anything about templates, and because view functions are very simple Python, you can use whatever templating system you're most comfortable with within Pyramid. Install the templating system, import its API functions into your views module, use those APIs to generate a string, then return that string as the body of a Pyramid *Response* object.

For example, here's an example of using "raw" Mako from within a Pyramid view:

```
from mako.template import Template
from pyramid.response import Response
def make_view(request):
   template = Template(filename='/templates/template.mak')
   result = template.render(name=request.params['name'])
   response = Response(result)
   return response
```

You probably wouldn't use this particular snippet in a project, because it's easier to use the Mako renderer bindings which already exist in Pyramid. But if your favorite templating system is not supported as a renderer extension for Pyramid, you can create your own simple combination as shown above.

■ If you use third-party templating languages without cooperating Pyramid bindings directly within view callables, the auto-template-reload strategy explained in *Automatically Reloading Templates* will not be available, nor will the template asset overriding capability explained in *Overriding Assets* be available, nor will it be possible to use any template using that language as a *renderer*. However, it's reasonably easy to write custom templating system binding packages for use under Pyramid so that templates written in the language can be used as renderers. See *Adding and Changing Renderers* for instructions on how to create your own template renderer and *Available Add-On Template System Bindings* for example packages.

If you need more control over the status code and content-type, or other response attributes from views that use direct templating, you may set attributes on the response that influence these values.

Here's an example of changing the content-type and status of the response object returned by render_to_response():

```
from pyramid.renderers import render_to_response
1
2
 def sample view(request):
3
      response = render_to_response('templates/foo.pt',
4
                                      {'foo':1, 'bar':2},
5
                                      request=request)
6
      response.content_type = 'text/plain'
7
      response.status int = 204
8
      return response
9
```

Here's an example of manufacturing a response object using the result of render() (a string):

```
from pyramid.renderers import render
1
  from pyramid.response import Response
2
3
4
  def sample_view(request):
      result = render('mypackage:templates/foo.pt',
5
                       {'foo':1, 'bar':2},
6
                       request=request)
7
      response = Response(result)
8
9
      response.content_type = 'text/plain'
10
      return response
```

9.2 System Values Used During Rendering

When a template is rendered using render_to_response() or render(), the renderer representing the template will be provided with a number of *system* values. These values are provided in a dictionary to the renderer and include:

context The current Pyramid context if request was provided as a keyword argument, or None.

request The request provided as a keyword argument.

- renderer_name The renderer name used to perform the rendering, e.g.
 mypackage:templates/foo.pt.
- **renderer_info** An object implementing the pyramid.interfaces.IRendererInfo interface. Basically, an object with the following attributes: name, package and type.

You can define more values which will be passed to every template executed as a result of rendering by defining *renderer globals*.

What any particular renderer does with these system values is up to the renderer itself, but most template renderers, including Chameleon and Mako renderers, make these names available as top-level template variables.

9.3 Templates Used as Renderers via Configuration

An alternative to using render_to_response() to render templates manually in your view callable code, is to specify the template as a *renderer* in your *view configuration*. This can be done with any of the templating languages supported by Pyramid.

To use a renderer via view configuration, specify a template *asset specification* as the renderer argument, or attribute to the *view configuration* of a *view callable*. Then return a *dictionary* from that view callable. The dictionary items returned by the view callable will be made available to the renderer template as top-level names.

The association of a template as a renderer for a *view configuration* makes it possible to replace code within a *view callable* that handles the rendering of a template.

Here's an example of using a view_config decorator to specify a *view configuration* that names a template renderer:

```
from pyramid.view import view_config

def my_view(request):
    return {'foo':1, 'bar':2}
```

Vou do not need to supply the request value as a key in the dictionary result returned from a renderer-configured view callable. Pyramid automatically supplies this value for you so that the "most correct" system values are provided to the renderer.

The renderer argument to the @view_config configuration decorator shown above is the template *path*. In the example above, the path templates/foo.pt is *relative*. Relative to what, you ask? Because we're using a Chameleon renderer, it means "relative to the directory in which the file which defines the view configuration lives". In this case, this is the directory containing the file that defines the my_view function. View-configuration-relative asset specifications work only in Chameleon, not in Mako templates.

Similar renderer configuration can be done imperatively and via ZCML. See Writing View Callables Which Use a Renderer. See also Built-In Renderers.

Although a renderer path is usually just a simple relative pathname, a path named as a renderer can be absolute, starting with a slash on UNIX or a drive letter prefix on Windows. The path can alternately

be an *asset specification* in the form some.dotted.package_name:relative/path, making it possible to address template assets which live in another package.

Not just any template from any arbitrary templating system may be used as a renderer. Bindings must exist specifically for Pyramid to use a templating language template as a renderer. Currently, Pyramid has built-in support for two Chameleon templating languages: ZPT and text, and the Mako templating system. See *Built-In Renderers* for a discussion of their details. Pyramid also supports the use of *Jinja2* templates as renderers. See *Available Add-On Template System Bindings*.

Why Use A Renderer via View Configuration

Using a renderer in view configuration is usually a better way to render templates than using any rendering API directly from within a *view callable* because it makes the view callable more unit-testable. Views which use templating or rendering APIs directly must return a *Response* object. Making testing assertions about response objects is typically an indirect process, because it means that your test code often needs to somehow parse information out of the response body (often HTML). View callables configured with renderers externally via view configuration typically return a dictionary, as above. Making assertions about results returned in a dictionary is almost always more direct and straightforward than needing to parse HTML. Specifying a renderer from within *ZCML* (as opposed to imperatively or via a view_config decorator, or using a template directly from within a view callable) also makes it possible for someone to modify the template used to render a view without needing to fork your code to do so. See *Extending An Existing Pyramid Application* for more information.

By default, views rendered via a template renderer return a *Response* object which has a *status code* of 200 OK, and a *content-type* of text/html. To vary attributes of the response of a view that uses a renderer, such as the content-type, headers, or status attributes, you must use the API of the pyramid.response.Response object exposed as request.response within the view before returning the dictionary. See *Varying Attributes of Rendered Responses* for more information.

The same set of system values are provided to templates rendered via a renderer view configuration as those provided to templates rendered imperatively. See *System Values Used During Rendering*.

9.4 Chameleon ZPT Templates

Like *Zope*, Pyramid uses *ZPT* (Zope Page Templates) as its default templating language. However, Pyramid uses a different implementation of the *ZPT* specification than Zope does: the *Chameleon* templating engine. The Chameleon engine complies largely with the Zope Page Template template specification. However, it is significantly faster.

The language definition documentation for Chameleon ZPT-style templates is available from the Chameleon website.

Chameleon only works on *CPython* platforms and *Google App Engine*. On *Jython* and other non-CPython platforms, you should use Mako (see *Templating With Mako Templates*) or pyramid_jinja2 instead. See *Available Add-On Template System Bindings*.

Given a *Chameleon* ZPT template named foo.pt in a directory in your application named templates, you can render the template as a *renderer* like so:

```
from pyramid.view import view_config

deview_config(renderer='templates/foo.pt')

def my_view(request):
    return {'foo':1, 'bar':2}
```

See also *Built-In Renderers* for more general information about renderers, including Chameleon ZPT renderers.

9.4.1 A Sample ZPT Template

Here's what a simple Chameleon ZPT template used under Pyramid might look like:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
       "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
2
   <html xmlns="http://www.w3.org/1999/xhtml"
3
         xmlns:tal="http://xml.zope.org/namespaces/tal">
4
   <head>
5
       <meta http-equiv="content-type" content="text/html; charset=utf-8" />
6
       <title>${project} Application</title>
7
   </head>
8
     <bodv>
9
        <h1 class="title">Welcome to <code>${project}</code>, an
10
         application generated by the <a
11
         href="http://docs.pylonsproject.org/projects/pyramid/current/"
12
        >pyramid</a> web
13
         application framework.</hl>
14
     </body>
15
   </html>
16
```

Note the use of *Genshi*-style \${replacements} above. This is one of the ways that *Chameleon* ZPT differs from standard ZPT. The above template expects to find a project key in the set of keywords passed in to it via render() or render_to_response(). Typical ZPT attribute-based syntax (e.g. tal:content and tal:replace) also works in these templates.

9.4.2 Using ZPT Macros in Pyramid

When a *renderer* is used to render a template, Pyramid makes at least two top-level names available to the template by default: context and request. One of the common needs in ZPT-based templates is to use one template's "macros" from within a different template. In Zope, this is typically handled by retrieving the template from the context. But the context in Pyramid is a *resource* object, and templates cannot usually be retrieved from resources. To use macros in Pyramid, you need to make the macro template itself available to the rendered template by passing the macro template, or even the macro itself, *into* the rendered template. To do this you can use the pyramid.renderers.get_renderer() API to retrieve the macro template, and pass it into the template being rendered via the dictionary returned by the view. For example, using a *view configuration* via a view_config decorator that uses a *renderer*:

```
1 from pyramid.renderers import get_renderer
2 from pyramid.view import view_config
3
4 @view_config(renderer='templates/mytemplate.pt')
5 def my_view(request):
6 main = get_renderer('templates/master.pt').implementation()
7 return {'main':main}
```

Where templates/master.pt might look like so:

```
<html xmlns="http://www.w3.org/1999/xhtml"
1
         xmlns:tal="http://xml.zope.org/namespaces/tal"
2
         xmlns:metal="http://xml.zope.org/namespaces/metal">
3
     <span metal:define-macro="hello">
4
       <h1>
5
         Hello <span metal:define-slot="name">Fred</span>!
6
7
       </h1>
     </span>
8
   </html>
```

And templates/mytemplate.pt might look like so:

```
1 <html xmlns="http://www.w3.org/1999/xhtml"
2 xmlns:tal="http://xml.zope.org/namespaces/tal"
3 xmlns:metal="http://xml.zope.org/namespaces/metal">
4 <span metal="http://xml.zope.org/namespaces/metal">
5 <span metal="http://xml.zope.org/namespaces/metal">
6 </span>
7 </html>
```

9.5 Templating with Chameleon Text Templates

Pyramid also allows for the use of templates which are composed entirely of non-XML text via *Chameleon*. To do so, you can create templates that are entirely composed of text except for \${name} -style substitution points.

Here's an example usage of a Chameleon text template. Create a file on disk named mytemplate.txt in your project's templates directory with the following contents:

```
Hello, ${name}!
```

Then in your project's views.py module, you can create a view which renders this template:

```
1 from pyramid.view import view_config
2
3 @view_config(renderer='templates/mytemplate.txt')
4 def my_view(request):
5 return {'name':'world'}
```

When the template is rendered, it will show:

```
Hello, world!
```

If you'd rather use templates directly within a view callable (without the indirection of using a renderer), see *pyramid.chameleon_text* for the API description.

See also *Built-In Renderers* for more general information about renderers, including Chameleon text renderers.

9.6 Side Effects of Rendering a Chameleon Template

When a Chameleon template is rendered from a file, the templating engine writes a file in the same directory as the template file itself as a kind of cache, in order to do less work the next time the template needs to be read from disk. If you see "strange" .py files showing up in your templates directory (or otherwise directly "next" to your templates), it is due to this feature.

If you're using a version control system such as Subversion, you should configure it to ignore these files. Here's the contents of the author's svn propedit svn:ignore . in each of my templates directories.

```
*.pt.py
*.txt.py
```

Note that I always name my Chameleon ZPT template files with a .pt extension and my Chameleon text template files with a .txt extension so that these svn:ignore patterns work.

9.7 Nicer Exceptions in Chameleon Templates

The exceptions raised by Chameleon templates when a rendering fails are sometimes less than helpful. Pyramid allows you to configure your application development environment so that exceptions generated by Chameleon during template compilation and execution will contain nicer debugging information.

Template-debugging behavior is not recommended for production sites as it slows renderings; it's usually only desirable during development.

In order to turn on template exception debugging, you can use an environment variable setting or a configuration file setting.

To use an environment variable, start your application under a shell using the PYRAMID_DEBUG_TEMPLATES operating system environment variable set to 1, For example:

\$ PYRAMID_DEBUG_TEMPLATES=1 bin/paster serve myproject.ini

To use a setting in the application .ini file for the same purpose, set the debug_templates key to true within the application's configuration section, e.g.:

```
1 [app:MyProject]
2 use = egg:MyProject#app
3 debug_templates = true
```

With template debugging off, a NameError exception resulting from rendering a template with an undefined variable (e.g. \${wrong}) might end like this:

```
File "...", in __getitem__
raise NameError(key)
NameError: wrong
```

Note that the exception has no information about which template was being rendered when the error occured. But with template debugging on, an exception resulting from the same problem might end like so:

```
RuntimeError: Caught exception rendering template.
        - Expression: ``wrong``
        - Filename: /home/fred/env/proj/proj/templates/mytemplate.pt
        - Arguments: renderer_name: proj:templates/mytemplate.pt
        template: <PageTemplateFile - at 0x1d2ecf0>
        xincludes: <XIncludes - at 0x1d3a130>
        request: <Request - at 0x1d2ecd0>
        project: proj
        macros: <Macros - at 0x1d3aed0>
        context: <MyResource None at 0x1d39130>
        view: <function my_view at 0x1d23570>
NameError: wrong
```

The latter tells you which template the error occurred in, as well as displaying the arguments passed to the template itself.

U Turning on debug_templates has the same effect as using the Chameleon environment variable CHAMELEON_DEBUG. See Chameleon Environment Variables for more information.

9.8 Chameleon Template Internationalization

See Chameleon Template Support for Translation Strings for information about supporting internationalized units of text within Chameleon templates.

9.9 Templating With Mako Templates

Mako is a templating system written by Mike Bayer. Pyramid has built-in bindings for the Mako templating system. The language definition documentation for Mako templates is available from the Mako website.

To use a Mako template, given a *Mako* template file named foo.mak in the templates subdirectory in your application package named mypackage, you can configure the template as a *renderer* like so:

```
1 from pyramid.view import view_config
2
3 @view_config(renderer='foo.mak')
4 def my_view(request):
5 return {'project':'my project'}
```

For the above view callable to work, the following setting needs to be present in the application stanza of your configuration's ini file:

```
mako.directories = mypackage:templates
```

This lets the Mako templating system know that it should look for templates in the templates subdirectory of the mypackage Python package. See *Mako Template Render Settings* for more information about the mako.directories setting and other Mako-related settings that can be placed into the application's ini file.

9.9.1 A Sample Mako Template

Here's what a simple *Mako* template used under Pyramid might look like:

```
<html>
1
   <head>
2
       <title>${project} Application</title>
3
   </head>
4
     <body>
5
        <h1 class="title">Welcome to <code>${project}</code>, an
6
         application generated by the <a
7
         href="http://docs.pylonsproject.org/projects/pyramid/current/"
8
        >pyramid</a> web application framework.</hl>
9
     </body>
10
   </html>
11
```

This template doesn't use any advanced features of Mako, only the $\{\}$ replacement syntax for names that are passed in as *renderer globals*. See the the Mako documentation to use more advanced features.

9.10 Automatically Reloading Templates

It's often convenient to see changes you make to a template file appear immediately without needing to restart the application process. Pyramid allows you to configure your application development environment so that a change to a template will be automatically detected, and the template will be reloaded on the next rendering.

Auto-template-reload behavior is not recommended for production sites as it slows rendering slightly; it's usually only desirable during development.

In order to turn on automatic reloading of templates, you can use an environment variable, or a configuration file setting.

To use an environment variable, start your application under a shell using the PYRAMID_RELOAD_TEMPLATES operating system environment variable set to 1, For example:

\$ PYRAMID_RELOAD_TEMPLATES=1 bin/paster serve myproject.ini

To use a setting in the application .ini file for the same purpose, set the reload_templates key to true within the application's configuration section, e.g.:

```
1 [app:main]
2 use = egg:MyProject#app
3 reload_templates = true
```

9.11 Available Add-On Template System Bindings

Jinja2 template bindings are available for Pyramid in the pyramid_jinja2 package. You can get the latest release of this package from the Python package index (pypi).

CHAPTER

TEN

VIEW CONFIGURATION

View lookup is the Pyramid subsystem responsible for finding and invoking a *view callable. View configuration* controls how *view lookup* operates in your application. During any given request, view configuration information is compared against request data by the view lookup subsystem in order to find the "best" view callable for that request.

In earlier chapters, you have been exposed to a few simple view configuration declarations without much explanation. In this chapter we will explore the subject in detail.

10.1 Mapping a Resource or URL Pattern to a View Callable

A developer makes a *view callable* available for use within a Pyramid application via *view configuration.* A view configuration associates a view callable with a set of statements that determine the set of circumstances which must be true for the view callable to be invoked.

A view configuration statement is made about information present in the *context* resource and the *request*.

View configuration is performed in one of two ways:

- by running a *scan* against application source code which has a pyramid.view.view_config decorator attached to a Python object as per *Adding View Configuration Using the @view_config Decorator*.
- by using the pyramid.config.Configurator.add_view() method as per Adding View Configuration Using add_view().

10.1.1 View Configuration Parameters

All forms of view configuration accept the same general types of arguments.

Many arguments supplied during view configuration are *view predicate* arguments. View predicate arguments used during view configuration are used to narrow the set of circumstances in which *view lookup* will find a particular view callable.

View predicate attributes are an important part of view configuration that enables the *view lookup* subsystem to find and invoke the appropriate view. The greater number of predicate attributes possessed by a view's configuration, the more specific the circumstances need to be before the registered view callable will be invoked. The fewer number of predicates which are supplied to a particular view configuration, the more likely it is that the associated view callable will be invoked. A view with five predicates will always be found and evaluated before a view with two, for example. All predicates must match for the associated view to be called.

This does not mean however, that Pyramid "stops looking" when it finds a view registration with predicates that don't match. If one set of view predicates does not match, the "next most specific" view (if any) is consulted for predicates, and so on, until a view is found, or no view can be matched up with the request. The first view with a set of predicates all of which match the request environment will be invoked.

If no view can be found with predicates which allow it to be matched up with the request, Pyramid will return an error to the user's browser, representing a "not found" (404) page. See *Changing the Not Found View* for more information about changing the default notfound view.

Other view configuration arguments are non-predicate arguments. These tend to modify the response of the view callable or prevent the view callable from being invoked due to an authorization policy. The presence of non-predicate arguments in a view configuration does not narrow the circumstances in which the view callable will be invoked.

Non-Predicate Arguments

permission The name of a *permission* that the user must possess in order to invoke the *view callable*. See *Configuring View Security* for more information about view security and permissions.

If permission is not supplied, no permission is registered for this view (it's accessible by any caller).

attr The view machinery defaults to using the __call__ method of the view callable (or the function itself, if the view callable is a function) to obtain a response. The attr value allows you to vary the method attribute used to obtain the response. For example, if your view was a class, and the class has a method named index and you wanted to use this method instead of the class' __call__ method to return the response, you'd say attr="index" in the view configuration for the view. This is most useful when the view definition is a class.

If attr is not supplied, None is used (implying the function itself if the view is a function, or the ______ call___ callable attribute if the view is a class).

renderer Denotes the *renderer* implementation which will be used to construct a *response* from the associated view callable's return value. (see also *Renderers*).

This is either a single string term (e.g. json) or a string implying a path or *asset specification* (e.g. templates/views.pt) naming a *renderer* implementation. If the renderer value does not contain a dot (.), the specified string will be used to look up a renderer implementation, and that renderer implementation will be used to construct a response from the view return value. If the renderer value contains a dot (.), the specified term will be treated as a path, and the filename extension of the last element in the path will be used to look up the renderer implementation, which will be passed the full path.

When the renderer is a path, although a path is usually just a simple relative pathname (e.g. templates/foo.pt, implying that a template named "foo.pt" is in the "templates" directory relative to the directory of the current *package*), a path can be absolute, starting with a slash on UNIX or a drive letter prefix on Windows. The path can alternately be a *asset specification* in the form some.dotted.package_name:relative/path, making it possible to address template assets which live in a separate package.

The renderer attribute is optional. If it is not defined, the "null" renderer is assumed (no rendering is performed and the value is passed back to the upstream Pyramid machinery unchanged). Note that if the view callable itself returns a *response* (see *View Callable Responses*), the specified renderer implementation is never called.

- http_cache When you supply an http_cache value to a view configuration, the Expires and Cache-Control headers of a response generated by the associated view callable are modified. The value for http_cache may be one of the following:
 - A nonzero integer. If it's a nonzero integer, it's treated as a number of seconds. This number of seconds will be used to compute the Expires header and the Cache-Control: max-age parameter of responses to requests which call this view. For example: http_cache=3600 instructs the requesting browser to 'cache this response for an hour, please'.

- A datetime.timedelta instance. If it's a datetime.timedelta instance, it will be converted into a number of seconds, and that number of seconds will be used to compute the Expires header and the Cache-Control: max-age parameter of responses to requests which call this view. For example: http_cache=datetime.timedelta(days=1) instructs the requesting browser to 'cache this response for a day, please'.
- Zero (0). If the value is zero, the Cache-Control and Expires headers present in all responses from this view will be composed such that client browser cache (and any intermediate caches) are instructed to never cache the response.
- A two-tuple. If it's a two tuple (e.g. http_cache=(1, {'public':True})), the first value in the tuple may be a nonzero integer or a datetime.timedelta instance; in either case this value will be used as the number of seconds to cache the response. The second value in the tuple must be a dictionary. The values present in the dictionary will be used as input to the Cache-Control response header. For example: http_cache=(3600, {'public':True}) means 'cache for an hour, and add public to the Cache-Control header of the response'. All keys and values supported by the webob.cachecontrol.CacheControl interface may be added to the dictionary. Supplying {'public':True} is equivalent to calling response.cache_control.public = True.

Providing a non-tuple value as http_cache is equivalent to calling
response.cache_expires(value) within your view's body.

Providing a two-tuple value as http_cache is equivalent to calling
response.cache_expires(value[0], **value[1]) within your view's body.

If you wish to avoid influencing, the Expires header, and instead wish to only influence Cache-Control headers, pass a tuple as http_cache with the first element of None, e.g.: (None, {'public':True}).

wrapper The view name of a different view configuration which will receive the response body of this view as the request.wrapped_body attribute of its own request, and the response returned by this view as the request.wrapped_response attribute of its own request. Using a wrapper makes it possible to "chain" views together to form a composite response. The response of the outermost wrapper view will be returned to the user. The wrapper view will be found as any view is found: see View Configuration. The "best" wrapper view will be found based on the lookup ordering: "under the hood" this wrapper view is looked up via pyramid.view.render_view_to_response(context, request, 'wrapper_viewname'). The context and request of a wrapper view is the same context and request of the inner view.

If wrapper is not supplied, no wrapper view is used.

- **decorator** A *dotted Python name* to a function (or the function itself) which will be used to decorate the registered *view callable*. The decorator function will be called with the view callable as a single argument. The view callable it is passed will accept (context, request). The decorator must return a replacement view callable which also accepts (context, request).
- **mapper** A Python object or *dotted Python name* which refers to a *view mapper*, or None. By default it is None, which indicates that the view should use the default view mapper. This plug-point is useful for Pyramid extension developers, but it's not very useful for 'civilians' who are just developing stock Pyramid applications. Pay no attention to the man behind the curtain.

Predicate Arguments

These arguments modify view lookup behavior. In general, the more predicate arguments that are supplied, the more specific, and narrower the usage of the configured view.

name The *view name* required to match this view callable. A name argument is typically only used when your application uses *traversal*. Read *Traversal* to understand the concept of a view name.

If name is not supplied, the empty string is used (implying the default view).

context An object representing a Python class that the *context* resource must be an instance of *or* the *interface* that the *context* resource must provide in order for this view to be found and called. This predicate is true when the *context* resource is an instance of the represented class or if the *context* resource provides the represented interface; it is otherwise false.

If context is not supplied, the value None, which matches any resource, is used.

route_name If route_name is supplied, the view callable will be invoked only when the named route has matched.

This value must match the name of a *route configuration* declaration (see *URL Dispatch*) that must match before this view will be called. Note that the route configuration referred to by route_name will usually have a *traverse token in the value of its pattern, representing a part of the path that will be used by *traversal* against the result of the route's *root factory*.

If route_name is not supplied, the view callable will only have a chance of being invoked if no other route was matched. This is when the request/context pair found via *resource location* does not indicate it matched any configured route.

request_type This value should be an interface that the request must provide in order for this view
to be found and called.

If request_type is not supplied, the value None is used, implying any request type.

This is an advanced feature, not often used by "civilians".

10. VIEW CONFIGURATION

request_method This value can be one of the strings GET, POST, PUT, DELETE, or HEAD representing an HTTP REQUEST_METHOD. A view declaration with this argument ensures that the view will only be called when the request's method attribute (aka the REQUEST_METHOD of the WSGI environment) string matches the supplied value.

If request_method is not supplied, the view will be invoked regardless of the REQUEST_METHOD of the WSGI environment.

request_param This value can be any string. A view declaration with this argument ensures that the view will only be called when the *request* has a key in the request.params dictionary (an HTTP GET or POST variable) that has a name which matches the supplied value.

If the value supplied has a = sign in it, e.g. request_param="foo=123", then the key (foo) must both exist in the request .params dictionary, *and* the value must match the right hand side of the expression (123) for the view to "match" the current request.

If request_param is not supplied, the view will be invoked without consideration of keys and values in the request.params dictionary.

containment This value should be a reference to a Python class or *interface* that a parent object in the context resource's *lineage* must provide in order for this view to be found and called. The resources in your resource tree must be "location-aware" to use this feature.

If containment is not supplied, the interfaces and classes in the lineage are not considered when deciding whether or not to invoke the view callable.

See Location-Aware Resources for more information about location-awareness.

xhr This value should be either True or False. If this value is specified and is True, the WSGI environment must possess an HTTP_X_REQUESTED_WITH (aka X-Requested-With) header that has the value XMLHttpRequest for the associated view callable to be found and called. This is useful for detecting AJAX requests issued from jQuery, Prototype and other Javascript libraries.

If xhr is not specified, the HTTP_X_REQUESTED_WITH HTTP header is not taken into consideration when deciding whether or not to invoke the associated view callable.

accept The value of this argument represents a match query for one or more mimetypes in the Accept HTTP request header. If this value is specified, it must be in one of the following forms: a mimetype match token in the form text/plain, a wildcard mimetype match token in the form text/* or a match-all wildcard mimetype match token in the form */*. If any of the forms matches the Accept header of the request, this predicate will be true.

If accept is not specified, the HTTP_ACCEPT HTTP header is not taken into consideration when deciding whether or not to invoke the associated view callable.

header This value represents an HTTP header name or a header name/value pair.

If header is specified, it must be a header name or a headername: headervalue pair.

If header is specified without a value (a bare header name only, e.g. If-Modified-Since), the view will only be invoked if the HTTP header exists with any value in the request.

If header is specified, and possesses a name/value pair (e.g. User-Agent:Mozilla/.*), the view will only be invoked if the HTTP header exists *and* the HTTP header matches the value requested. When the headervalue contains a : (colon), it will be considered a name/value pair (e.g. User-Agent:Mozilla/.* or Host:localhost). The value portion should be a regular expression.

Whether or not the value represents a header name or a header name/value pair, the case of the header name is not significant.

If header is not specified, the composition, presence or absence of HTTP headers is not taken into consideration when deciding whether or not to invoke the associated view callable.

path_info This value represents a regular expression pattern that will be tested against the PATH_INFO WSGI environment variable to decide whether or not to call the associated view callable. If the regex matches, this predicate will be True.

If path_info is not specified, the WSGI PATH_INFO is not taken into consideration when deciding whether or not to invoke the associated view callable.

custom_predicates If custom_predicates is specified, it must be a sequence of references to custom predicate callables. Use custom predicates when no set of predefined predicates do what you need. Custom predicates can be combined with predefined predicates as necessary. Each custom predicate callable should accept two arguments: context and request and should return either True or False after doing arbitrary evaluation of the context resource and/or the request. If all callables return True, the associated view callable will be considered viable for a given request.

If custom_predicates is not specified, no custom predicates are used.

10.1.2 Adding View Configuration Using the @view_config Decorator

Using this feature tends to slows down application startup slightly, as more work is performed at application startup to scan for view configuration declarations. For maximum startup performance, use the view configuration method described in *Adding View Configuration Using add_view()* instead.

The view_config decorator can be used to associate *view configuration* information with a function, method, or class that acts as a Pyramid view callable.

Here's an example of the view_config decorator that lives within a Pyramid application module views.py:

```
1 from resources import MyResource
2 from pyramid.view import view_config
3 from pyramid.response import Response
4 
5 @view_config(route_name='ok', request_method='POST', permission='read')
6 def my_view(request):
7 return Response('OK')
```

Using this decorator as above replaces the need to add this imperative configuration stanza:

```
1 config.add_view('mypackage.views.my_view', route_name='ok',
2 request_method='POST', permission='read')
```

All arguments to view_config may be omitted. For example:

```
1 from pyramid.response import Response
2 from pyramid.view import view_config
3
4 @view_config()
5 def my_view(request):
6 """ My view """
7 return Response()
```

Such a registration as the one directly above implies that the view name will be my_view, registered with a context argument that matches any resource type, using no permission, registered against requests with any request method, request type, request param, route name, or containment.

The mere existence of a @view_config decorator doesn't suffice to perform view configuration. All that the decorator does is "annotate" the function with your configuration declarations, it doesn't process them. To make Pyramid process your pyramid.view.view_config declarations, you *must* use the scan method of a pyramid.config.Configurator:

```
1 # config is assumed to be an instance of the
```

```
2 # pyramid.config.Configurator class
```

```
3 config.scan()
```

Please see *Declarative Configuration* for detailed information about what happens when code is scanned for configuration declarations resulting from use of decorators like view_config.

See *pyramid.config* for additional API arguments to the scan() method. For example, the method allows you to supply a package argument to better control exactly *which* code will be scanned.

All arguments to the view_config decorator mean precisely the same thing as they would if they were passed as arguments to the pyramid.config.Configurator.add_view() method save for the view argument. Usage of the view_config decorator is a form of *declarative configuration*, while pyramid.config.Configurator.add_view() is a form of *imperative configuration*. However, they both do the same thing.

@view_config Placement

A view_config decorator can be placed in various points in your application.

If your view callable is a function, it may be used as a function decorator:

```
from pyramid.view import view_config
from pyramid.response import Response

def edit(request):
    return Response('edited!')
```

If your view callable is a class, the decorator can also be used as a class decorator in Python 2.6 and better (Python 2.5 and below do not support class decorators). All the arguments to the decorator are the same when applied against a class as when they are applied against a function. For example:

```
from pyramid.response import Response
1
2 from pyramid.view import view_config
3
  @view_config(route_name='hello')
4
  class MyView(object):
5
      def __init__(self, request):
6
          self.request = request
7
8
      def __call__(self):
9
          return Response('hello')
10
```

You can use the view_config decorator as a simple callable to manually decorate classes in Python 2.5 and below without the decorator syntactic sugar, if you wish:

```
1 from pyramid.response import Response
  from pyramid.view import view_config
2
3
  class MyView(object):
4
      def __init__(self, request):
5
          self.request = request
6
7
      def __call__(self):
8
          return Response('hello')
9
10
  my_view = view_config(route_name='hello')(MyView)
11
```

More than one view_config decorator can be stacked on top of any number of others. Each decorator creates a separate view registration. For example:

```
1 from pyramid.view import view_config
2 from pyramid.response import Response
3
4 @view_config(route_name='edit')
5 @view_config(route_name='change')
6 def edit(request):
7 return Response('edited!')
```

This registers the same view under two different names.

The decorator can also be used against a method of a class:

```
1 from pyramid.response import Response
  from pyramid.view import view_config
2
3
  class MyView(object):
4
      def __init__(self, request):
5
           self.request = request
6
7
      @view_config(route_name='hello')
8
      def amethod(self):
9
          return Response('hello')
10
```

When the decorator is used against a method of a class, a view is registered for the *class*, so the class constructor must accept an argument list in one of two forms: either it must accept a single argument request or it must accept two arguments, context, request.

The method which is decorated must return a *response*.

Using the decorator against a particular method of a class is equivalent to using the attr parameter in a decorator attached to the class itself. For example, the above registration implied by the decorator being used against the amethod method could be spelled equivalently as the below:

```
from pyramid.response import Response
1
  from pyramid.view import view_config
2
3
  @view_config(attr='amethod', route_name='hello')
4
  class MyView(object):
5
      def __init__(self, request):
6
          self.request = request
7
8
      def amethod(self):
9
          return Response('hello')
10
```

10.1.3 Adding View Configuration Using add_view()

The pyramid.config.Configurator.add_view() method within *pyramid.config* is used to configure a view "imperatively" (without a view_config decorator). The arguments to this method are very similar to the arguments that you provide to the view_config decorator. For example:

```
from pyramid.response import Response
def hello_world(request):
    return Response('hello!')

    # config is assumed to be an instance of the
    # pyramid.config.Configurator class
    config.add_view(hello_world, route_name='hello')
```

The first argument, view, is required. It must either be a Python object which is the view itself or a *dotted Python name* to such an object. In the above example, view is the hello_world function. All other arguments are optional. See pyramid.config.Configurator.add_view() for more information.

When you use only add_view() to add view configurations, you don't need to issue a *scan* in order for the view configuration to take effect.

10.1.4 Configuring View Security

If an *authorization policy* is active, any *permission* attached to a *view configuration* found during view lookup will be verified. This will ensure that the currently authenticated user possesses that permission against the *context* resource before the view function is actually called. Here's an example of specifying a permission in a view configuration using add_view():

When an *authorization policy* is enabled, this view will be protected with the add permission. The view will *not be called* if the user does not possess the add permission relative to the current *context*. Instead the *forbidden view* result will be returned to the client as per *Protecting Views with Permissions*.

10.1.5 NotFound Errors

It's useful to be able to debug NotFound error responses when they occur unexpectedly due to an application registry misconfiguration. To debug these errors, use the PYRAMID_DEBUG_NOTFOUND environment variable or the debug_notfound configuration file setting. Details of why a view was not found will be printed to stderr, and the browser representation of the error will include the same information. See *Environment Variables and .ini File Settings* for more information about how, and where to set these values.

10.2 Influencing HTTP Caching

This feature is new in Pyramid 1.1.

When a non-None http_cache argument is passed to a view configuration, Pyramid will set Expires and Cache-Control response headers in the resulting response, causing browsers to cache the response data for some time. See http_cache in *Non-Predicate Arguments* for the its allowable values and what they mean.

Sometimes it's undesirable to have these headers set as the result of returning a response from a view, even though you'd like to decorate the view with a view configuration decorator that has http_cache. Perhaps there's an alternate branch in your view code that returns a response that should never be cacheable, while the "normal" branch returns something that should always be cacheable. If this is the case, set the prevent_auto attribute of the response.cache_control object to a non-False value. For example, the below view callable is configured with a @view_config decorator that indicates any response from the view should be cached for 3600 seconds. However, the view itself prevents caching from taking place unless there's a should_cache GET or POST variable:

```
from pyramid.view import view_config
@view_config(http_cache=3600)
def view(request):
    response = Response()
    if not 'should_cache' in request.params:
        response.cache_control.prevent_auto = True
    return response
```

Note that the http_cache machinery will overwrite or add to caching headers you set within the view itself unless you use preserve_auto.

You can also turn of the effect of http_cache entirely for the duration of a Pyramid application lifetime. To do so, set the PYRAMID_PREVENT_HTTP_CACHE environment variable or the prevent_http_cache configuration value setting to a true value. For more information, see *Preventing HTTP Caching*.

Note that setting prevent_http_cache will have no effect on caching headers that your application code itself sets. It will only prevent caching headers that would have been set by the Pyramid HTTP caching machinery invoked as the result of the http_cache argument to view configuration.

10.3 Debugging View Configuration

See *Displaying Matching Views for a Given URL* for information about how to display each of the view callables that might match for a given URL. This can be an effective way to figure out why a particular view callable is being called instead of the one you'd like to be called.

10. VIEW CONFIGURATION

CHAPTER ELEVEN

STATIC ASSETS

An *asset* is any file contained within a Python *package* which is *not* a Python source code file. For example, each of the following is an asset:

- a GIF image file contained within a Python package or contained within any subdirectory of a Python package.
- a CSS file contained within a Python package or contained within any subdirectory of a Python package.
- a JavaScript source file contained within a Python package or contained within any subdirectory of a Python package.
- A directory within a package that does not have an <u>___init__</u>.py in it (if it possessed an <u>___init__</u>.py it would *be* a package).
- a *Chameleon* or *Mako* template file contained within a Python package.

The use of assets is quite common in most web development projects. For example, when you create a Pyramid application using one of the available scaffolds, as described in *Creating the Project*, the directory representing the application contains a Python *package*. Within that Python package, there are directories full of files which are static assets. For example, there's a static directory which contains .css,.js, and .gif files. These asset files are delivered when a user visits an application URL.

11.1 Understanding Asset Specifications

Let's imagine you've created a Pyramid application that uses a *Chameleon* ZPT template via the pyramid.renderers.render_to_response() API. For example, the application might address the asset using the *asset specification* myapp:templates/some_template.pt using that API within a views.py file inside a myapp package:

```
1 from pyramid.renderers import render_to_response
2 render_to_response('myapp:templates/some_template.pt', {}, request)
```

"Under the hood", when this API is called, Pyramid attempts to make sense out of the string myapp:templates/some_template.pt provided by the developer. This string is an *asset specification*. It is composed of two parts:

- The package name (myapp)
- The asset name (templates/some_template.pt), relative to the package directory.

The two parts are separated by the colon character.

Pyramid uses the Python *pkg_resources* API to resolve the package name and asset name to an absolute (operating-system-specific) file name. It eventually passes this resolved absolute filesystem path to the Chameleon templating engine, which then uses it to load, parse, and execute the template file.

There is a second form of asset specification: a *relative* asset specification. Instead of using an "absolute" asset specification which includes the package name, in certain circumstances you can omit the package name from the specification. For example, you might be able to use templates/mytemplate.pt instead of myapp:templates/some_template.pt. Such asset specifications are usually relative to a "current package." The "current package" is usually the package which contains the code that *uses* the asset specification. Pyramid APIs which accept relative asset specifications typically describe what the asset is relative to in their individual documentation.

11.2 Serving Static Assets

Pyramid makes it possible to serve up static asset files from a directory on a filesystem to an application user's browser. Use the pyramid.config.Configurator.add_static_view() to instruct Pyramid to serve static assets such as JavaScript and CSS files. This mechanism makes a directory of static files available at a name relative to the application root URL, e.g. /static or as an external URL.

add_static_view() cannot serve a single file, nor can it serve a directory of static files directly relative to the root URL of a Pyramid application. For these features, see *Advanced: Serving Static Assets Using a View Callable*.

Here's an example of a use of add_static_view() that will serve files up from the /var/www/static directory of the computer which runs the Pyramid application as URLs beneath the /static URL prefix.

```
1 # config is an instance of pyramid.config.Configurator
2 config.add_static_view(name='static', path='/var/www/static')
```

The name prepresents a URL *prefix*. In order for files that live in the path directory to be served, a URL that requests one of them must begin with that prefix. In the example above, name is static, and path is /var/www/static. In English, this means that you wish to serve the files that live in /var/www/static as sub-URLs of the /static URL prefix. Therefore, the file /var/www/static/foo.css will be returned when the user visits your application's URL /static/foo.css.

A static directory named at path may contain subdirectories recursively, and any subdirectories may hold files; these will be resolved by the static view as you would expect. The Content-Type header returned by the static view for each particular type of file is dependent upon its file extension.

By default, all files made available via add_static_view() are accessible by completely anonymous users. Simple authorization can be required, however. To protect a set of static files using a permission, in addition to passing the required name and path arguments, also pass the permission keyword argument to add_static_view(). The value of the permission argument represents the *permission* that the user must have relative to the current *context* when the static view is invoked. A user will be required to possess this permission to view any of the files represented by path of the static view. If your static assets must be protected by a more complex authorization scheme, see *Advanced: Serving Static Assets Using a View Callable*.

Here's another example that uses an *asset specification* instead of an absolute path as the path argument. To convince add_static_view() to serve files up under the /static URL from the a/b/c/static directory of the Python package named some_package, we can use a fully qualified *asset specification* as the path:

```
1 # config is an instance of pyramid.config.Configurator
2 config.add_static_view(name='static', path='some_package:a/b/c/static')
```

The path provided to add_static_view() may be a fully qualified *asset specification* or an *absolute path*.

Instead of representing a URL prefix, the name argument of a call to add_static_view() can alternately be a *URL*. Each of examples we've seen so far have shown usage of the name argument as a URL prefix. However, when name is a *URL*, static assets can be served from an external webserver. In this mode, the name is used as the URL prefix when generating a URL using pyramid.url.static_url().

For example, add_static_view() may be fed a name argument which is http://example.com/images:

```
1 # config is an instance of pyramid.config.Configurator
2 config.add_static_view(name='http://example.com/images',
3 path='mypackage:images')
```

Because add_static_view() is provided with a name argument that is the URL http://example.com/images, subsequent calls to static_url() with paths that start with the path argument passed to add_static_view() will generate a URL something like http://example.com/images/logo.png. The external webserver listening on example.com must be itself configured to respond properly to such a request. The static_url() API is discussed in more detail later in this chapter.

11.2.1 Generating Static Asset URLs

When a add_static_view() method is used to register a static asset directory, a special helper API named pyramid.url.static_url() can be used to generate the appropriate URL for an asset that lives in one of the directories named by the static registration path attribute.

For example, let's assume you create a set of static declarations like so:

```
1 config.add_static_view(name='static1', path='mypackage:assets/1')
2 config.add_static_view(name='static2', path='mypackage:assets/2')
```

These declarations create URL-accessible directories which have URLs that begin with /static1 and /static2, respectively. The assets in the assets/1 directory of the mypackage package are consulted when a user visits a URL which begins with /static1, and the assets in the assets/2 directory of the mypackage package are consulted when a user visits a URL which begins with /static2.

You needn't generate the URLs to static assets "by hand" in such a configuration. Instead, use the static_url() API to generate them for you. For example:

```
1 from pyramid.url import static_url
 from pyramid.chameleon_zpt import render_template_to_response
2
3
 def my_view(request):
4
      css_url = static_url('mypackage:assets/1/foo.css', request)
5
      js_url = static_url('mypackage:assets/2/foo.js', request)
6
      return render_template_to_response('templates/my_template.pt',
7
                                          css_url = css_url,
8
                                          js_url = js_url)
9
```

If the request "application URL" of the running system is http://example.com, the css_url generated above would be: http://example.com/static1/foo.css. The js_url generated above would be http://example.com/static2/foo.js.

One benefit of using the static_url() function rather than constructing static URLs "by hand" is that if you need to change the name of a static URL declaration, the generated URLs will continue to resolve properly after the rename.

URLs may also be generated by static_url() to static assets that live *outside* the Pyramid application. This will happen when the add_static_view() API associated with the path fed to static_url() is a *URL* instead of a view name. For example, the name argument may be http://example.com while the the path given may be mypackage:images:

Under such a configuration, the URL generated by static_url for assets which begin with mypackage:images will be prefixed with http://example.com/images:

```
static_url('mypackage:images/logo.png', request)
{    # -> http://example.com/images/logo.png
```

Using static_url() in conjunction with a add_static_view() makes it possible to put static media on a separate webserver during production (if the name argument to add_static_view() is a URL), while keeping static media package-internal and served by the development webserver during development (if the name argument to add_static_view() is a URL prefix). To create such a circumstance, we suggest using the pyramid.registry.Registry.settings API in conjunction with a setting in the application .ini file named media_location. Then set the value of media_location to either a prefix or a URL depending on whether the application is being run in development or in production (use a different .ini file for production than you do for development). This is just a suggestion for a pattern; any setting name other than media_location could be used.

11.3 Advanced: Serving Static Assets Using a View Callable

For more flexibility, static assets can be served by a *view callable* which you register manually. For example, if you're using *URL dispatch*, you may want static assets to only be available as a fallback if no previous route matches. Alternately, you might like to serve a particular static asset manually, because its download requires authentication.

Note that you cannot use the static_url() API to generate URLs against assets made accessible by registering a custom static view.

11.3.1 Root-Relative Custom Static View (URL Dispatch Only)

The pyramid.static.static_view helper class generates a Pyramid view callable. This view callable can serve static assets from a directory. An instance of this class is actually used by the add_static_view() configuration method, so its behavior is almost exactly the same once it's configured.

The following example *will not work* for applications that use *traversal*, it will only work if you use *URL dispatch* exclusively. The root-relative route we'll be registering will always be matched before traversal takes place, subverting any views registered via add_view (at least those without a route_name). A static_view static view cannot be made root-relative when you use traversal unless it's registered as a *Not Found view*.

To serve files within a directory located on your filesystem at /path/to/static/dir as the result of a "catchall" route hanging from the root that exists at the end of your routing table, create an instance of the static_view class inside a static.py file in your application root as below.

```
1 from pyramid.static import static
2 static_view = static_view('/path/to/static/dir', use_subpath=True)
```

● For better cross-system flexibility, use an *asset specification* as the argument to static_view instead of a physical absolute filesystem path, e.g. mypackage:static instead of /path/to/mypackage/static.

Subsequently, you may wire the files that are served by this view up to be accessible as /<filename> using a configuration method in your application's startup code.

```
1 # .. every other add_route declaration should come
2 # before this one, as it will, by default, catch all requests
3 4
4 config.add_route('catchall_static', '/*subpath')
5 config.add_view('myapp.static.static_view', route_name='catchall_static')
```

The special name *subpath above is used by the static_view view callable to signify the path of the file relative to the directory you're serving.

11.3.2 Registering A View Callable to Serve a "Static" Asset

You can register a simple view callable to serve a single static asset. To do so, do things "by hand". First define the view callable.

```
import os
from pyramid.response import Response
def favicon_view(request):
    here = os.path.dirname(__file__)
    icon = open(os.path.join(here, 'static', 'favicon.ico'))
return Response(content_type='image/x-icon', app_iter=icon)
```

The above bit of code within favicon_view computes "here", which is a path relative to the Python file in which the function is defined. It then uses the Python open function to obtain a file handle to a file within "here" named static, and returns a response using the open the file handle as the response's app_iter. It makes sure to set the right content_type too.

You might register such a view via configuration as a view callable that should be called as the result of a traversal:

```
config.add_view('myapp.views.favicon_view', name='favicon.ico')
```

Or you might register it to be the view callable for a particular route:

```
1 config.add_route('favicon', '/favicon.ico')
2 config.add_view('myapp.views.favicon_view', route_name='favicon')
```

Because this is a simple view callable, it can be protected with a *permission* or can be configured to respond under different circumstances using *view predicate* arguments.

11.4 Overriding Assets

It can often be useful to override specific assets from "outside" a given Pyramid application. For example, you may wish to reuse an existing Pyramid application more or less unchanged. However, some specific template file owned by the application might have inappropriate HTML, or some static asset (such as a logo file or some CSS file) might not be appropriate. You *could* just fork the application entirely, but it's often more convenient to just override the assets that are inappropriate and reuse the application "as is". This is particularly true when you reuse some "core" application over and over again for some set of

customers (such as a CMS application, or some bug tracking application), and you want to make arbitrary visual modifications to a particular application deployment without forking the underlying code.

To this end, Pyramid contains a feature that makes it possible to "override" one asset with one or more other assets. In support of this feature, a *Configurator* API exists named pyramid.config.Configurator.override_asset(). This API allows you to *override* the following kinds of assets defined in any Python package:

- Individual *Chameleon* templates.
- A directory containing multiple Chameleon templates.
- Individual static files served up by an instance of the pyramid.static.static_view helper class.
- A directory of static files served up by an instance of the pyramid.static.static_view helper class.
- Any other asset (or set of assets) addressed by code that uses the setuptools *pkg_resources* API.

• The ZCML directive named asset serves the same purpose as the override_asset() method.

11.4.1 The override_asset API

An individual call to override_asset() can override a single asset. For example:

```
1 config.override_asset(
2     to_override='some.package:templates/mytemplate.pt',
3     override_with='another.package:othertemplates/anothertemplate.pt')
```

The string value passed to both to_override and override_with sent to the override_asset API is called an *asset specification*. The colon separator in a specification separates the *package name* from the *asset name*. The colon and the following asset name are optional. If they are not specified, the override attempts to resolve every lookup into a package from the directory of another package. For example:

Individual subdirectories within a package can also be overridden:

1

2

If you wish to override a directory with another directory, you *must* make sure to attach the slash to the end of both the to_override specification and the override_with specification. If you fail to attach a slash to the end of a specification that points to a directory, you will get unexpected results.

You cannot override a directory specification with a file specification, and vice versa: a startup error will occur if you try. You cannot override an asset with itself: a startup error will occur if you try.

Only individual *package* assets may be overridden. Overrides will not traverse through subpackages within an overridden package. This means that if you want to override assets for both some.package:templates, and some.package.views:templates, you will need to register two overrides.

The package name in a specification may start with a dot, meaning that the package is relative to the package in which the configuration construction file resides (or the package argument to the Configurator class construction). For example:

Multiple calls to override_asset which name a shared to_override but a different override_with specification can be "stacked" to form a search path. The first asset that exists in the search path will be used; if no asset exists in the override path, the original asset is used.

Asset overrides can actually override assets other than templates and static files. Any software which uses the pkg_resources.get_resource_filename(), pkg_resources.get_resource_stream() or pkg_resources.get_resource_string() APIs will obtain an overridden file when an override is used.

CHAPTER

TWELVE

REQUEST AND RESPONSE OBJECTS

U This chapter is adapted from a portion of the *WebOb* documentation, originally written by Ian Bicking.

Pyramid uses the *WebOb* package as a basis for its *request* and *response* object implementations. The *request* object that is passed to a Pyramid *view* is an instance of the pyramid.request.Request class, which is a subclass of webob.Request. The *response* returned from a Pyramid *view renderer* is an instance of the pyramid.response.Response class, which is a subclass of the webob.Response class. Users can also return an instance of pyramid.response.Response directly from a view as necessary.

WebOb is a project separate from Pyramid with a separate set of authors and a fully separate set of documentation. Pyramid adds some functionality to the standard WebOb request, which is documented in the *pyramid.request* API documentation.

WebOb provides objects for HTTP requests and responses. Specifically it does this by wrapping the WSGI request environment and response status, header list, and app_iter (body) values.

WebOb request and response objects provide many conveniences for parsing WSGI requests and forming WSGI responses. WebOb is a nice way to represent "raw" WSGI requests and responses; however, we won't cover that use case in this document, as users of Pyramid don't typically need to use the WSGI-related features of WebOb directly. The reference documentation shows many examples of creating requests and using response objects in this manner, however.

12.1 Request

The request object is a wrapper around the WSGI environ dictionary. This dictionary contains keys for each header, keys that describe the request (including the path and query string), a file-like object for the request body, and a variety of custom keys. You can always access the environ with req.environ.

Some of the most important/interesting attributes of a request object:

req.method: The request method, e.g., 'GET', 'POST'

- req.GET: A *multidict* with all the variables in the query string.
- **req.POST:** A *multidict* with all the variables in the request body. This only has variables if the request was a POST and it is a form submission.
- req.params: A multidict with a combination of everything in req.GET and req.POST.
- **req.body:** The contents of the body of the request. This contains the entire request body as a string. This is useful when the request is a POST that is *not* a form submission, or a request like a PUT. You can also get req.body_file for a file-like object.
- **req.json_body** The JSON-decoded contents of the body of the request. See *Dealing With A JSON-Encoded Request Body.*
- req.cookies: A simple dictionary of all the cookies.
- req. headers: A dictionary of all the headers. This dictionary is case-insensitive.
- req.urlvars and req.urlargs: req.urlvars are the keyword parameters associated with the request URL. req.urlargs are the positional parameters. These are set by products like Routes and Selector.

Also, for standard HTTP request headers there are usually attributes, for instance: req.accept_language, req.content_length, req.user_agent, as an example. These properties expose the *parsed* form of each header, for whatever parsing makes sense. For instance, req.if_modified_since returns a datetime object (or None if the header is was not provided).

Full API documentation for the Pyramid request object is available in *pyramid.request*.

12.1.1 Special Attributes Added to the Request by Pyramid

In addition to the standard *WebOb* attributes, Pyramid adds special attributes to every request: context, registry, root, subpath, traversed, view_name, virtual_root, virtual_root_path, session, and tmpl_context, matchdict, and matched_route. These attributes are documented further within the pyramid.request.Request API documentation.

12.1.2 URLs

In addition to these attributes, there are several ways to get the URL of the request. I'll show various values for an example URL http://localhost/app/blog?id=10, where the application is mounted at http://localhost/app.

req.url: The full request URL, with query string, e.g., http://localhost/app/blog?id=10

- req.host: The host information in the URL, e.g., localhost
- req.host_url: The URL with the host, e.g., http://localhost
- req.path_url: The URL of the application including the PATH_INFO. e.g., http://localhost/app/blog
- req.path: The URL including PATH_INFO without the host or scheme. e.g., /app/blog

req.path_qs: The URL including PATH_INFO and the query string. e.g, /app/blog?id=10

req.query_string: The query string in the URL, e.g., id=10

req.relative_url(url, to_application=False): Gives a URL, relative to the current URL. If to_application is True, then resolves it relative to req.application_url.

12.1.3 Methods

There are methods of request objects documented in pyramid.request.Request but you'll find that you won't use very many of them. Here are a couple that might be useful:

- **Request.blank (base_url):** Creates a new request with blank information, based at the given URL. This can be useful for subrequests and artificial requests. You can also use req.copy() to copy an existing request, or for subrequests req.copy_get() which copies the request but always turns it into a GET (which is safer to share for subrequests).
- req.get_response (wsgi_application): This method calls the given WSGI application with this request, and returns a pyramid.response.Response object. You can also use this for subrequests, or testing.

12.1.4 Unicode

Many of the properties in the request object will return unicode values if the request encoding/charset is provided. The client *can* indicate the charset with something like Content-Type: application/x-www-form-urlencoded; charset=utf8, but browsers seldom set this. You can set the charset with req.charset = 'utf8', or during instantiation with Request (environ, charset='utf8'). If you subclass Request you can also set charset as a class-level attribute.

If it is set, then req.POST, req.GET, req.params, and req.cookies will contain unicode strings. Each has a corresponding req.str_* (e.g., req.str_POST) that is always a str, and never unicode.

12.1.5 Multidict

Several attributes of a WebOb request are "multidict"; structures (such as request.GET, request.POST, and request.params). A multidict is a dictionary where a key can have multiple values. The quintessential example is a query string like ?pref=red&pref=blue; the pref variable has two values: red and blue.

In a multidict, when you do request.GET['pref'] you'll get back only 'blue' (the last value of pref). Sometimes returning a string, and sometimes returning a list, is the cause of frequent exceptions. If you want *all* the values back, use request.GET.getall('pref'). If you want to be sure there is *one and only one* value, use request.GET.getone('pref'), which will raise an exception if there is zero or more than one value for pref.

When you use operations like request.GET.items() you'll get back something like [('pref', 'red'), ('pref', 'blue')]. All the key/value pairs will show up. Similarly request.GET.keys() returns ['pref', 'pref']. Multidict is a view on a list of tuples; all the keys are ordered, and all the values are ordered.

API documentation for a multidict exists as pyramid.interfaces.IMultiDict.

12.1.6 Dealing With A JSON-Encoded Request Body

```
this feature is new as of Pyramid 1.1.
```

pyramid.request.Request.json_body is a property that returns a *JSON* -decoded representation of the request body. If the request does not have a body, or the body is not a properly JSON-encoded value, an exception will be raised when this attribute is accessed.

This attribute is useful when you invoke a Pyramid view callable via e.g. jQuery's \$.ajax function, which has the potential to send a request with a JSON-encoded body.

Using request.json_body is equivalent to:

```
from json import loads
loads(request.body, encoding=request.charset)
```

Here's how to construct an AJAX request in Javascript using *jQuery* that allows you to use the request.json_body attribute when the request is sent to a Pyramid application:

When such a request reaches a view in your application, the request.json_body attribute will be available in the view callable body.

```
@view_config(renderer='string')
def aview(request):
    print request.json_body
    return 'OK'
```

For the above view, printed to the console will be:

{u'a': 1}

For bonus points, here's a bit of client-side code that will produce a request that has a body suitable for reading via request.json_body using Python's urllib2 instead of a Javascript AJAX request:

```
import urllib2
import json
json_payload = json.dumps({'a':1})
headers = {'Content-Type':'application/json; charset=utf-8'}
req = urllib2.Request('http://localhost:6543/', json_payload, headers)
resp = urllib2.urlopen(req)
```

12.1.7 More Details

More detail about the request object API is available in:

- The pyramid.request.Request API documentation.
- The WebOb documentation. All methods and attributes of a webob.Request documented within the WebOb documentation will work with request objects created by Pyramid.

12.2 Response

The Pyramid response object can be imported as pyramid.response.Response. This class is a subclass of the webob.Response class. The subclass does not add or change any functionality, so the WebOb Response documentation will be completely relevant for this class as well.

A response object has three fundamental parts:

- **response.status:** The response code plus reason message, like '200 OK'. To set the code without a message, use status_int, i.e.: response.status_int = 200.
- response.app_iter: An iterable (such as a list or generator) that will produce the content of the response. This is also accessible as response.body (a string), response.unicode_body (a unicode object, informed by response.charset), and response.body_file (a file-like object; writing to it appends to app_iter).

Everything else in the object typically derives from this underlying state. Here are some highlights:

- response.content_type The content type not including the charset parameter. Typical use: response.content_type = 'text/html'.
- response.charset: The charset parameter of the content-type, it also informs encoding in response.unicode_body.response.content_type_params is a dictionary of all the parameters.
- response.set_cookie (key, value, max_age=None, path='/', ...): Set a cookie. The keyword arguments control the various cookie parameters. The max_age argument is the length for the cookie to live in seconds (you may also use a timedelta object). The Expires key will also be set based on the value of max_age.
- response.cache_expires(seconds=0): This makes this response cacheable for the given
 number of seconds, or if seconds is 0 then the response is uncacheable (this also sets the
 Expires header).
- **response (environ, start_response):** The response object is a WSGI application. As an application, it acts according to how you create it. It *can* do conditional responses if you pass conditional_response=True when instantiating (or set that attribute later). It can also do HEAD and Range requests.

12.2.1 Headers

Like the request, most HTTP response headers are available as properties. These are parsed, so you can do things like response.last_modified = os.path.getmtime(filename).

The details are available in the extracted Response documentation.

12.2.2 Instantiating the Response

Of course most of the time you just want to *make* a response. Generally any attribute of the response can be passed in as a keyword argument to the class; e.g.:

```
1 from pyramid.response import Response
2 response = Response(body='hello world!', content_type='text/plain')
```

The status defaults to '200 OK'. The content_type does not default to anything, though if you subclass pyramid.response.Response and set default_content_type you can override this behavior.

12.2.3 Exception Responses

To facilitate error responses like 404 Not Found, the module pyramid.httpexceptions contains classes for each kind of error response. These include boring, but appropriate error bodies. The exceptions exposed by this module, when used under Pyramid, should be imported from the pyramid.httpexceptions module. This import location contains subclasses and replacements that mirror those in the webob.exc module.

Each class is named pyramid.httpexceptions.HTTP*, where * is the reason for the error. For instance, pyramid.httpexceptions.HTTPNotFound subclasses pyramid.Response, so you can manipulate the instances in the same way. A typical example is:

```
from pyramid.httpexceptions import HTTPNotFound
from pyramid.httpexceptions import HTTPMovedPermanently
response = HTTPNotFound('There is no such resource')
# or:
response = HTTPMovedPermanently(location=new_url)
```

12.2.4 More Details

More details about the response object API are available in the pyramid.response documentation. More details about exception responses are in the pyramid.httpexceptions API documentation. The WebOb documentation is also useful.

CHAPTER

THIRTEEN

SESSIONS

A *session* is a namespace which is valid for some period of continual activity that can be used to represent a user's interaction with a web application.

This chapter describes how to configure sessions, what session implementations Pyramid provides out of the box, how to store and retrieve data from sessions, and two session-specific features: flash messages, and cross-site request forgery attack prevention.

13.1 Using The Default Session Factory

In order to use sessions, you must set up a session factory during your Pyramid configuration.

A very basic, insecure sample session factory implementation is provided in the Pyramid core. It uses a cookie to store session information. This implementation has the following limitation:

- The session information in the cookies used by this implementation is *not* encrypted, so it can be viewed by anyone with access to the cookie storage of the user's browser or anyone with access to the network along which the cookie travels.
- The maximum number of bytes that are storable in a serialized representation of the session is fewer than 4000. This is suitable only for very small data sets.

It is digitally signed, however, and thus its data cannot easily be tampered with.

You can configure this session factory in your Pyramid application by using the session_factory argument to the Configurator class:

```
from pyramid.session import UnencryptedCookieSessionFactoryConfig
my_session_factory = UnencryptedCookieSessionFactoryConfig('itsaseekreet')
from pyramid.config import Configurator
form form pyramid.config import Configurator
form factory = my_session_factory)
```

Note the very long, very explicit name for UnencryptedCookieSessionFactoryConfig. It's trying to tell you that this implementation is, by default, *unencrypted*. You should not use it when you keep sensitive information in the session object, as the information can be easily read by both users of your application and third parties who have access to your users' network traffic. Use a different session factory implementation (preferably one which keeps session data on the server) for anything but the most basic of applications where "session security doesn't matter".

13.2 Using a Session Object

Once a session factory has been configured for your application, you can access session objects provided by the session factory via the session attribute of any *request* object. For example:

```
from pyramid.response import Response
2
  def myview(request):
3
      session = request.session
4
      if 'abc' in session:
5
           session['fred'] = 'yes'
6
      session['abc'] = '123'
7
      if 'fred' in session:
8
          return Response('Fred was in the session')
9
      else:
10
          return Response ('Fred was not in the session')
11
```

You can use a session much like a Python dictionary. It supports all dictionary methods, along with some extra attributes, and methods.

Extra attributes:

created An integer timestamp indicating the time that this session was created.

new A boolean. If new is True, this session is new. Otherwise, it has been constituted from data that was already serialized.

Extra methods:

- **changed()** Call this when you mutate a mutable value in the session namespace. See the gotchas below for details on when, and why you should call this.
- **invalidate()** Call this when you want to invalidate the session (dump all data, and perhaps set a clearing cookie).

The formal definition of the methods and attributes supported by the session object are in the pyramid.interfaces.ISession documentation.

Some gotchas:

- Keys and values of session data must be *pickleable*. This means, typically, that they are instances of basic types of objects, such as strings, lists, dictionaries, tuples, integers, etc. If you place an object in a session data key or value that is not pickleable, an error will be raised when the session is serialized.
- If you place a mutable value (for example, a list or a dictionary) in a session object, and you subsequently mutate that value, you must call the changed() method of the session object. In this case, the session has no way to know that is was modified. However, when you modify a session object directly, such as setting a value (i.e., __setitem__), or removing a key (e.g., del or pop), the session will automatically know that it needs to re-serialize its data, thus calling changed() is unnecessary. There is no harm in calling changed() in either case, so when in doubt, call it after you've changed sessioning data.

13.3 Using Alternate Session Factories

At the time of this writing, exactly one alternate session factory implementation exists, named pyramid_beaker. This is a session factory that uses the Beaker library as a backend. Beaker has support for file-based sessions, database based sessions, and encrypted cookie-based sessions. See http://github.com/Pylons/pyramid_beaker for more information about pyramid_beaker.

13.4 Creating Your Own Session Factory

If none of the default or otherwise available sessioning implementations for Pyramid suit you, you may create your own session object by implementing a *session factory*. Your session factory should return a *session*. The interfaces for both types are available in pyramid.interfaces.ISessionFactory and pyramid.interfaces.ISession. You might use the cookie implementation in the pyramid.session module as inspiration.

13.5 Flash Messages

"Flash messages" are simply a queue of message strings stored in the *session*. To use flash messaging, you must enable a *session factory* as described in *Using The Default Session Factory* or *Using Alternate Session Factories*.

Flash messaging has two main uses: to display a status message only once to the user after performing an internal redirect, and to allow generic code to log messages for single-time display without having direct access to an HTML template. The user interface consists of a number of methods of the *session* object.

13.5.1 Using the session.flash Method

To add a message to a flash message queue, use a session object's flash() method:

```
request.session.flash('mymessage')
```

The flash () method appends a message to a flash queue, creating the queue if necessary.

flash() accepts three arguments:

```
flash (message, queue='', allow_duplicate=True)
```

The message argument is required. It represents a message you wish to later display to a user. It is usually a string but the message you provide is not modified in any way.

The queue argument allows you to choose a queue to which to append the message you provide. This can be used to push different kinds of messages into flash storage for later display in different places on a page. You can pass any name for your queue, but it must be a string. Each queue is independent, and can be popped by pop_flash() or examined via peek_flash() separately. queue defaults to the empty string. The empty string represents the default flash message queue.

request.session.flash(msg, 'myappsqueue')

The allow_duplicate argument defaults to True. If this is False, and you attempt to add a message value which is already present in the queue, it will not be added.

13.5.2 Using the session.pop_flash Method

Once one or more messages have been added to a flash queue by the session.flash() API, the session.pop_flash() API can be used to pop an entire queue and return it for use.

To pop a particular queue of messages from the flash object, use the session object's $pop_flash()$ method. This returns a list of the messages that were added to the flash queue, and empties the queue.

pop_flash(queue='')

```
1 >>> request.session.flash('info message')
2 >>> request.session.pop_flash()
3 ['info message']
```

Calling session.pop_flash() again like above without a corresponding call to session.flash() will return an empty list, because the queue has already been popped.

```
1 >>> request.session.flash('info message')
2 >>> request.session.pop_flash()
3 ['info message']
4 >>> request.session.pop_flash()
5 []
```

13.5.3 Using the session.peek_flash Method

Once one or more messages has been added to a flash queue by the session.flash() API, the session.peek_flash() API can be used to "peek" at that queue. Unlike session.pop_flash(), the queue is not popped from flash storage.

```
peek_flash(queue='')
```

```
1 >>> request.session.flash('info message')
2 >>> request.session.peek_flash()
3 ['info message']
4 >>> request.session.peek_flash()
5 ['info message']
6 >>> request.session.pop_flash()
7 ['info message']
8 >>> request.session.peek_flash()
9 []
```

13.6 Preventing Cross-Site Request Forgery Attacks

Cross-site request forgery attacks are a phenomenon whereby a user with an identity on your website might click on a URL or button on another website which secretly redirects the user to your application to perform some command that requires elevated privileges.

You can avoid most of these attacks by making sure that the correct *CSRF token* has been set in an Pyramid session object before performing any actions in code which requires elevated privileges that is invoked via a form post. To use CSRF token support, you must enable a *session factory* as described in *Using The Default Session Factory* or *Using Alternate Session Factories*.

13.6.1 Using the session.get_csrf_token Method

To get the current CSRF token from the session, use the session.get_csrf_token() method.

```
token = request.session.get_csrf_token()
```

The session.get_csrf_token() method accepts no arguments. It returns a CSRF *token* string. If session.get_csrf_token() or session.new_csrf_token() was invoked previously for this session, the existing token will be returned. If no CSRF token previously existed for this session, a new token will be set into the session and returned. The newly created token will be opaque and randomized.

You can use the returned token as the value of a hidden field in a form that posts to a method that requires elevated privileges. The handler for the form post should use <code>session.get_csrf_token()</code> again to obtain the current CSRF token related to the user from the session, and compare it to the value of the hidden form field. For example, if your form rendering included the CSRF token obtained via <code>session.get_csrf_token()</code> as a hidden input field named <code>csrf_token</code>:

```
token = request.session.get_csrf_token()
if token != request.POST['csrf_token']:
    raise ValueError('CSRF token did not match')
```

13.6.2 Using the session.new_csrf_token Method

To explicitly add a new CSRF token to the session, use the session.new_csrf_token() method. This differs only from session.get_csrf_token() inasmuch as it clears any existing CSRF token, creates a new CSRF token, sets the token into the session, and returns the token.

token = request.session.new_csrf_token()

CHAPTER

FOURTEEN

USING EVENTS

An *event* is an object broadcast by the Pyramid framework at interesting points during the lifetime of an application. You don't need to use events in order to create most Pyramid applications, but they can be useful when you want to perform slightly advanced operations. For example, subscribing to an event can allow you to run some code as the result of every new request.

Events in Pyramid are always broadcast by the framework. However, they only become useful when you register a *subscriber*. A subscriber is a function that accepts a single argument named *event*:

```
1 def mysubscriber(event):
2 print event
```

The above is a subscriber that simply prints the event to the console when it's called.

The mere existence of a subscriber function, however, is not sufficient to arrange for it to be called. To arrange for the subscriber to be called, you'll need to use the pyramid.config.Configurator.add_subscriber() method or you'll need to use the pyramid.events.subscriber() decorator to decorate a function found via a *scan*.

14.1 Configuring an Event Listener Imperatively

You can imperatively configure a subscriber function to be called for some event type via the add_subscriber() method (see also *Configurator*):

```
from pyramid.events import NewRequest
from subscribers import mysubscriber
#
# "config" below is assumed to be an instance of a
# pyramid.config.Configurator object
#
config.add_subscriber(mysubscriber, NewRequest)
```

The first argument to add_subscriber() is the subscriber function (or a *dotted Python name* which refers to a subscriber callable); the second argument is the event type.

14.2 Configuring an Event Listener Using a Decorator

You can configure a subscriber function to be called for some event type via the pyramid.events.subscriber() function.

```
1 from pyramid.events import NewRequest
2 from pyramid.events import subscriber
3
4 @subscriber(NewRequest)
5 def mysubscriber(event):
6 event.request.foo = 1
```

When the subscriber() decorator is used a *scan* must be performed against the package containing the decorated function for the decorator to have any effect.

Either of the above registration examples implies that every time the Pyramid framework emits an event object that supplies an pyramid.events.NewRequest interface, the mysubscriber function will be called with an *event* object.

As you can see. a subscription is made in terms of а class (such as pyramid.events.NewResponse). The event object sent to a subscriber will always be an object that possesses an *interface*. For pyramid.events.NewResponse, that interface is pyramid.interfaces.INewResponse. The interface documentation provides information about available attributes and methods of the event objects.

The return value of a subscriber function is ignored. Subscribers to the same event type are not guaranteed to be called in any particular order relative to each other.

All the concrete Pyramid event types are documented in the pyramid.events API documentation.

14.3 An Example

If you create event listener functions in a subscribers.py file in your application like so:

```
def handle_new_request(event):
    print 'request', event.request
def handle_new_response(event):
    print 'response', event.response
```

You may configure these functions to be called at the appropriate times by adding the following code to your application's configuration startup:

Either mechanism causes the functions in subscribers.py to be registered as event subscribers. Under this configuration, when the application is run, each time a new request or response is detected, a message will be printed to the console.

Each of our subscriber functions accepts an event object and prints an attribute of the event object. This begs the question: how can we know which attributes a particular event has?

We know that pyramid.events.NewRequest event objects have a request attribute, which is a *request* object, because the interface defined at pyramid.interfaces.INewRequest says it must. Likewise, we know that pyramid.interfaces.NewResponse events have a response attribute, which is a response object constructed by your application, because the interface defined at pyramid.interfaces.INewResponse says it must (pyramid.events.NewResponse objects also have a request).

CHAPTER

FIFTEEN

ENVIRONMENT VARIABLES AND . INI FILE SETTINGS

Pyramid behavior can be configured through a combination of operating system environment variables and .ini configuration file application section settings. The meaning of the environment variables and the configuration file settings overlap.

Where a configuration file setting exists with the same meaning as an environment variable, and both are present at application startup time, the environment variable setting takes precedence.

The term "configuration file setting name" refers to a key in the .ini configuration for your application. The configuration file setting names documented in this chapter are reserved for Pyramid use. You should not use them to indicate application-specific configuration settings.

15.1 Reloading Templates

When this value is true, templates are automatically reloaded whenever they are modified without restarting the application, so you can see changes to templates take effect immediately during development. This flag is meaningful to Chameleon and Mako templates, as well as most third-party template rendering extensions.

Environment Variable Name	Config File Setting Name
PYRAMID_RELOAD_TEMPLATES	reload_templates

15.2 Reloading Assets

Don't cache any asset file data when this value is true. See also Overriding Assets.

Environment Variable Name	Config File Setting Name
PYRAMID_RELOAD_ASSETS	reload_assets

• For backwards compatibility purposes, aliases can be used for configurating asset reloading: PYRAMID_RELOAD_RESOURCES (envvar) and reload_resources (config file).

15.3 Debugging Authorization

Print view authorization failure and success information to stderr when this value is true. See also *Debug*ging View Authorization Failures.

Environment Variable Name	Config File Setting Name
PYRAMID_DEBUG_AUTHORIZATION	debug_authorization

15.4 Debugging Not Found Errors

Print view-related NotFound debug messages to stderr when this value is true. See also NotFound Errors.

Environment Variable Name	Config File Setting Name
PYRAMID_DEBUG_NOTFOUND	debug_notfound

15.5 Debugging Route Matching

Print debugging messages related to *url dispatch* route matching when this value is true. See also *Debugging Route Matching*.

Environment Variable Name	Config File Setting Name
PYRAMID_DEBUG_ROUTEMATCH	debug_routematch

15.6 Preventing HTTP Caching

Prevent the http_cache view configuration argument from having any effect globally in this process when this value is true. No http caching-related response headers will be set by the Pyramid http_cache view configuration feature when this is true. See also *Influencing HTTP Caching*.

Environment Variable Name	Config File Setting Name
PYRAMID_PREVENT_HTTP_CACHE	prevent_http_cache

15.7 Debugging All

Turns on all debug* settings.

Environment Variable Name	Config File Setting Name
PYRAMID_DEBUG_ALL	debug_all

15.8 Reloading All

Turns on all reload* settings.

Environment Variable Name	Config File Setting Name
PYRAMID_RELOAD_ALL	reload_all

15.9 Default Locale Name

The value supplied here is used as the default locale name when a *locale negotiator* is not registered. See also *Localization-Related Deployment Settings*.

Environment Variable Name	Config File Setting Name
PYRAMID_DEFAULT_LOCALE_NAME	default_locale_name

15.10 Mako Template Render Settings

Mako derives additional settings to configure its template renderer that should be set when using it. Many of these settings are optional and only need to be set if they should be different from the default. The Mako Template Renderer uses a subclass of Mako's template lookup and accepts several arguments to configure it.

15.10.1 Mako Directories

The value(s) supplied here are passed in as the template directories. They should be in *asset specification* format, for example: my.package:templates.

Config File Setting Name mako.directories

15.10.2 Mako Module Directory

The value supplied here tells Mako where to store compiled Mako templates. If omitted, compiled templates will be stored in memory. This value should be an absolute path, for example: %(here)s/data/templates would use a directory called data/templates in the same parent directory as the INI file.

Config File Setting Name mako.module_directory

15.10.3 Mako Input Encoding

The encoding that Mako templates are assumed to have. By default this is set to utf-8. If you wish to use a different template encoding, this value should be changed accordingly.

Config File Setting Name mako.input_encoding

15.10.4 Mako Error Handler

A callable (or a *dotted Python name* which names a callable) which is called whenever Mako compile or runtime exceptions occur. The callable is passed the current context as well as the exception. If the callable returns True, the exception is considered to be handled, else it is re-raised after the function completes. Is used to provide custom error-rendering functions.

Config File Setting Name mako.error_handler

15.10.5 Mako Default Filters

List of string filter names that will be applied to all Mako expressions.

Config File Setting Name mako.default_filters

15.10.6 Mako Import

String list of Python statements, typically individual "import" lines, which will be placed into the module level preamble of all generated Python modules.

Config File Setting Name mako.imports

15.10.7 Mako Strict Undefined

true or false, representing the "strict undefined" behavior of Mako (see Mako Context Variables). By default, this is false.

```
Config File Setting Name
mako.strict_undefined
```

15.10.8 Mako Preprocessor

A callable (or a *dotted Python name* which names a callable) which is called to preprocess the source before the template is called. The callable will be passed the full template source before it is parsed. The return result of the callable will be used as the template source code.

```
This feature is new in Pyramid 1.1.
```

```
Config File Setting Name
mako.preprocessor
```

15.11 Examples

Let's presume your configuration file is named MyProject.ini, and there is a section representing your application named [app:main] within the file that represents your Pyramid application. The configuration file settings documented in the above "Config File Setting Name" column would go in the [app:main] section. Here's an example of such a section:

```
1 [app:main]
2 use = egg:MyProject#app
3 reload_templates = true
4 debug_authorization = true
```

You can also use environment variables to accomplish the same purpose for settings documented as such. For example, you might start your Pyramid application using the following command line:

```
$ PYRAMID_DEBUG_AUTHORIZATION=1 PYRAMID_RELOAD_TEMPLATES=1 \
    bin/paster serve MyProject.ini
```

If you started your application this way, your Pyramid application would behave in the same manner as if you had placed the respective settings in the [app:main] section of your application's .ini file.

If you want to turn all debug settings (every setting that starts with debug_). on in one fell swoop, you can use PYRAMID_DEBUG_ALL=1 as an environment variable setting or you may use debug_all=true in the config file. Note that this does not affect settings that do not start with debug_* such as reload_templates.

If you want to turn all reload settings (every setting that starts with reload_) on in one fell swoop, you can use PYRAMID_RELOAD_ALL=1 as an environment variable setting or you may use reload_all=true in the config file. Note that this does not affect settings that do not start with reload_* such as debug_notfound.

Specifying configuration settings via environment variables is generally most useful during development, where you may wish to augment or override the more permanent settings in the configuration file. This is useful because many of the reload and debug settings may have performance or security (i.e., disclosure) implications that make them undesirable in a production environment.

15.12 Understanding the Distinction Between reload_templates and reload_assets

The difference between reload_assets and reload_templates is a bit subtle. Templates are themselves also treated by Pyramid as asset files (along with other static files), so the distinction can be confusing. It's helpful to read *Overriding Assets* for some context about assets in general.

When reload_templates is true, Pyramid takes advantage of the underlying templating systems' ability to check for file modifications to an individual template file. When reload_templates is true but reload_assets is *not* true, the template filename returned by the pkg_resources package (used under the hood by asset resolution) is cached by Pyramid on the first request. Subsequent requests for the same template file will return a cached template filename. The underlying templating system checks for modifications to this particular file for every request. Setting reload_templates to True doesn't affect performance dramatically (although it should still not be used in production because it has some effect).

However, when reload_assets is true, Pyramid will not cache the template filename, meaning you can see the effect of changing the content of an overridden asset directory for templates without restarting the server after every change. Subsequent requests for the same template file may return different filenames based on the current state of overridden asset directories. Setting reload_assets to True affects performance *dramatically*, slowing things down by an order of magnitude for each template rendering. However, it's convenient to enable when moving files around in overridden asset directories. reload_assets makes the system *very slow* when templates are in use. Never set reload_assets to True on a production system.

15.13 Adding A Custom Setting

From time to time, you may need to add a custom setting to your application. Here's how:

• If you're using an .ini file, change the .ini file, adding the setting to the [app:foo] section representing your Pyramid application. For example:

```
[app:myapp]
# .. other settings
debug_frobnosticator = True
```

• In the main () function that represents the place that your Pyramid WSGI application is created, anticipate that you'll be getting this key/value pair as a setting and do any type conversion necessary.

If you've done any type conversion of your custom value, reset the converted values into the settings dictionary *before* you pass the dictionary as settings to the *Configurator*. For example:

U It's especially important that you mutate the settings dictionary with the converted version of the variable *before* passing it to the Configurator: the configurator makes a *copy* of settings, it doesn't use the one you pass directly.

• In the runtime code that you need to access the new settings value, find the value in the registry.settings dictionary and use it. In *view* code (or any other code that has access to the request), the easiest way to do this is via request.registry.settings. For example:

```
registry = request.registry.settings
debug_frobnosticator = settings['debug_frobnosticator']
```

If you wish to use the value in code that does not have access to the request and you wish to use the value, you'll need to use the pyramid.threadlocal.get_current_registry() API to obtain the current registry, then ask for its settings attribute. For example:

```
registry = pyramid.threadlocal.get_current_registry()
settings = registry.settings
debug_frobnosticator = settings['debug_frobnosticator']
```

CHAPTER

SIXTEEN

COMMAND-LINE PYRAMID

Your Pyramid application can be controlled and inspected using a variety of command-line utilities. These utilities are documented in this chapter.

16.1 Displaying Matching Views for a Given URL

For a big application with several views, it can be hard to keep the view configuration details in your head, even if you defined all the views yourself. You can use the paster priews command in a terminal window to print a summary of matching routes and views for a given URL in your application. The paster priews command accepts two arguments. The first argument to priews is the path to your application's .ini file and section name inside the .ini file which points to your application. This should be of the format config_file#section_name. The second argument is the URL to test for matching views. The section_name may be omitted; if it is, it's considered to be main.

Here is an example for a simple view configuration using *traversal*:

```
$ ../bin/paster pviews development.ini#tutorial /FrontPage
1
2
  URL = /FrontPage
3
4
      context: <tutorial.models.Page object at 0xa12536c>
5
      view name:
6
7
      View:
8
9
      tutorial.views.view_page
10
      required permission = view
11
```

16. COMMAND-LINE PYRAMID

The output always has the requested URL at the top and below that all the views that matched with their view configuration details. In this example only one view matches, so there is just a single *View* section. For each matching view, the full code path to the associated view callable is shown, along with any permissions and predicates that are part of that view configuration.

A more complex configuration might generate something like this:

```
$ ../bin/paster pviews development.ini#shootout /about
1
2
  URL = /about
3
4
       context: <shootout.models.RootFactory object at 0xa56668c>
5
       view name: about
6
7
       Route:
8
       _____
9
       route name: about
10
       route pattern: /about
11
12
       route path: /about
       subpath:
13
       route predicates (request method = GET)
14
15
           View:
16
           ____
17
           shootout.views.about_view
18
           required permission = view
19
           view predicates (request_param testing, header X/header)
20
21
       Route:
22
23
       ____
       route name: about_post
24
25
       route pattern: /about
       route path: /about
26
       subpath:
27
       route predicates (request method = POST)
28
29
           View:
30
           ____
31
           shootout.views.about_view_post
32
           required permission = view
33
           view predicates (request_param test)
34
35
           View:
36
           ____
37
           shootout.views.about_view_post2
38
           required permission = view
39
```

view predicates (request_param test2)

In this case, we are dealing with a *URL dispatch* application. This specific URL has two matching routes. The matching route information is displayed first, followed by any views that are associated with that route. As you can see from the second matching route output, a route can be associated with more than one view.

For a URL that doesn't match any views, paster pviews will simply print out a Not found message.

16.2 The Interactive Shell

40

Once you've installed your program for development using setup.py develop, you can use an interactive Python shell to execute expressions in a Python environment exactly like the one that will be used when your application runs "for real". To do so, use the paster pshell command.

The argument to pshell follows the format config_file#section_name where config_file is the path to your application's .ini file and section_name is the app section name inside the .ini file which points to your application. For example, if your application .ini file might have a [app:MyProject] section that looks like so:

```
1 [app:MyProject]
2 use = egg:MyProject
3 reload_templates = true
4 debug_authorization = false
5 debug_notfound = false
6 debug_templates = true
7 default_locale_name = en
```

If so, you can use the following command to invoke a debug shell using the name MyProject as a section name:

```
root Root of the default resource tree.
root_factory Default root factory used to create `root`.
>>> root
<myproject.resources.MyResource object at 0x445270>
>>> registry
<Registry myproject>
>>> registry.settings['debug_notfound']
False
>>> from myproject.views import my_view
>>> from pyramid.request import Request
>>> r = Request.blank('/')
>>> my_view(r)
{'project': 'myproject'}
```

The WSGI application that is loaded will be available in the shell as the app global. Also, if the application that is loaded is the Pyramid app with no surrounding middleware, the root object returned by the default *root factory*, registry, and request will be available.

You can also simply rely on the main default section name by omitting any hash after the filename:

chrism@thinko env26]\$ bin/paster pshell starter/development.ini

Press Ctrl-D to exit the interactive shell (or Ctrl-Z on Windows).

16.2.1 Extending the Shell

It is sometimes convenient when using the interactive shell often to have some variables significant to your application already loaded as globals when you start the pshell. To facilitate this, pshell will look for a special [pshell] section in your INI file and expose the subsequent key/value pairs to the shell. Each key is a variable name that will be global within the pshell session; each value is a *dotted Python name*.

For example, you want to expose your model to the shell, along with the database session so that you can mutate the model on an actual database. Here, we'll assume your model is stored in the myapp.models package.

```
1 [pshell]
2 m = myapp.models
3 session = myapp.models.DBSession
4 t = transaction
```

When this INI file is loaded, the extra variables m, session and t will be available for use immediately. For example:

```
chrism@thinko env26]$ bin/paster pshell starter/development.ini
Python 2.6.5 (r265:79063, Apr 29 2010, 00:31:32)
[GCC 4.4.3] on linux2
Type "help" for more information.
Environment:
              The WSGI application.
  app
            Active Pyramid registry.
 registry
             Active request object.
 request
             Root of the default resource tree.
 root
 root_factory Default root factory used to create 'root'.
Custom Variables:
 m
              myapp.models
            myapp.models.DBSession
 session
              transaction
 t
>>>
```

16.2.2 IPython

If you have IPython installed in the interpreter you use to invoke the paster command, the pshell command will use an IPython interactive shell instead of a standard Python interpreter shell. If you don't want this to happen, even if you have IPython installed, you can pass the --disable-ipython flag to the pshell command to use a standard Python interpreter shell unconditionally.

16.3 Displaying All Application Routes

You can use the paster proutes command in a terminal window to print a summary of routes related to your application. Much like the paster pshell command (see *The Interactive Shell*), the paster proutes command accepts one argument with the format config_file#section_name. The config_file is the path to your application's .ini file, and section_name is the app section name inside the .ini file which points to your application. By default, the section_name is main and can be omitted.

For example:

1	[chrism@thinko	MyProject]\$/bin/paster prout	es development.ini#MyProject
2	Name	Pattern	View
3			
4	home	/	<function my_view=""></function>
5	home2	/	<function my_view=""></function>
6	another	/another	None
7	static/	static/*subpath	<static_view object=""></static_view>
8	catchall	/*subpath	<function static_view=""></function>

paster proutes generates a table. The table has three columns: a Name column, a Pattern column, and a View column. The items listed in the Name column are route names, the items listed in the Pattern column are route patterns, and the items listed in the View column are representations of the view callable that will be invoked when a request matches the associated route pattern. The view column may show None if no associated view callable could be found. If no routes are configured within your application, nothing will be printed to the console when paster proutes is executed.

16.4 Writing a Script

All web applications are, at their hearts, systems which accept a request and return a response. When a request is accepted by a Pyramid application, the system receives state from the request which is later relied on by your application code. For example, one *view callable* may assume it's working against a request that has a request .matchdict of a particular composition, while another assumes a different composition of the matchdict.

In the meantime, it's convenient to be able to write a Python script that can work "in a Pyramid environment", for instance to update database tables used by your Pyramid application. But a "real" Pyramid environment doesn't have a completely static state independent of a request; your application (and Pyramid itself) is almost always reliant on being able to obtain information from a request. When you run a Python script that simply imports code from your application and tries to run it, there just is no request data, because there isn't any real web request. Therefore some parts of your application and some Pyramid APIs will not work.

For this reason, Pyramid makes it possible to run a script in an environment much like the environment produced when a particular *request* reaches your Pyramid application. This is achieved by using the pyramid.paster.bootstrap() command in the body of your script.

This feature is new as of Pyramid 1.1.

In the simplest case, pyramid.paster.bootstrap() can be used with a single argument, which accepts the *PasteDeploy* .ini file representing Pyramid your application configuration as a single argument:

```
from pyramid.paster import bootstrap
env = bootstrap('/path/to/my/development.ini')
print env['request'].route_url('home')
```

pyramid.paster.bootstrap() returns a dictionary containing framework-related information. This dictionary will always contain a *request* object as its request key.

The following keys are available in the env dictionary returned by pyramid.paster.bootstrap():

request

A pyramid.request.Request object implying the current request state for your script.

app

The WSGI application object generated by bootstrapping.

root

The *resource* root of your Pyramid application. This is an object generated by the *root factory* configured in your application.

registry

The application registry of your Pyramid application.

closer

A parameterless callable that can be used to pop an internal Pyramid threadlocal stack (used by pyramid.threadlocal.get_current_registry() and pyramid.threadlocal.get_current_request()) when your scripting job is finished.

Let's assume that the /path/to/my/development.ini file used in the example above looks like so:

16. COMMAND-LINE PYRAMID

The configuration loaded by the above bootstrap example will use the configuration implied by the [pipeline:main] section of your configuration file by default. Specifying /path/to/my/development.ini is logically equivalent to specifying /path/to/my/development.ini#main. In this case, we'll be using a configuration that includes an app object which is wrapped in the WebError evalerror middleware.

You can also specify a particular section of the PasteDeploy .ini file to load instead of main:

```
from pyramid.paster import bootstrap
env = bootstrap('/path/to/my/development.ini#another')
print env['request'].route_url('home')
```

The above example specifies the another app, pipeline, or composite section of your PasteDeploy configuration file. The app object present in the env dictionary returned by pyramid.paster.bootstrap() will be a Pyramid router.

16.4.1 Changing the Request

By default, Pyramid will generate a request object in the env dictionary for the URL http://localhost:80/. This means that any URLs generated by Pyramid during the execution of your script will be anchored here. This is generally not what you want.

So how do we make Pyramid generate the correct URLs?

Assuming that you have a route configured in your application like so:

```
config.add_route('verify', '/verify/{code}')
```

You need to inform the Pyramid environment that the WSGI application is handling requests from a certain base. For example, we want to mount our application at *example.com/prefix* and the generated URLs should use HTTPS. This can be done by mutating the request object:

```
from pyramid.paster import bootstrap
env = bootstrap('/path/to/my/development.ini#another')
env['request'].host = 'example.com'
env['request'].scheme = 'https'
env['request'].script_name = '/prefix'
print env['request'].application_url
# will print 'https://example.com/prefix/another/url'
```

Now you can readily use Pyramid's APIs for generating URLs:

```
route_url('verify', env['request'], code='1337')
# will return 'https://example.com/prefix/verify/1337'
```

16.4.2 Cleanup

When your scripting logic finishes, it's good manners (but not required) to call the closer callback:

```
from pyramid.paster import bootstrap
env = bootstrap('/path/to/my/development.ini')
# .. do stuff ...
env['closer']()
```

16.4.3 Setting Up Logging

By default, pyramid.paster.bootstrap() does not configure logging parameters present in the configuration file. If you'd like to configure logging based on [logger] and related sections in the configuration file, use the following command:

```
import logging
logging.fileConfig('/path/to/my/development.ini')
```

16. COMMAND-LINE PYRAMID

CHAPTER

SEVENTEEN

INTERNATIONALIZATION AND LOCALIZATION

Internationalization (i18n) is the act of creating software with a user interface that can potentially be displayed in more than one language or cultural context. *Localization* (110n) is the process of displaying the user interface of an internationalized application in a *particular* language or cultural context.

Pyramid offers internationalization and localization subsystems that can be used to translate the text of buttons, error messages and other software- and template-defined values into the native language of a user of your application.

17.1 Creating a Translation String

While you write your software, you can insert specialized markup into your Python code that makes it possible for the system to translate text values into the languages used by your application's users. This markup creates a *translation string*. A translation string is an object that behaves mostly like a normal Unicode object, except that it also carries around extra information related to its job as part of the Pyramid translation machinery.

17.1.1 Using The TranslationString Class

The most primitive way to create a translation string is to use the pyramid.il8n.TranslationString callable:

17. INTERNATIONALIZATION AND LOCALIZATION

```
1 from pyramid.i18n import TranslationString
2 ts = TranslationString('Add')
```

This creates a Unicode-like object that is a TranslationString.

• For people more familiar with *Zope* i18n, a TranslationString is a lot like a zope.i18nmessageid.Message object. It is not a subclass, however. For people more familiar with *Pylons* or *Django* i18n, using a TranslationString is a lot like using "lazy" versions of related gettext APIs.

The first argument to TranslationString is the msgid; it is required. It represents the key into the translation mappings provided by a particular localization. The msgid argument must be a Unicode object or an ASCII string. The msgid may optionally contain *replacement markers*. For instance:

```
1 from pyramid.i18n import TranslationString
2 ts = TranslationString('Add ${number}')
```

Within the string above, \${number} is a replacement marker. It will be replaced by whatever is in the *mapping* for a translation string. The mapping may be supplied at the same time as the replacement marker itself:

```
1 from pyramid.i18n import TranslationString
2 ts = TranslationString('Add ${number}', mapping={'number':1})
```

Any number of replacement markers can be present in the msgid value, any number of times. Only markers which can be replaced by the values in the *mapping* will be replaced at translation time. The others will not be interpolated and will be output literally.

A translation string should also usually carry a *domain*. The domain represents a translation category to disambiguate it from other translations of the same msgid, in case they conflict.

```
1 from pyramid.i18n import TranslationString
2 ts = TranslationString('Add ${number}', mapping={'number':1},
3 domain='form')
```

The above translation string named a domain of form. A *translator* function will often use the domain to locate the right translator file on the filesystem which contains translations for a given domain. In this case, if it were trying to translate our msgid to German, it might try to find a translation from a *gettext* file within a *translation directory* like this one:

locale/de/LC_MESSAGES/form.mo

In other words, it would want to take translations from the form.mo translation file in the German language.

Finally, the TranslationString constructor accepts a default argument. If a default argument is supplied, it replaces usages of the msgid as the *default value* for the translation string. When default is None, the msgid value passed to a TranslationString is used as an implicit message identifier. Message identifiers are matched with translations in translation files, so it is often useful to create translation strings with "opaque" message identifiers unrelated to their default text:

```
1 from pyramid.i18n import TranslationString
2 ts = TranslationString('add-number', default='Add ${number}',
3 domain='form', mapping={'number':1})
```

When default text is used, Default text objects may contain replacement values.

17.1.2 Using the TranslationStringFactory Class

Another way to generate a translation string is to use the TranslationStringFactory object. This object is a *translation string factory*. Basically a translation string factory presets the domain value of any *translation string* generated by using it. For example:

```
from pyramid.il8n import TranslationStringFactory
2 _ = TranslationStringFactory('pyramid')
3 ts = _('Add ${number}', msgid='add-number', mapping={'number':1})
```

We assigned the translation string factory to the name _. This is a convention which will be supported by translation file generation tools.

After assigning _ to the result of a TranslationStringFactory (), the subsequent result of calling _ will be a TranslationString instance. Even though a domain value was not passed to _ (as would have been necessary if the TranslationString constructor were used instead of a translation string factory), the domain attribute of the resulting translation string will be pyramid. As a result, the previous code example is completely equivalent (except for spelling) to:

```
1 from pyramid.i18n import TranslationString as _
2 ts = _('Add ${number}', msgid='add-number', mapping={'number':1},
3 domain='pyramid')
```

You can set up your own translation string factory much like the one provided above by using the TranslationStringFactory class. For example, if you'd like to create a translation string factory which presets the domain value of generated translation strings to form, you'd do something like this:

```
1 from pyramid.i18n import TranslationStringFactory
2 _ = TranslationStringFactory('form')
3 ts = _('Add ${number}', msgid='add-number', mapping={'number':1})
```

Creating a unique domain for your application via a translation string factory is best practice. Using your own unique translation domain allows another person to reuse your application without needing to merge your translation files with his own. Instead, he can just include your package's *translation directory* via the pyramid.config.Configurator.add_translation_dirs() method.

U For people familiar with Zope internationalization, a TranslationStringFactory is a lot like a zope.il8nmessageid.MessageFactory object. It is not a subclass, however.

17.2 Working With gettext Translation Files

The basis of Pyramid translation services is GNU *gettext*. Once your application source code files and templates are marked up with translation markers, you can work on translations by creating various kinds of gettext files.

The steps a developer must take to work with *gettext message catalog* files within a Pyramid application are very similar to the steps a *Pylons* developer must take to do the same. See the Pylons internationalization documentation for more information.

GNU gettext uses three types of files in the translation framework, .pot files, .po files and .mo files.

.pot (Portable Object Template) files

A .pot file is created by a program which searches through your project's source code and which picks out every *message identifier* passed to one of the _() functions (eg. *translation string* constructions). The list of all message identifiers is placed into a .pot file, which serves as a template for creating .po files.

.po (Portable Object) files

The list of messages in a .pot file are translated by a human to a particular language; the result is saved as a .po file.

.mo (Machine Object) files

A .po file is turned into a machine-readable binary file, which is the .mo file. Compiling the translations to machine code makes the localized program run faster.

The tools for working with *gettext* translation files related to a Pyramid application is *Babel* and *Lingua*. Lingua is a Balel extension that provides support for scraping i18n references out of Python and Chameleon files.

17.2.1 Installing Babel and Lingua

In order for the commands related to working with gettext translation files to work properly, you will need to have *Babel* and *Lingua* installed into the same environment in which Pyramid is installed.

Installation on UNIX

If the *virtualenv* into which you've installed your Pyramid application lives in /my/virtualenv, you can install Babel and Lingua like so:

```
$ cd /my/virtualenv
$ bin/easy_install Babel lingua
```

Installation on Windows

If the *virtualenv* into which you've installed your Pyramid application lives in C:\my\virtualenv, you can install Babel and Lingua like so:

```
C> cd \my\virtualenv
C> Scripts\easy_install Babel lingua
```

Changing the setup.py

You need to add a few boilerplate lines to your application's setup.py file in order to properly generate *gettext* files from your application.

See *Creating a Pyramid Project* to learn about about the composition of an application's setup.py file.

In particular, add the Babel and lingua distributions to the install_requires list and insert a set of references to *Babel message extractors* within the call to setuptools.setup() inside your application's setup.py file:

```
setup (name="mypackage",
1
          # ...
2
          install_requires = [
3
                 # ...
4
                 'Babel',
5
                 'lingua',
6
7
                 ],
          message_extractors = { '.': [
8
                 ('**.py', 'lingua_python', None ),
9
                 ('**.pt', 'lingua_xml', None ),
10
                 ]},
11
          )
12
```

The message_extractors stanza placed into the setup.py file causes the *Babel* message catalog extraction machinery to also consider *.pt files when doing message id extraction.

17.2.2 Extracting Messages from Code and Templates

Once Babel and Lingua are installed and your application's setup.py file has the correct message extractor references, you may extract a message catalog template from the code and *Chameleon* templates which reside in your Pyramid application. You run a setup.py command to extract the messages:

\$ cd /place/where/myapplication/setup.py/lives

```
$ mkdir -p myapplication/locale
```

```
$ python setup.py extract_messages
```

The message catalog .pot template will end up in:

```
myapplication/locale/myapplication.pot.
```

Translation Domains

The name myapplication above in the filename myapplication.pot denotes the *translation domain* of the translations that must be performed to localize your application. By default, the translation domain is the *project* name of your Pyramid application.

To change the translation domain of the extracted messages in your project, edit the setup.cfg file of your application, The default setup.cfg file of a Paster-generated Pyramid application has stanzas in it that look something like the following:

```
[compile_catalog]
1
   directory = myproject/locale
2
   domain = MyProject
3
   statistics = true
4
5
   [extract_messages]
6
   add_comments = TRANSLATORS:
7
   output_file = myproject/locale/MyProject.pot
8
   width = 80
9
10
11
   [init_catalog]
12
   domain = MyProject
   input_file = myproject/locale/MyProject.pot
13
   output_dir = myproject/locale
14
15
   [update_catalog]
16
   domain = MyProject
17
   input_file = myproject/locale/MyProject.pot
18
   output_dir = myproject/locale
19
   previous = true
20
```

In the above example, the project name is MyProject. To indicate that you'd like the domain of your translations to be mydomain instead, change the setup.cfg file stanzas to look like so:

```
[compile_catalog]
1
   directory = myproject/locale
2
   domain = mydomain
3
   statistics = true
4
5
   [extract messages]
6
   add_comments = TRANSLATORS:
7
   output_file = myproject/locale/mydomain.pot
8
   width = 80
9
10
   [init_catalog]
11
   domain = mydomain
12
   input_file = myproject/locale/mydomain.pot
13
   output_dir = myproject/locale
14
15
   [update_catalog]
16
   domain = mydomain
17
   input_file = myproject/locale/mydomain.pot
18
   output_dir = myproject/locale
19
   previous = true
20
```

17.2.3 Initializing a Message Catalog File

Once you've extracted messages into a .pot file (see *Extracting Messages from Code and Templates*), to begin localizing the messages present in the .pot file, you need to generate at least one .po file. A .po file represents translations of a particular set of messages to a particular locale. Initialize a .po file for a specific locale from a pre-generated .pot template by using the setup.py init_catalog command:

```
$ cd /place/where/myapplication/setup.py/lives
$ python setup.py init_catalog -l es
```

By default, the message catalog .po file will end up in:

```
myapplication/locale/es/LC_MESSAGES/myapplication.po.
```

Once the file is there, it can be worked on by a human translator. One tool which may help with this is Poedit.

Note that Pyramid itself ignores the existence of all .po files. For a running application to have translations available, a .mo file must exist. See *Compiling a Message Catalog File*.

17.2.4 Updating a Catalog File

If more translation strings are added to your application, or translation strings change, you will need to update existing .po files based on changes to the .pot file, so that the new and changed messages can also be translated or re-translated.

First, regenerate the .pot file as per *Extracting Messages from Code and Templates*. Then use the setup.py update_catalog command.

```
$ cd /place/where/myapplication/setup.py/lives
$ python setup.py update_catalog
```

17.2.5 Compiling a Message Catalog File

Finally, to prepare an application for performing actual runtime translations, compile .po files to .mo files:

```
$ cd /place/where/myapplication/setup.py/lives
$ python setup.py compile_catalog
```

This will create a .mo file for each .po file in your application. As long as the *translation directory* in which the .mo file ends up in is configured into your application, these translations will be available to Pyramid.

17.3 Using a Localizer

A *localizer* is an object that allows you to perform translation or pluralization "by hand" in an application. You may use the pyramid.il8n.get_localizer() function to obtain a *localizer*. This function will return either the localizer object implied by the active *locale negotiator* or a default localizer object if no explicit locale negotiator is registered.

```
from pyramid.i18n import get_localizer
def aview(request):
    locale = get_localizer(request)
```

● If you need to create a localizer for a locale use the pyramid.i18n.make_localizer() function.

17.3.1 Performing a Translation

A *localizer* has a translate method which accepts either a *translation string* or a Unicode string and which returns a Unicode object representing the translation. So, generating a translation in a view component of an application might look like so:

```
from pyramid.i18n import get_localizer
1
  from pyramid.i18n import TranslationString
2
3
  ts = TranslationString('Add ${number}', mapping={'number':1},
4
                          domain='pyramid')
5
6
  def aview(request):
7
      localizer = get_localizer(request)
8
      translated = localizer.translate(ts) # translation string
9
      # ... use translated ...
10
```

The get_localizer() function will return a pyramid.i18n.Localizer object bound to the locale name represented by the request. The translation returned from its pyramid.i18n.Localizer.translate() method will depend on the domain attribute of the provided translation string as well as the locale of the localizer.

U If you're using *Chameleon* templates, you don't need to pre-translate translation strings this way. See *Chameleon Template Support for Translation Strings*.

17.3.2 Performing a Pluralization

A *localizer* has a pluralize method with the following signature:

```
1 def pluralize(singular, plural, n, domain=None, mapping=None):
2 ...
```

The singular and plural arguments should each be a Unicode value representing a *message identifier*. n should be an integer. domain should be a *translation domain*, and mapping should be a dictionary that is used for *replacement value* interpolation of the translated string. If n is plural for the current locale, pluralize will return a Unicode translation for the message id plural, otherwise it will return a Unicode translation for the message id singular.

The arguments provided as singular and/or plural may also be *translation string* objects, but the domain and mapping information attached to those objects is ignored.

```
from pyramid.i18n import get_localizer
def aview(request):
    localizer = get_localizer(request)
    translated = localizer.pluralize('Item', 'Items', 1, 'mydomain')
    # ... use translated ...
```

17.4 Obtaining the Locale Name for a Request

You can obtain the locale name related to a request by using the pyramid.il8n.get_locale_name() function.

```
1 from pyramid.i18n import get_locale_name
2
3 def aview(request):
4 locale_name = get_locale_name(request)
```

This returns the locale name negotiated by the currently active *locale negotiator* or the *default locale name* if the locale negotiator returns None. You can change the default locale name by changing the default_locale_name setting; see *Default Locale Name*.

Once get_locale_name() is first run, the locale name is stored on the request object. Subsequent calls to get_locale_name() will return the stored locale name without invoking the *locale negotia-tor*. To avoid this caching, you can use the pyramid.il8n.negotiate_locale_name() function:

```
1 from pyramid.i18n import negotiate_locale_name
2
3 def aview(request):
4 locale_name = negotiate_locale_name(request)
```

You can also obtain the locale name related to a request using the locale_name attribute of a localizer.

```
from pyramid.i18n import get_localizer
def aview(request):
    localizer = get_localizer(request)
    locale_name = localizer.locale_name
```

Obtaining the locale name as an attribute of a localizer is equivalent to obtaining a locale name by calling the get_locale_name() function.

17.5 Performing Date Formatting and Currency Formatting

Pyramid does not itself perform date and currency formatting for different locales. However, *Babel* can help you do this via the babel.core.Locale class. The Babel documentation for this class provides minimal information about how to perform date and currency related locale operations. See *Installing Babel and Lingua* for information about how to install Babel.

The babel.core.Locale class requires a *locale name* as an argument to its constructor. You can use Pyramid APIs to obtain the locale name for a request to pass to the babel.core.Locale constructor; see *Obtaining the Locale Name for a Request*. For example:

```
from babel.core import Locale
from pyramid.i18n import get_locale_name
def aview(request):
    locale_name = get_locale_name(request)
    locale = Locale(locale_name)
```

17.6 Chameleon Template Support for Translation Strings

When a *translation string* is used as the subject of textual rendering by a *Chameleon* template renderer, it will automatically be translated to the requesting user's language if a suitable translation exists. This is true of both the ZPT and text variants of the Chameleon template renderers.

For example, in a Chameleon ZPT template, the translation string represented by "some_translation_string" in each example below will go through translation before being rendered:

```
<span tal:content="some_translation_string"/>
```

```
<span tal:replace="some_translation_string"/>
```

```
<span>${some_translation_string}</span>
```

<a tal:attributes="href some_translation_string">Click here

The features represented by attributes of the i18n namespace of Chameleon will also consult the Pyramid translations. See http://chameleon.repoze.org/docs/latest/i18n.html#the-i18n-namespace.

Unlike when Chameleon is used outside of Pyramid, when it is used *within* Pyramid, it does not support use of the zope.il8n translation framework. Applications which use Pyramid should use the features documented in this chapter rather than zope.il8n.

Third party Pyramid template renderers might not provide this support out of the box and may need special code to do an equivalent. For those, you can always use the more manual translation facility described in *Performing a Translation*.

17.7 Mako Pyramid I18N Support

There exists a recipe within the *Pyramid Cookbook* named "Mako Internationalization" which explains how to add idiomatic I18N support to *Mako* templates.

17.8 Localization-Related Deployment Settings

A Pyramid application will have a default_locale_name setting. This value represents the *default locale name* used when the *locale negotiator* returns None. Pass it to the Configurator constructor at startup time:

```
1 from pyramid.config import Configurator
2 config = Configurator(settings={'default_locale_name':'de'})
```

You may alternately supply a default_locale_name via an application's Paster .ini file:

```
1 [app:main]
2 use = egg:MyProject#app
3 reload_templates = true
4 debug_authorization = false
5 debug_notfound = false
6 default_locale_name = de
```

If this value is not supplied via the Configurator constructor or via a Paste config file, it will default to en.

If this setting is supplied within the Pyramid application .ini file, it will be available as a settings key:

```
1 from pyramid.threadlocal import get_current_registry
```

```
2 settings = get_current_registry().settings
```

```
3 default_locale_name = settings['default_locale_name']
```

17.9 "Detecting" Available Languages

Other systems provide an API that returns the set of "available languages" as indicated by the union of all languages in all translation directories on disk at the time of the call to the API.

It is by design that Pyramid doesn't supply such an API. Instead, the application itself is responsible for knowing the "available languages". The rationale is this: any particular application deployment must always know which languages it should be translatable to anyway, regardless of which translation files are on disk.

Here's why: it's not a given that because translations exist in a particular language within the registered set of translation directories that this particular deployment wants to allow translation to that language. For example, some translations may exist but they may be incomplete or incorrect. Or there may be translations to a language but not for all translation domains.

Any nontrivial application deployment will always need to be able to selectively choose to allow only some languages even if that set of languages is smaller than all those detected within registered translation directories. The easiest way to allow for this is to make the application entirely responsible for knowing which languages are allowed to be translated to instead of relying on the framework to divine this information from translation directory file info.

You can set up a system to allow a deployer to select available languages based on convention by using the pyramid.settings mechanism:

Allow a deployer to modify your application's PasteDeploy .ini file:

```
1 [app:main]
2 use = egg:MyProject#app
3 # ...
4 available_languages = fr de en ru
```

Then as a part of the code of a custom *locale negotiator*:

```
from pyramid.threadlocal import get_current_registry
settings = get_current_registry().settings
alanguages = settings['available_languages'].split()
```

This is only a suggestion. You can create your own "available languages" configuration scheme as necessary.

17.10 Activating Translation

By default, a Pyramid application performs no translation. To turn translation on, you must:

- add at least one translation directory to your application.
- ensure that your application sets the *locale name* correctly.

17.10.1 Adding a Translation Directory

gettext is the underlying machinery behind the Pyramid translation machinery. A translation directory is a directory organized to be useful to *gettext*. A translation directory usually includes a listing of language directories, each of which itself includes an LC_MESSAGES directory. Each LC_MESSAGES directory should contain one or more .mo files. Each .mo file represents a *message catalog*, which is used to provide translations to your application.

Adding a *translation directory* registers all of its constituent *message catalog* files within your Pyramid application to be available to use for translation services. This includes all of the .mo files found within all LC_MESSAGES directories within each locale directory in the translation directory.

You can add a translation directory imperatively by using the pyramid.config.Configurator.add_translation_dirs() during application startup. For example:

```
1 from pyramid.config import Configurator
2 config.add_translation_dirs('my.application:locale/',
3 'another.application:locale/')
```

A message catalog in a translation directory added via add_translation_dirs() will be merged into translations from a message catalog added earlier if both translation directories contain translations for the same locale and *translation domain*.

17.10.2 Setting the Locale

When the *default locale negotiator* (see *The Default Locale Negotiator*) is in use, you can inform Pyramid of the current locale name by doing any of these things before any translations need to be performed:

- Set the _LOCALE_ attribute of the request to a valid locale name (usually directly within view code). E.g. request ._LOCALE_ = 'de'.
- Ensure that a valid locale name value is in the request.params dictionary under the key named _LOCALE_. This is usually the result of passing a _LOCALE_ value in the query string or in the body of a form post associated with a request. For example, visiting http://my.application?_LOCALE_=de.
- Ensure that a valid locale name value is in the request.cookies dictionary under the key named _LOCALE_. This is usually the result of setting a _LOCALE_ cookie in a prior response, e.g. response.set_cookie('_LOCALE_', 'de').

U If this locale negotiation scheme is inappropriate for a particular application, you can configure a custom *locale negotiator* function into that application as required. See *Using a Custom Locale Negotiator*.

17.11 Locale Negotiators

A *locale negotiator* informs the operation of a *localizer* by telling it what *locale name* is related to a particular request. A locale negotiator is a bit of code which accepts a request and which returns a *locale name*. It is consulted when pyramid.il8n.Localizer.translate() or pyramid.il8n.Localizer.pluralize() is invoked. It is also consulted when get_locale_name() or negotiate_locale_name() is invoked.

17.11.1 The Default Locale Negotiator

Most applications can make use of the default locale negotiator, which requires no additional coding or configuration.

The default locale negotiator implementation named default_locale_negotiator uses the following set of steps to dermine the locale name.

- First, the negotiator looks for the _LOCALE_ attribute of the request object (possibly set directly by view code or by a listener for an *event*).
- Then it looks for the request.params['_LOCALE_'] value.
- Then it looks for the request.cookies['_LOCALE_'] value.
- If no locale can be found via the request, it falls back to using the *default locale name* (see *Localization-Related Deployment Settings*).
- Finally, if the default locale name is not explicitly set, it uses the locale name en.

17.11.2 Using a Custom Locale Negotiator

Locale negotiation is sometimes policy-laden and complex. If the (simple) default locale negotiation scheme described in *Activating Translation* is inappropriate for your application, you may create and a special *locale negotiator*. Subsequently you may override the default locale negotiator by adding your newly created locale negotiator to your application's configuration.

A locale negotiator is simply a callable which accepts a request and returns a single *locale name* or None if no locale can be determined.

Here's an implementation of a simple locale negotiator:

```
def my_locale_negotiator(request):
    locale_name = request.params.get('my_locale')
    return locale_name
```

If a locale negotiator returns None, it signifies to Pyramid that the default application locale name should be used.

You may add your newly created locale negotiator to your application's configuration by passing an object which can act as the negotiator (or a *dotted Python name* referring to the object) as the locale_negotiator argument of the Configurator instance during application startup. For example:

```
1 from pyramid.config import Configurator
2 config = Configurator(locale_negotiator=my_locale_negotiator)
```

Alternately, use the pyramid.config.Configurator.set_locale_negotiator() method.

For example:

17. INTERNATIONALIZATION AND LOCALIZATION

- from pyramid.config import Configurator
- 2 config = Configurator()
- 3 config.set_locale_negotiator(my_locale_negotiator)

CHAPTER

EIGHTEEN

VIRTUAL HOSTING

"Virtual hosting" is, loosely, the act of serving a Pyramid application or a portion of a Pyramid application under a URL space that it does not "naturally" inhabit.

Pyramid provides facilities for serving an application under a URL "prefix", as well as serving a *portion* of a *traversal* based application under a root URL.

18.1 Hosting an Application Under a URL Prefix

Pyramid supports a common form of virtual hosting whereby you can host a Pyramid application as a "subset" of some other site (e.g. under http://example.com/mypyramidapplication/ as opposed to under http://example.com/).

If you use a "pure Python" environment, this functionality is provided by Paste's urlmap "composite" WSGI application. Alternately, you can use *mod_wsgi* to serve your application, which handles this virtual hosting translation for you "under the hood".

If you use the urlmap composite application "in front" of a Pyramid application or if you use *mod_wsgi* to serve up a Pyramid application, nothing special needs to be done within the application for URLs to be generated that contain a prefix. paste.urlmap and *mod_wsgi* manipulate the *WSGI* environment in such a way that the PATH_INFO and SCRIPT_NAME variables are correct for some given prefix.

Here's an example of a PasteDeploy configuration snippet that includes a urlmap composite.

```
1 [app:mypyramidapp]
2 use = egg:mypyramidapp#app
3
4 [composite:main]
5 use = egg:Paste#urlmap
6 /pyramidapp = mypyramidapp
```

This "roots" the Pyramid application at the prefix /pyramidapp and serves up the composite as the "main" application in the file.

■ If you're using an Apache server to proxy to a Paste urlmap composite, you may have to use the ProxyPreserveHost directive to pass the original HTTP_HOST header along to the application, so URLs get generated properly. As of this writing the urlmap composite does not seem to respect the HTTP_X_FORWARDED_HOST parameter, which will contain the original host header even if HTTP_HOST is incorrect.

If you use *mod_wsgi*, you do not need to use a composite application in your .ini file. The WSGIScriptAlias configuration setting in a *mod_wsgi* configuration does the work for you:

WSGIScriptAlias /pyramidapp /Users/chrism/projects/modwsgi/env/pyramid.wsgi

In the above configuration, we root a Pyramid application at /pyramidapp within the Apache configuration.

18.2 Virtual Root Support

Pyramid also supports "virtual roots", which can be used in *traversal* -based (but not *URL dispatch* -based) applications.

Virtual root support is useful when you'd like to host some resource in a Pyramid resource tree as an application under a URL pathname that does not include the resource path itself. For example, you might want to serve the object at the traversal path /cms as an application reachable via http://example.com/ (as opposed to http://example.com/cms).

To specify a virtual root, cause an environment variable to be inserted into the WSGI environ named HTTP_X_VHM_ROOT with a value that is the absolute pathname to the resource object in the resource tree that should behave as the "root" resource. As a result, the traversal machinery will respect this value during traversal (prepending it to the PATH_INFO before traversal starts), and the pyramid.url.resource_url() API will generate the "correct" virtually-rooted URLs.

An example of an Apache mod_proxy configuration that will host the /cms subobject as http://www.example.com/ using this facility is below:

```
NameVirtualHost *:80
1
2
  <VirtualHost *:80>
3
     ServerName www.example.com
4
     RewriteEngine On
5
     RewriteRule ^/(.*) http://127.0.0.1:6543/$1 [L,P]
6
7
     ProxyPreserveHost on
     RequestHeader add X-Vhm-Root /cms
8
   </VirtualHost>
```

Use of the RequestHeader directive requires that the Apache mod_headers module be available in the Apache environment you're using.

For a Pyramid application running under *mod_wsgi*, the same can be achieved using SetEnv:

```
1 <Location />
2 SetEnv HTTP_X_VHM_ROOT /cms
3 </Location>
```

Setting a virtual root has no effect when using an application based on URL dispatch.

18.3 Further Documentation and Examples

The API documentation in *pyramid.traversal* documents a pyramid.traversal.virtual_root() API. When called, it returns the virtual root object (or the physical root object if no virtual root has been specified).

Running a Pyramid Application under mod_wsgi has detailed information about using *mod_wsgi* to serve Pyramid applications.

18. VIRTUAL HOSTING

CHAPTER

NINETEEN

UNIT, INTEGRATION, AND FUNCTIONAL TESTING

Unit testing is, not surprisingly, the act of testing a "unit" in your application. In this context, a "unit" is often a function or a method of a class instance. The unit is also referred to as a "unit under test".

The goal of a single unit test is to test **only** some permutation of the "unit under test". If you write a unit test that aims to verify the result of a particular codepath through a Python function, you need only be concerned about testing the code that *lives in the function body itself*. If the function accepts a parameter that represents a complex application "domain object" (such as a resource, a database connection, or an SMTP server), the argument provided to this function during a unit test *need not be* and likely *should not be* a "real" implementation object. For example, although a particular function may call a method of this object when the system is operating normally that would result in an email being sent, a unit test of this codepath of the function does *not* need to test that an email is actually sent. It just needs to make sure that the function calls the method of the object provided as an argument that *would* send an email if the argument happened to be the "real" implementation of an SMTP server object.

An *integration test*, on the other hand, is a different form of testing in which the interaction between two or more "units" is explicitly tested. Integration tests verify that the components of your application work together. You *might* make sure that an email was actually sent in an integration test.

A *functional test* is a form of integration test in which the application is run "literally". You would *have to* make sure that an email was actually sent in a functional test, because it tests your code end to end.

It is often considered best practice to write each type of tests for any given codebase. Unit testing often provides the opportunity to obtain better "coverage": it's usually possible to supply a unit under test with arguments and/or an environment which causes *all* of its potential codepaths to be executed. This is

usually not as easy to do with a set of integration or functional tests, but integration and functional testing provides a measure of assurance that your "units" work together, as they will be expected to when your application is run in production.

The suggested mechanism for unit and integration testing of a Pyramid application is the Python unittest module. Although this module is named unittest, it is actually capable of driving both unit and integration tests. A good unittest tutorial is available within Dive Into Python by Mark Pilgrim.

Pyramid provides a number of facilities that make unit, integration, and functional tests easier to write. The facilities become particularly useful when your code calls into Pyramid -related framework functions.

19.1 Test Set Up and Tear Down

Pyramid uses a "global" (actually *thread local*) data structure to hold on to two items: the current *request* and the current *application registry*. These data structures are available via the pyramid.threadlocal.get_current_request() and pyramid.threadlocal.get_current_registry() functions, respectively. See *Thread Locals* for information about these functions and the data structures they return.

If your code uses these get_current_* functions or calls Pyramid code which uses get_current_* functions, you will need to call pyramid.testing.setUp() in your test setup and you will need to call pyramid.testing.tearDown() in your test teardown.setUp() pushes a registry onto the *thread local* stack, which makes the get_current_* functions work. It returns a *Configurator* object which can be used to perform extra configuration required by the code under test. tearDown() pops the thread local stack.

Normally when a Configurator is used directly with the main block of a Pyramid application, it defers performing any "real work" until its .commit method is called (often implicitly by the pyramid.config.Configurator.make_wsgi_app() method). The Configurator returned by setUp() is an *autocommitting* Configurator, however, which performs all actions implied by methods called on it immediately. This is more convenient for unit-testing purposes than needing to call pyramid.config.Configurator.commit() in each test after adding extra configuration statements.

The use of the setUp() and tearDown() functions allows you to supply each unit test method in a test case with an environment that has an isolated registry and an isolated request for the duration of a single test. Here's an example of using this feature:

```
import unittest
from pyramid import testing

class MyTest(unittest.TestCase):
    def setUp(self):
        self.config = testing.setUp()

def tearDown(self):
        testing.tearDown()
```

The above will make sure that get_current_registry() called within a test case method of MyTest will return the *application registry* associated with the config Configurator instance. Each test case method attached to MyTest will use an isolated registry.

The setUp() and tearDown() functions accepts various arguments that influence the environment of the test. See the *pyramid.testing* chapter for information about the extra arguments supported by these functions.

If you also want to make get_current_request() return something other than None during the course of a single test, you can pass a *request* object into the pyramid.testing.setUp() within the setUp method of your test:

```
import unittest
  from pyramid import testing
2
3
  class MyTest (unittest.TestCase):
4
      def setUp(self):
5
          request = testing.DummyRequest()
6
          self.config = testing.setUp(request=request)
7
8
      def tearDown(self):
9
          testing.tearDown()
10
```

If you pass a *request* object into pyramid.testing.setUp() within your test case's setUp, any test method attached to the MyTest test case that directly or indirectly calls get_current_request() will receive the request object. Otherwise, during testing, get_current_request() will return None. We use a "dummy" request implementation supplied by pyramid.testing.DummyRequest because it's easier to construct than a "real" Pyramid request object.

19.1.1 What?

Thread local data structures are always a bit confusing, especially when they're used by frameworks. Sorry. So here's a rule of thumb: if you don't *know* whether you're calling code that uses the get_current_registry() or get_current_request() functions, or you don't care about any of this, but you still want to write test code, just always call pyramid.testing.setUp() in your test's setUp method and pyramid.testing.tearDown() in your tests' tearDown method. This won't really hurt anything if the application you're testing does not call any get_current * function.

19.2 Using the Configurator and pyramid.testing APIs in Unit Tests

The Configurator API and the pyramid.testing module provide a number of functions which can be used during unit testing. These functions make *configuration declaration* calls to the current *application registry*, but typically register a "stub" or "dummy" feature in place of the "real" feature that the code would call if it was being run normally.

For example, let's imagine you want to unit test a Pyramid view function.

```
from pyramid.security import has_permission
from pyramid.httpexceptions import HTTPForbidden
def view_fn(request):
    if not has_permission('edit', request.context, request):
    raise HTTPForbidden
    return {'greeting':'hello'}
```

Without doing anything special during a unit test, the call to has_permission() in this view function will always return a True value. When a Pyramid application starts normally, it will populate a *application registry* using *configuration declaration* calls made against a *Configurator*. But if this application registry is not created and populated (e.g. by initializing the configurator with an authorization policy), like when you invoke application code via a unit test, Pyramid API functions will tend to either fail or return default results. So how do you test the branch of the code in this view function that raises HTTPForbidden?

The testing API provided by Pyramid allows you to simulate various application registry registrations for use under a unit testing framework without needing to invoke the actual application configuration implied by its main function. For example, if you wanted to test the above <code>view_fn</code> (assuming it lived in the package named <code>my.package</code>), you could write a unittest.TestCase that used the testing API.

```
import unittest
1
  from pyramid import testing
2
3
  class MyTest (unittest.TestCase):
4
      def setUp(self):
5
           self.config = testing.setUp()
6
7
      def tearDown(self):
8
          testing.tearDown()
9
10
      def test_view_fn_forbidden(self):
11
           from pyramid.httpexceptions import HTTPForbidden
12
          from my.package import view_fn
13
           self.config.testing_securitypolicy(userid='hank',
14
                                                permissive=False)
15
          request = testing.DummyRequest()
16
          request.context = testing.DummyResource()
17
          self.assertRaises(HTTPForbidden, view_fn, request)
18
19
      def test_view_fn_allowed(self):
20
           from my.package import view_fn
21
           self.config.testing_securitypolicy(userid='hank',
22
                                                permissive=True)
23
          request = testing.DummyRequest()
24
          request.context = testing.DummyResource()
25
          response = view_fn(request)
26
          self.assertEqual(response, {'greeting':'hello'})
27
```

In the above example, we create a MyTest test case that inherits from unittest.TestCase. If it's in our Pyramid application, it will be found when setup.py test is run. It has two test methods.

The first test method, test_view_fn_forbidden tests the view_fn when the authentication policy forbids the current user the edit permission. Its third line registers a "dummy" "non-permissive" authorization policy using the testing_securitypolicy() method, which is a special helper method for unit testing.

We then create a pyramid.testing.DummyRequest object which simulates a WebOb request object API. A pyramid.testing.DummyRequest is a request object that requires less setup than a "real" Pyramid request. We call the function being tested with the manufactured request. When the function is called, pyramid.security.has_permission() will call the "dummy" authentication policy we've registered through testing_securitypolicy(), which denies access. We check that the view function raises a HTTPForbidden error.

The second test method, named test_view_fn_allowed tests the alternate case, where the authentication policy allows access. Notice that we pass different values to testing_securitypolicy() to obtain this result. We assert at the end of this that the view function returns a value. Note that the test calls the pyramid.testing.setUp() function in its setUp method and the pyramid.testing.tearDown() function in its tearDown method. We assign the result of pyramid.testing.setUp() as config on the unittest class. This is a *Configurator* object and all methods of the configurator can be called as necessary within tests. If you use any of the Configurator APIs during testing, be sure to use this pattern in your test case's setUp and tearDown; these methods make sure you're using a "fresh" *application registry* per test run.

See the *pyramid.testing* chapter for the entire Pyramid -specific testing API. This chapter describes APIs for registering a security policy, registering resources at paths, registering event listeners, registering views and view permissions, and classes representing "dummy" implementations of a request and a resource.

See also the various methods of the *Configurator* documented in *pyramid.config* that begin with the testing_prefix.

19.3 Creating Integration Tests

In Pyramid, a *unit test* typically relies on "mock" or "dummy" implementations to give the code under test only enough context to run.

"Integration testing" implies another sort of testing. In the context of a Pyramid, integration test, the test logic tests the functionality of some code *and* its integration with the rest of the Pyramid framework.

In Pyramid applications that are plugins to Pyramid, you can create an integration test by including it's includeme function via pyramid.config.Configurator.include() in the test's setup code. This causes the entire Pyramid environment to be set up and torn down as if your application was running "for real". This is a heavy-hammer way of making sure that your tests have enough context to run properly, and it tests your code's integration with the rest of Pyramid.

Let's demonstrate this by showing an integration test for a view. The below test assumes that your application's package name is myapp, and that there is a views module in the app with a function with the name my_view in it that returns the response 'Welcome to this application' after accessing some values that require a fully set up environment.

```
import unittest
from pyramid import testing
class ViewIntegrationTests(unittest.TestCase):
def setUp(self):
    """ This sets up the application registry with the
    registrations your application declares in its ''includeme''
```

```
function.
9
           .....
10
           import myapp
11
           self.config = testing.setUp()
12
           self.config.include('myapp')
13
14
      def tearDown(self):
15
           """ Clear out the application registry """
16
           testing.tearDown()
17
18
      def test_my_view(self):
19
           from myapp.views import my_view
20
           request = testing.DummyRequest()
21
           result = my_view(request)
22
           self.assertEqual(result.status, '200 OK')
23
           body = result.app_iter[0]
24
           self.failUnless('Welcome to' in body)
25
           self.assertEqual(len(result.headerlist), 2)
26
           self.assertEqual(result.headerlist[0],
27
                              ('Content-Type', 'text/html; charset=UTF-8'))
28
           self.assertEqual(result.headerlist[1], ('Content-Length',
29
                                                       str(len(body))))
30
```

Unless you cannot avoid it, you should prefer writing unit tests that use the Configurator API to set up the right "mock" registrations rather than creating an integration test. Unit tests will run faster (because they do less for each test) and the result of a unit test is usually easier to make assertions about.

19.4 Creating Functional Tests

Functional tests test your literal application.

The below test assumes that your application's package name is myapp, and that there is view that returns an HTML body when the root URL is invoked. It further assumes that you've added a tests_require dependency on the WebTest package within your setup.py file. *WebTest* is a functional testing package written by Ian Bicking.

```
import unittest
class FunctionalTests(unittest.TestCase):
def setUp(self):
from myapp import main
```

When this test is run, each test creates a "real" WSGI application using the main function in your myapp.___init___ module and uses *WebTest* to wrap that WSGI application. It assigns the result to self.testapp. In the test named test_root, we use the testapp's get method to invoke the root URL. We then assert that the returned HTML has the string Pyramid in it.

See the *WebTest* documentation for further information about the methods available to a webtest.TestApp instance.

CHAPTER TWENTY

RESOURCES

A *resource* is an object that represents a "place" in a tree related to your application. Every Pyramid application has at least one resource object: the *root* resource. Even if you don't define a root resource manually, a default one is created for you. The root resource is the root of a *resource tree*. A resource tree is a set of nested dictionary-like objects which you can use to represent your website's structure.

In an application which uses *traversal* to map URLs to code, the resource tree structure is used heavily to map each URL to a *view callable*. When *traversal* is used, Pyramid will walk through the resource tree by traversing through its nested dictionary structure in order to find a *context* resource. Once a context resource is found, the context resource and data in the request will be used to find a *view callable*.

In an application which uses *URL dispatch*, the resource tree is only used indirectly, and is often "invisible" to the developer. In URL dispatch applications, the resource "tree" is often composed of only the root resource by itself. This root resource sometimes has security declarations attached to it, but is not required to have any. In general, the resource tree is much less important in applications that use URL dispatch than applications that use traversal.

In "Zope-like" Pyramid applications, resource objects also often store data persistently, and offer methods related to mutating that persistent data. In these kinds of applications, resources not only represent the site structure of your website, but they become the *domain model* of the application.

Also:

- The context and containment predicate arguments to add_view() (or a view_config() decorator) reference a resource class or resource *interface*.
- A root factory returns a resource.
- A resource is exposed to *view* code as the *context* of a view.
- Various helpful Pyramid API methods expect a resource as an argument (e.g. resource_url() and others).

20.1 Defining a Resource Tree

When *traversal* is used (as opposed to a purely *url dispatch* based application), Pyramid expects to be able to traverse a tree composed of resources (the *resource tree*). Traversal begins at a root resource, and descends into the tree recursively, trying each resource's <u>___getitem__</u> method to resolve a path segment to another resource object. Pyramid imposes the following policy on resource instances in the tree:

- A container resource (a resource which contains other resources) must supply a __getitem__ method which is willing to resolve a unicode name to a sub-resource. If a sub-resource by a particular name does not exist in a container resource, __getitem__ method of the container resource must raise a KeyError. If a sub-resource by that name *does* exist, the container's __getitem__ should return the sub-resource.
- Leaf resources, which do not contain other resources, must not implement a ______, or if they do, their ______ method must always raise a KeyError.

See Traversal for more information about how traversal works against resource instances.

Here's a sample resource tree, represented by a variable named root:

```
1 class Resource(dict):
2     pass
3
4     root = Resource({'a':Resource({'c':Resource()})})
```

The resource tree we've created above is represented by a dictionary-like root object which has a single child named 'b', and 'b' has a single child named 'c', which has no children. It is therefore possible to access the 'c' leaf resource like so:

```
root['a']['b']['c']
```

If you returned the above root object from a *root factory*, the path /a/b/c would find the 'c' object in the resource tree as the result of *traversal*.

In this example, each of the resources in the tree is of the same class. This is not a requirement. Resource elements in the tree can be of any type. We used a single class to represent all resources in the tree for the sake of simplicity, but in a "real" app, the resources in the tree can be arbitrary.

Although the example tree above can service a traversal, the resource instances in the above example are not aware of *location*, so their utility in a "real" application is limited. To make best use of built-in Pyramid API facilities, your resources should be "location-aware". The next section details how to make resources location-aware.

20.2 Location-Aware Resources

In order for certain Pyramid location, security, URL-generation, and traversal APIs to work properly against the resources in a resource tree, all resources in the tree must be *location* -aware. This means they must have two attributes: ____parent___ and ____name___.

The __parent__ attribute of a location-aware resource should be a reference to the resource's parent resource instance in the tree. The __name__ attribute should be the name with which a resource's parent refers to the resource via __getitem__.

The __parent__ of the root resource should be None and its __name__ should be the empty string. For instance:

```
1 class MyRootResource(object):
2     ___name___ = ''
3     ___parent__ = None
```

A resource returned from the root resource's __getitem__ method should have a __parent__ attribute that is a reference to the root resource, and its __name__ attribute should match the name by which it is reachable via the root resource's __getitem__. A container resource within the root resource should have a __getitem__ that returns resources with a __parent__ attribute that points at the container, and these subobjects should have a __name__ attribute that matches the name by which they are retrieved from the container via __getitem__. This pattern continues recursively "up" the tree from the root.

The __parent__ attributes of each resource form a linked list that points "downwards" toward the root. This is analogous to the .. entry in filesystem directories. If you follow the __parent__ values from any resource in the resource tree, you will eventually come to the root resource, just like if you keep executing the cd .. filesystem command, eventually you will reach the filesystem root directory.

If your root resource has a __name__ argument that is not None or the empty string, URLs returned by the resource_url() function and paths generated by the resource_path() and resource_path_tuple() APIs will be generated improperly. The value of __name__ will be prepended to every path and URL generated (as opposed to a single leading slash or empty tuple element).

Using pyramid_traversalwrapper

If you'd rather not manage the ___name___ and ___parent___ attributes of your resources "by hand", an add-on package named pyramid_traversalwrapper can help. In order to use this helper feature, you must first install the pyramid_traversalwrapper package (available via PyPI), then register its ModelGraphTraverser as the traversal policy, rather than the default Pyramid traverser. The package contains instructions for doing so. Once Pyramid is configured with this feature, you will no longer need to manage the __parent__ and ___name__ attributes on resource objects "by hand". Instead, as necessary, during traversal Pyramid will wrap each resource (even the root resource) in a LocationProxy which will dynamically assign a __name__ and a __parent__ to the traversed resource (based on the last traversed resource and the name supplied to __getitem__). The root resource will have a __name__ attribute of None and a __parent__ attribute of None.

Applications which use tree-walking Pyramid APIs require location-aware resources. These APIs include (but are not limited to) resource_url(), find_resource(), find_root(), find_interface(), resource_path(), resource_path_tuple(), or traverse(), virtual_root(), and (usually) has_permission() and principals_allowed_by_permission().

In general, since so much Pyramid infrastructure depends on location-aware resources, it's a good idea to make each resource in your tree location-aware.

20.3 Generating The URL Of A Resource

If your resources are *location* aware, you can use the pyramid.url.resource_url() API to generate a URL for the resource. This URL will use the resource's position in the parent tree to create a resource path, and it will prefix the path with the current application URL to form a fully-qualified URL with the scheme, host, port, and path. You can also pass extra arguments to resource_url() to influence the generated URL.

The simplest call to resource_url() looks like this:

```
1 from pyramid.url import resource_url
2 url = resource_url(resource, request)
```

The request passed to resource_url in the above example is an instance of a Pyramid *request* object.

If the resource referred to as resource in the above example was the root resource, and the host that was used to contact the server was example.com, the URL generated would be http://example.com/. However, if the resource was a child of the root resource named a, the generated URL would be http://example.com/a/.

A slash is appended to all resource URLs when resource_url() is used to generate them in this simple manner, because resources are "places" in the hierarchy, and URLs are meant to be clicked on to be visited. Relative URLs that you include on HTML pages rendered as the result of the default view of a resource are more apt to be relative to these resources than relative to their parent.

You can also pass extra elements to resource_url():

```
1 from pyramid.url import resource_url
2 url = resource_url(resource, request, 'foo', 'bar')
```

If the resource referred to as resource in the above example was the root resource, and the host that was used to contact the server was example.com, the URL generated would be http://example.com/foo/bar. Any number of extra elements can be passed to resource_url() as extra positional arguments. When extra elements are passed, they are appended to the resource's URL. A slash is not appended to the final segment when elements are passed.

You can also pass a query string:

```
1 from pyramid.url import resource_url
2 url = resource_url(resource, request, query={'a':'1'})
```

If the resource referred to as resource in the above example was the root resource, and the host that was used to contact the server was example.com, the URL generated would be http://example.com/?a=1.

When a *virtual root* is active, the URL generated by resource_url() for a resource may be "shorter" than its physical tree path. See *Virtual Root Support* for more information about virtually rooting a resource.

The shortcut method of the *request* named pyramid.request.Request.resource_url() can be used instead of resource_url() to generate a resource URL.

For more information about generating resource URLs, see the documentation for pyramid.url.resource_url().

20.3.1 Overriding Resource URL Generation

If a resource object implements a __resource_url__ method, this method will be called when resource_url() is called to generate a URL for the resource, overriding the default URL returned for the resource by resource_url().

- physical_path The "physical path" computed for the resource, as defined by pyramid.traversal.resource_path(resource).
- virtual_path The "virtual path" computed for the resource, as defined by Virtual Root Support. This
 will be identical to the physical path if virtual rooting is not enabled.

The <u>resource_url</u> method of a resource should return a string representing a URL. If it cannot override the default, it should return None. If it returns None, the default URL will be returned.

Here's an example ____resource_url___ method.

```
1 class Resource(object):
2 def __resource_url__(self, request, info):
3 return request.application_url + info['virtual_path']
```

The above example actually just generates and returns the default URL, which would have been what was returned anyway, but your code can perform arbitrary logic as necessary. For example, your code may wish to override the hostname or port number of the generated URL.

Note that the URL generated by __resource_url__ should be fully qualified, should end in a slash, and should not contain any query string or anchor elements (only path elements) to work best with resource_url().

20.4 Generating the Path To a Resource

pyramid.traversal.resource_path() returns a string object representing the absolute physical path of the resource object based on its position in the resource tree. Each segment of the path is separated with a slash character.

```
1 from pyramid.traversal import resource_path
2 url = resource_path(resource)
```

If resource in the example above was accessible in the tree as root ['a'] ['b'], the above example would generate the string /a/b.

Any positional arguments passed in to resource_path() will be appended as path segments to the end of the resource path.

```
1 from pyramid.traversal import resource_path
2 url = resource_path(resource, 'foo', 'bar')
```

If resource in the example above was accessible in the tree as root ['a'] ['b'], the above example would generate the string /a/b/foo/bar.

The resource passed in must be *location*-aware.

The presence or absence of a virtual root has no impact on the behavior of resource_path().

20.5 Finding a Resource by Path

If you have a string path to a resource, you can grab the resource from that place in the application's resource tree using pyramid.traversal.find_resource().

You can resolve an absolute path by passing a string prefixed with a / as the path argument:

```
1 from pyramid.traversal import find_resource
2 url = find_resource(anyresource, '/path')
```

Or you can resolve a path relative to the resource you pass in by passing a string that isn't prefixed by /:

```
1 from pyramid.traversal import find_resource
2 url = find_resource(anyresource, 'path')
```

Often the paths you pass to find_resource() are generated by the resource_path() API. These APIs are "mirrors" of each other.

If the path cannot be resolved when calling find_resource() (if the respective resource in the tree does not exist), a KeyError will be raised.

See the pyramid.traversal.find_resource() documentation for more information about resolving a path to a resource.

20.6 Obtaining the Lineage of a Resource

pyramid.location.lineage() returns a generator representing the *lineage* of the *location* aware *resource* object.

The lineage () function returns the resource it is passed, then each parent of the resource, in order. For example, if the resource tree is composed like so:

```
class Thing(object): pass
thing1 = Thing()
thing2 = Thing()
thing2.__parent__ = thing1
```

Calling lineage (thing2) will return a generator. When we turn it into a list, we will get:

```
list(lineage(thing2))
[ <Thing object at thing2>, <Thing object at thing1> ]
```

The generator returned by lineage() first returns the resource it was passed unconditionally. Then, if the resource supplied a __parent__ attribute, it returns the resource represented by resource.__parent__. If *that* resource has a __parent__ attribute, return that resource's parent, and so on, until the resource being inspected either has no __parent__ attribute or has a __parent__ attribute of None.

See the documentation for pyramid.location.lineage() for more information.

20.7 Determining if a Resource is In The Lineage of Another Resource

Use the pyramid.location.inside() function to determine if one resource is in the *lineage* of another resource.

For example, if the resource tree is:

```
1 class Thing(object): pass
2 
3 a = Thing()
4 b = Thing()
5 b.__parent__ = a
```

Calling inside (b, a) will return True, because b has a lineage that includes a. However, calling inside (a, b) will return False because a does not have a lineage that includes b.

The argument list for inside() is (resource1, resource2). resource1 is 'inside' resource2 if resource2 is a *lineage* ancestor of resource1. It is a lineage ancestor if its parent (or one of its parent's parents, etc.) is an ancestor.

See pyramid.location.inside() for more information.

20.8 Finding the Root Resource

Use the pyramid.traversal.find_root() API to find the *root* resource. The root resource is the root resource of the *resource tree*. The API accepts a single argument: resource. This is a resource that is *location* aware. It can be any resource in the tree for which you want to find the root.

For example, if the resource tree is:

```
class Thing(object): pass
a = Thing()
b = Thing()
b.__parent__ = a
```

Calling find_root (b) will return a.

The root resource is also available as request.root within view callable code.

The presence or absence of a *virtual root* has no impact on the behavior of find_root(). The root object returned is always the *physical* root object.

20.9 Resources Which Implement Interfaces

Resources can optionally be made to implement an *interface*. An interface is used to tag a resource object with a "type" that can later be referred to within *view configuration* and by pyramid.traversal.find_interface().

Specifying an interface instead of a class as the context or containment predicate arguments within *view configuration* statements makes it possible to use a single view callable for more than one class of resource object. If your application is simple enough that you see no reason to want to do this, you can skip reading this section of the chapter.

For example, here's some code which describes a blog entry which also declares that the blog entry implements an *interface*.

```
import datetime
1
2 from zope.interface import implements
  from zope.interface import Interface
3
4
  class IBlogEntry(Interface):
5
      pass
6
7
  class BlogEntry(object):
8
9
      implements(IBlogEntry)
      def __init__(self, title, body, author):
10
           self.title = title
11
           self.body = body
12
           self.author = author
13
           self.created = datetime.datetime.now()
14
```

This resource consists of two things: the class which defines the resource constructor as the class BlogEntry, and an *interface* attached to the class via an implements statement at class scope using the IBlogEntry interface as its sole argument.

The interface object used must be an instance of a class that inherits from zope.interface.Interface.

A resource class may implement zero or more interfaces. You specify that a resource implements an interface by using the zope.interface.implements() function at class scope. The above BlogEntry resource implements the IBlogEntry interface.

You can also specify that a particular resource *instance* provides an interface, as opposed to its class. When you declare that a class implements an interface, all instances of that class will also provide that interface. However, you can also just say that a single object provides the interface. To do so, use the zope.interface.directlyProvides() function:

```
import datetime
  from zope.interface import directlyProvides
2
  from zope.interface import Interface
3
4
  class IBlogEntry(Interface):
5
      pass
6
7
  class BlogEntry(object):
8
      def __init__(self, title, body, author):
9
          self.title = title
10
          self.body = body
11
          self.author = author
12
           self.created = datetime.datetime.now()
13
```

14
15 entry = BlogEntry('title', 'body', 'author')
16 directlyProvides(entry, IBlogEntry)

zope.interface.directlyProvides() will replace any existing interface that was previously
provided by an instance. If a resource object already has instance-level interface declarations that you
don't want to replace, use the zope.interface.alsoProvides() function:

```
i import datetime
2 from zope.interface import alsoProvides
3 from zope.interface import directlyProvides
 from zope.interface import Interface
4
5
  class IBlogEntry1(Interface):
6
      pass
7
8
  class IBlogEntry2(Interface):
9
10
      pass
11
  class BlogEntry(object):
12
      def __init__(self, title, body, author):
13
          self.title = title
14
          self.body = body
15
          self.author = author
16
          self.created = datetime.datetime.now()
17
18
19 entry = BlogEntry('title', 'body', 'author')
20 directlyProvides(entry, IBlogEntry1)
21 alsoProvides (entry, IBlogEntry2)
```

zope.interface.alsoProvides() will augment the set of interfaces directly provided by an instance instead of overwriting them like zope.interface.directlyProvides() does.

For more information about how resource interfaces can be used by view configuration, see Using Resource Interfaces In View Configuration.

20.10 Finding a Resource With a Class or Interface in Lineage

Use the find_interface() API to locate a parent that is of a particular Python class, or which implements some *interface*.

For example, if your resource tree is composed as follows:

```
1 class Thing1(object): pass
2 class Thing2(object): pass
3
4 a = Thing1()
5 b = Thing2()
6 b.__parent__ = a
```

Calling find_interface(a, Thing1) will return the a resource because a is of class Thing1 (the resource passed as the first argument is considered first, and is returned if the class or interface spec matches).

Calling find_interface(b, Thing1) will return the a resource because a is of class Thing1 and a is the first resource in b's lineage of this class.

Calling find_interface (b, Thing2) will return the b resource.

The second argument to find_interface may also be a *interface* instead of a class. If it is an interface, each resource in the lineage is checked to see if the resource implements the specificed interface (instead of seeing if the resource is of a class). See also *Resources Which Implement Interfaces*.

20.11 Pyramid API Functions That Act Against Resources

A resource object is used as the *context* provided to a view. See *Traversal* and *URL Dispatch* for more information about how a resource object becomes the context.

The APIs provided by *pyramid.traversal* are used against resource objects. These functions can be used to find the "path" of a resource, the root resource in a resource tree, or to generate a URL for a resource.

The APIs provided by *pyramid.location* are used against resources. These can be used to walk down a resource tree, or conveniently locate one resource "inside" another.

Some APIs in *pyramid.security* accept a resource object as a parameter. For example, the has_permission() API accepts a resource object as one of its arguments; the ACL is obtained from this resource or one of its ancestors. Other APIs in the pyramid.security module also accept *context* as an argument, and a context is always a resource.

CHAPTER

TWENTYONE

MUCH ADO ABOUT TRAVERSAL

U This chapter was adapted, with permission, from a blog post by Rob Miller, originally published at http://blog.nonsequitarian.org/2010/much-ado-about-traversal/.

Traversal is an alternative to URL dispatch which allows Pyramid applications to map URLs to code.

• Ex-Zope users whom are already familiar with traversal and view lookup conceptually may want to skip directly to the *Traversal* chapter, which discusses technical details. This chapter is mostly aimed at people who have previous *Pylons* experience or experience in another framework which does not provide traversal, and need an introduction to the "why" of traversal.

Some folks who have been using Pylons and its Routes-based URL matching for a long time are being exposed for the first time, via Pyramid, to new ideas such as "*traversal*" and "*view lookup*" as a way to route incoming HTTP requests to callable code. Some of the same folks believe that traversal is hard to understand. Others question its usefulness; URL matching has worked for them so far, why should they even consider dealing with another approach, one which doesn't fit their brain and which doesn't provide any immediately obvious value?

You can be assured that if you don't want to understand traversal, you don't have to. You can happily build Pyramid applications with only *URL dispatch*. However, there are some straightforward, real-world use cases that are much more easily served by a traversal-based approach than by a pattern-matching mechanism. Even if you haven't yet hit one of these use cases yourself, understanding these new ideas is worth the effort for any web developer so you know when you might want to use them. *Traversal* is actually a straightforward metaphor easily comprehended by anyone who's ever used a run-of-the-mill file system with folders and files.

21.1 URL Dispatch

Let's step back and consider the problem we're trying to solve. An HTTP request for a particular path has been routed to our web application. The requested path will possibly invoke a specific *view callable* function defined somewhere in our app. We're trying to determine *which* callable function, if any, should be invoked for a given requested URL.

Many systems, including Pyramid, offer a simple solution. They offer the concept of "URL matching". URL matching approaches this problem by parsing the URL path and comparing the results to a set of registered "patterns", defined by a set of regular expressions, or some other URL path templating syntax. Each pattern is mapped to a callable function somewhere; if the request path matches a specific pattern, the associated function is called. If the request path matches more than one pattern, some conflict resolution scheme is used, usually a simple order precedence so that the first match will take priority over any subsequent matches. If a request path doesn't match any of the defined patterns, a "404 Not Found" response is returned.

In Pyramid, we offer an implementation of URL matching which we call *URL dispatch*. Using Pyramid syntax, we might have a match pattern such as /{userid}/photos/{photoid}, mapped to a photo_view() function defined somewhere in our code. Then a request for a path such as /joeschmoe/photos/photol would be a match, and the photo_view() function would be invoked to handle the request. Similarly, /{userid}/blog/{year}/{month}/{postid} might map to a blog_post_view() function, so /joeschmoe/blog/2010/12/urlmatching would trigger the function, which presumably would know how to find and render the urlmatching blog post.

21.2 Historical Refresher

Now that we've refreshed our understanding of *URL dispatch*, we'll dig in to the idea of traversal. Before we do, though, let's take a trip down memory lane. If you've been doing web work for a while, you may remember a time when we didn't have fancy web frameworks like *Pylons* and Pyramid. Instead, we had general purpose HTTP servers that primarily served files off of a file system. The "root" of a given site mapped to a particular folder somewhere on the file system. Each segment of the request URL path represented a subdirectory. The final path segment would be either a directory or a file, and once the server found the right file it would package it up in an HTTP response and send it back to the client. So serving up a request for /joeschmoe/photos/photol literally meant that there was a joeschmoe folder somewhere, which contained a photos folder, which in turn contained a photol file. If at any point along the way we find that there is not a folder or file matching the requested path, we return a 404 response.

As the web grew more dynamic, however, a little bit of extra complexity was added. Technologies such as CGI and HTTP server modules were developed. Files were still looked up on the file system, but if the

file ended with (for example) .cgi or .php, or if it lived in a special folder, instead of simply sending the file to the client the server would read the file, execute it using an interpreter of some sort, and then send the output from this process to the client as the final result. The server configuration specified which files would trigger some dynamic code, with the default case being to just serve the static file.

21.3 Traversal (aka Resource Location)

Believe it or not, if you understand how serving files from a file system works, you understand traversal. And if you understand that a server might do something different based on what type of file a given request specifies, then you understand view lookup.

The major difference between file system lookup and traversal is that a file system lookup steps through nested directories and files in a file system tree, while traversal steps through nested dictionary-type objects in a *resource tree*. Let's take a detailed look at one of our example paths, so we can see what I mean:

The path /joeschmoe/photos/photol, has four segments: /, joeschmoe, photos and photol. With file system lookup we might have a root folder (/) containing a nested folder (joeschmoe), which contains another nested folder (photos), which finally contains a JPG file (photol). With traversal, we instead have a dictionary-like root object. Asking for the joeschmoe key gives us another dictionary-like object. Asking this in turn for the photos key gives us yet another mapping object, which finally (hopefully) contains the resource that we're looking for within its values, referenced by the photol key.

In pure Python terms, then, the traversal or "resource location" portion of satisfying the /joeschmoe/photos/photol request will look something like this pseudocode:

```
get_root()['joeschmoe']['photos']['photo1']
```

get_root () is some function that returns a root traversal *resource*. If all of the specified keys exist, then the returned object will be the resource that is being requested, analogous to the JPG file that was retrieved in the file system example. If a KeyError is generated anywhere along the way, Pyramid will return 404. (This isn't precisely true, as you'll see when we learn about view lookup below, but the basic idea holds.)

21.4 What Is a "Resource"?

"Files on a file system I understand", you might say. "But what are these nested dictionary things? Where do these objects, these 'resources', live? What *are* they?"

Since Pyramid is not a highly opinionated framework, it makes no restriction on how a *resource* is implemented; a developer can implement them as he wishes. One common pattern used is to persist all of the resources, including the root, in a database as a graph. The root object is a dictionary-like object. Dictionary-like objects in Python supply a <u>___getitem__</u> method which is called when key lookup is done. Under the hood, when adict is a dictionary-like object, Python translates adict['a'] to adict.<u>___getitem__</u> ('a'). Try doing this in a Python interpreter prompt if you don't believe us:

```
Python 2.4.6 (#2, Apr 29 2010, 00:31:48)
 [GCC 4.4.3] on linux2
2
 Type "help", "copyright", "credits" or "license" for more information.
3
 >>> adict = {}
4
 >>> adict['a'] = 1
5
 >>> adict['a']
 1
7
 >>> adict.__getitem__('a')
8
9
 1
```

In fact, you don't need a "database" at all. You could use plain dictionaries, with your site's URL structure hard-coded directly in the Python source. Or you could trivially implement a set of objects with ______getitem___ methods that search for files in specific directories, and thus precisely recreate the traditional mechanism of having the URL path mapped directly to a folder structure on the file system. Traversal is in fact a superset of file system lookup.

See the chapter entitled Resources for a more technical overview of resources.

21.5 View Lookup

At this point we're nearly there. We've covered traversal, which is the process by which a specific resource is retrieved according to a specific URL path. But what is "view lookup"?

The need for view lookup is simple: there is more than one possible action that you might want to take after finding a *resource*. With our photo example, for instance, you might want to view the photo in a page, but you might also want to provide a way for the user to edit the photo and any associated metadata. We'll call the former the view view, and the latter will be the edit view. (Original, I know.) Pyramid has a centralized view *application registry* where named views can be associated with specific resource types. So in our example, we'll assume that we've registered view and edit views for photo objects, and that we've specified the view view as the default, so that /joeschmoe/photos/photol/view and /joeschmoe/photos/photol are equivalent. The edit view would sensibly be provided by a request for /joeschmoe/photos/photol/edit.

Hopefully it's clear that the first portion of the edit view's URL path is going to resolve to the same resource as the non-edit version, specifically the resource returned by get_root()['joeschmoe']['photos']['photo1']. But traveral ends there; the photo1 resource doesn't have an edit key. In fact, it might not even be a dictionary-like object, in which case photo1['edit'] would be meaningless. When the Pyramid resource location has been resolved to a *leaf* resource, but the entire request path has not yet been expended, the *very next* path segment is treated as a *view name*. The registry is then checked to see if a view of the given name has been specified for a resource of the given type. If so, the view callable is invoked, with the resource passed in as the related context object (also available as request.context). If a view callable could not be found, Pyramid will return a "404 Not Found" response.

You might conceptualize a request for /joeschmoe/photos/photo1/edit as ultimately converted into the following piece of Pythonic pseudocode:

```
context = get_root()['joeschmoe']['photos']['photol']
view_callable = get_view(context, 'edit')
request.context = context
view_callable(request)
```

The get_root and get_view functions don't really exist. Internally, Pyramid does something more complicated. But the example above is a reasonable approximation of the view lookup algorithm in pseudocode.

21.6 Use Cases

Why should we care about traversal? URL matching is easier to explain, and it's good enough, right?

In some cases, yes, but certainly not in all cases. So far we've had very structured URLs, where our paths have had a specific, small number of pieces, like this:

```
/{userid}/{typename}/{objectid}[/{view_name}]
```

In all of the examples thus far, we've hard coded the typename value, assuming that we'd know at development time what names were going to be used ("photos", "blog", etc.). But what if we don't know what these names will be? Or, worse yet, what if we don't know *anything* about the structure of the URLs inside a user's folder? We could be writing a CMS where we want the end user to be able to arbitrarily add content and other folders inside his folder. He might decide to nest folders dozens of layers deep. How will you construct matching patterns that could account for every possible combination of paths that might develop?

It might be possible, but it certainly won't be easy. The matching patterns are going to become complex quickly as you try to handle all of the edge cases.

With traversal, however, it's straightforward. Twenty layers of nesting would be no problem. Pyramid will happily call __getitem__ as many times as it needs to, until it runs out of path segments or until a resource raises a KeyError. Each resource only needs to know how to fetch its immediate children, the traversal algorithm takes care of the rest. Also, since the structure of the resource tree can live in the database and not in the code, it's simple to let users modify the tree at runtime to set up their own personalized "directory" structures.

Another use case in which traversal shines is when there is a need to support a context-dependent security policy. One example might be a document management infrastructure for a large corporation, where members of different departments have varying access levels to the various other departments' files. Reasonably, even specific files might need to be made available to specific individuals. Traversal does well here if your resources actually represent the data objects related to your documents, because the idea of a resource authorization is baked right into the code resolution and calling process. Resource objects can store ACLs, which can be inherited and/or overridden by the subresources.

If each resource can thus generate a context-based ACL, then whenever view code is attempting to perform a sensitive action, it can check against that ACL to see whether the current user should be allowed to perform the action. In this way you achieve so called "instance based" or "row level" security which is considerably harder to model using a traditional tabular approach. Pyramid actively supports such a scheme, and in fact if you register your views with guard permissions and use an authorization policy, Pyramid can check against a resource's ACL when deciding whether or not the view itself is available to the current user.

In summary, there are entire classes of problems that are more easily served by traversal and view lookup than by *URL dispatch*. If your problems don't require it, great: stick with *URL dispatch*. But if you're using Pyramid and you ever find that you *do* need to support one of these use cases, you'll be glad you have traversal in your toolkit.

U It is even possible to mix and match *traversal* with *URL dispatch* in the same Pyramid application. See the *Combining Traversal and URL Dispatch* chapter for details.

21. MUCH ADO ABOUT TRAVERSAL

CHAPTER

TWENTYTWO

TRAVERSAL

A *traversal* uses the URL (Universal Resource Locator) to find a *resource* located in a *resource tree*, which is a set of nested dictionary-like objects. Traversal is done by using each segment of the path portion of the URL to navigate through the *resource tree*. You might think of this as looking up files and directories in a file system. Traversal walks down the path until it finds a published resource, analogous to a file system "directory" or "file". The resource found as the result of a traversal becomes the *context* of the *request*. Then, the *view lookup* subsystem is used to find some view code willing to "publish" this resource by generating a *response*.

Using *Traversal* to map a URL to code is optional. It is often less easy to understand than *URL dispatch*, so if you're a rank beginner, it probably makes sense to use URL dispatch to map URLs to code instead of traversal. In that case, you can skip this chapter.

22.1 Traversal Details

Traversal is dependent on information in a *request* object. Every *request* object contains URL path information in the PATH_INFO portion of the WSGI environment. The PATH_INFO string is the portion of a request's URL following the hostname and port number, but before any query string elements or fragment element. For example the PATH_INFO portion of the URL http://example.com:8080/a/b/c?foo=1 is /a/b/c.

Traversal treats the PATH_INFO segment of a URL as a sequence of path segments. For example, the PATH_INFO string /a/b/c is converted to the sequence ['a', 'b', 'c'].

This path sequence is then used to descend through the *resource tree*, looking up a resource for each path segment. Each lookup uses the ____getitem___ method of a resource in the tree.

For example, if the path info sequence is ['a', 'b', 'c']:

- *Traversal* starts by acquiring the *root* resource of the application by calling the *root factory*. The *root factory* can be configured to return whatever object is appropriate as the traversal root of your application.
- Next, the first element (' a') is popped from the path segment sequence and is used as a key to lookup the corresponding resource in the root. This invokes the root resource's _____getitem___ method using that value (' a') as an argument.
- If the root resource "contains" a resource with key 'a', its __getitem__ method will return it. The *context* temporarily becomes the "A" resource.
- The next segment ('b') is popped from the path sequence, and the "A" resource's _____getitem____ is called with that value ('b') as an argument; we'll presume it succeeds.
- The "A" resource's <u>______</u> returns another resource, which we'll call "B". The *context* temporarily becomes the "B" resource.

Traversal continues until the path segment sequence is exhausted or a path element cannot be resolved to a resource. In either case, the *context* resource is the last object that the traversal successfully resolved. If any resource found during traversal lacks a ______ method, or if its ______ method raises a KeyError, traversal ends immediately, and that resource becomes the *context*.

The results of a *traversal* also include a *view name*. If traversal ends before the path segment sequence is exhausted, the *view name* is the *next* remaining path segment element. If the *traversal* expends all of the path segments, then the *view name* is the empty string (").

The combination of the context resource and the *view name* found via traversal is used later in the same request by the *view lookup* subsystem to find a *view callable*. How Pyramid performs view lookup is explained within the *View Configuration* chapter.

22.2 The Resource Tree

The resource tree is a set of nested dictionary-like resource objects that begins with a *root* resource. In order to use *traversal* to resolve URLs to code, your application must supply a *resource tree* to Pyramid.

In order to supply a root resource for an application the Pyramid *Router* is configured with a callback known as a *root factory*. The root factory is supplied by the application, at startup time, as the root_factory argument to the *Configurator*.

The root factory is a Python callable that accepts a *request* object, and returns the root object of the *resource tree*. A function, or class is typically used as an application's root factory. Here's an example of a simple root factory class:

```
1 class Root(dict):
2 def __init__(self, request):
3 pass
```

Here's an example of using this root factory within startup configuration, by passing it to an instance of a *Configurator* named config:

```
config = Configurator(root_factory=Root)
```

The root_factory argument to the Configurator constructor registers this root factory to be called to generate a root resource whenever a request enters the application. The root factory registered this way is also known as the global root factory. A root factory can alternately be passed to the Configurator as a *dotted Python name* which can refer to a root factory defined in a different module.

If no *root factory* is passed to the Pyramid *Configurator* constructor, or if the root_factory value specified is None, a *default* root factory is used. The default root factory always returns a resource that has no child resources; it is effectively empty.

Usually a root factory for a traversal-based application will be more complicated than the above Root class; in particular it may be associated with a database connection or another persistence mechanism.

Emulating the Default Root Factory

For purposes of understanding the default root factory better, we'll note that you can emulate the default root factory by using this code as an explicit root factory in your application setup:

```
1 class Root(object):
2 def __init__(self, request):
3 pass
4 
5 config = Configurator(root_factory=Root)
```

The default root factory is just a really stupid object that has no behavior or state. Using *traversal* against an application that uses the resource tree supplied by the default root resource is not very interesting, because the default root resource has no children. Its availability is more useful when you're developing an application using *URL dispatch*.

■ If the items contained within the resource tree are "persistent" (they have state that lasts longer than the execution of a single process), they become analogous to the concept of *domain model* objects used by many other frameworks.

22. TRAVERSAL

The resource tree consists of *container* resources and *leaf* resources. There is only one difference between a *container* resource and a *leaf* resource: *container* resources possess a __getitem__ method (making it "dictionary-like") while *leaf* resources do not. The __getitem__ method was chosen as the signifying difference between the two types of resources because the presence of this method is how Python itself typically determines whether an object is "containerish" or not (dictionary objects are "containerish").

Each container resource is presumed to be willing to return a child resource or raise a KeyError based on a name passed to its ___getitem__.

Leaf-level instances must not have a __getitem__. If instances that you'd like to be leaves already happen to have a __getitem__ through some historical inequity, you should subclass these resource types and cause their __getitem__ methods to simply raise a KeyError. Or just disuse them and think up another strategy.

Usually, the traversal root is a *container* resource, and as such it contains other resources. However, it doesn't *need* to be a container. Your resource tree can be as shallow or as deep as you require.

22.3 The Traversal Algorithm

This section will attempt to explain the Pyramid traversal algorithm. We'll provide a description of the algorithm, a diagram of how the algorithm works, and some example traversal scenarios that might help you understand how the algorithm operates against a specific resource tree.

We'll also talk a bit about *view lookup*. The *View Configuration* chapter discusses *view lookup* in detail, and it is the canonical source for information about views. Technically, *view lookup* is a Pyramid subsystem that is separated from traversal entirely. However, we'll describe the fundamental behavior of view lookup in the examples in the next few sections to give you an idea of how traversal and view lookup cooperate, because they are almost always used together.

22.3.1 A Description of The Traversal Algorithm

When a user requests a page from your traversal-powered application, the system uses this algorithm to find a *context* resource and a *view name*.

- 1. The request for the page is presented to the Pyramid *router* in terms of a standard *WSGI* request, which is represented by a WSGI environment and a WSGI start_response callable.
- 2. The router creates a *request* object based on the WSGI environment.
- 3. The *root factory* is called with the *request*. It returns a *root* resource.
- 4. The router uses the WSGI environment's PATH_INFO information to determine the path segments to traverse. The leading slash is stripped off PATH_INFO, and the remaining path segments are split on the slash character to form a traversal sequence.

The traversal algorithm by default attempts to first URL-unquote and then Unicode-decode each path segment derived from PATH_INFO from its natural byte string (str type) representation. URL unquoting is performed using the Python standard library urllib.unquote function. Conversion from a URL-decoded string into Unicode is attempted using the UTF-8 encoding. If any URL-unquoted path segment in PATH_INFO is not decodeable using the UTF-8 decoding, a TypeError is raised. A segment will be fully URL-unquoted and UTF8-decoded before it is passed in to the ___getitem__ of any resource during traversal.

Thus, a request with a PATH_INFO variable of /a/b/c maps to the traversal sequence [u'a', u'b', u'c'].

- 5. *Traversal* begins at the root resource returned by the root factory. For the traversal sequence [u'a', u'b', u'c'], the root resource's __getitem__ is called with the name 'a'. Traversal continues through the sequence. In our example, if the root resource's __getitem__ called with the name a returns a resource (aka resource "A"), that resource's __getitem__ is called with the name 'b'. If resource "A" returns a resource "B" when asked for 'b', resource B's __getitem__ is then asked for the name 'c', and may return resource "C".
- 6. Traversal ends when a) the entire path is exhausted or b) when any resouce raises a KeyError from its __getitem__ or c) when any non-final path element traversal does not have a __getitem__ method (resulting in a AttributeError) or d) when any path element is prefixed with the set of characters @@ (indicating that the characters following the @@ token should be treated as a *view name*).
- 7. When traversal ends for any of the reasons in the previous step, the last resource found during traversal is deemed to be the *context*. If the path has been exhausted when traversal ends, the *view name* is deemed to be the empty string ("). However, if the path was *not* exhausted before traversal terminated, the first remaining path segment is treated as the view name.


8. Any subsequent path elements after the *view name* is found are deemed the *subpath*. The subpath is always a sequence of path segments that come from PATH_INFO that are "left over" after traversal has completed.

Once the *context* resource, the *view name*, and associated attributes such as the *subpath* are located, the job of *traversal* is finished. It passes back the information it obtained to its caller, the Pyramid *Router*, which subsequently invokes *view lookup* with the context and view name information.

The traversal algorithm exposes two special cases:

- You will often end up with a *view name* that is the empty string as the result of a particular traversal. This indicates that the view lookup machinery should look up the *default view*. The default view is a view that is registered with no name or a view which is registered with a name that equals the empty string.
- If any path segment element begins with the special characters @@ (think of them as goggles), the value of that segment minus the goggle characters is considered the *view name* immediately and traversal stops there. This allows you to address views that may have the same names as resource names in the tree unambiguously.

Finally, traversal is responsible for locating a *virtual root*. A virtual root is used during "virtual hosting"; see the *Virtual Hosting* chapter for information. We won't speak more about it in this chapter.



22.3.2 Traversal Algorithm Examples

No one can be expected to understand the traversal algorithm by analogy and description alone, so let's examine some traversal scenarios that use concrete URLs and resource tree compositions.

Let's pretend the user asks for http://example.com/foo/bar/baz/biz/buz.txt. The request's PATH_INFO in that case is /foo/bar/baz/biz/buz.txt. Let's further pretend that when this request comes in that we're traversing the following resource tree:

```
/--
|
|-- foo
|
_---bar
```

Here's what happens:

- traversal traverses the root, and attempts to find "foo", which it finds.
- traversal traverses "foo", and attempts to find "bar", which it finds.
- traversal traverses "bar", and attempts to find "baz", which it does not find (the "bar" resource raises a KeyError when asked for "baz").

The fact that it does not find "baz" at this point does not signify an error condition. It signifies that:

- the context is the "bar" resource (the context is the last resource found during traversal).
- the view name is baz
- the subpath is ('biz', 'buz.txt')

At this point, traversal has ended, and view lookup begins.

Because it's the "context" resource, the view lookup machinery examines "bar" to find out what "type" it is. Let's say it finds that the context is a Bar type (because "bar" happens to be an instance of the class Bar). Using the *view name* (baz) and the type, view lookup asks the *application registry* this question:

• Please find me a *view callable* registered using a *view configuration* with the name "baz" that can be used for the class Bar.

Let's say that view lookup finds no matching view type. In this circumstance, the Pyramid *router* returns the result of the *not found view* and the request ends.

However, for this tree:

/--| |-- foo | ----bar | ----baz | biz

The user asks for http://example.com/foo/bar/baz/biz/buz.txt

- traversal traverses "foo", and attempts to find "bar", which it finds.
- traversal traverses "bar", and attempts to find "baz", which it finds.
- traversal traverses "baz", and attempts to find "biz", which it finds.
- traversal traverses "biz", and attempts to find "buz.txt" which it does not find.

The fact that it does not find a resource related to "buz.txt" at this point does not signify an error condition. It signifies that:

- the *context* is the "biz" resource (the context is the last resource found during traversal).
- the view name is "buz.txt"
- the *subpath* is an empty sequence (()).

At this point, traversal has ended, and view lookup begins.

Because it's the "context" resource, the view lookup machinery examines the "biz" resource to find out what "type" it is. Let's say it finds that the resource is a Biz type (because "biz" is an instance of the Python class Biz). Using the *view name* (buz.txt) and the type, view lookup asks the *application registry* this question:

• Please find me a *view callable* registered with a *view configuration* with the name buz.txt that can be used for class Biz.

Let's say that question is answered by the application registry; in such a situation, the application registry returns a *view callable*. The view callable is then called with the current *WebOb request* as the sole argument: request; it is expected to return a response.

The Example View Callables Accept Only a Request; How Do I Access the Context Resource?

Most of the examples in this book assume that a view callable is typically passed only a *request* object. Sometimes your view callables need access to the *context* resource, especially when you use *traversal*. You might use a supported alternate view callable argument list in your view callables such as the (context, request) calling convention described in *Alternate View Callable Argument/Calling Conventions*. But you don't need to if you don't want to. In view callables that accept only a request, the *context* resource found by traversal is available as the context attribute of the request object, e.g. request. The *view name* is available as the view_name attribute of the request object, e.g. request.view_name. Other Pyramid -specific request attributes are also available as described in *Special Attributes Added to the Request by Pyramid*.

22.3.3 Using Resource Interfaces In View Configuration

Instead of registering your views with a context that names a Python resource *class*, you can optionally register a view callable with a context which is an *interface*. An interface can be attached arbitrarily to any resource object. View lookup treats context interfaces specially, and therefore the identity of a resource can be divorced from that of the class which implements it. As a result, associating a view with an interface can provide more flexibility for sharing a single view between two or more different implementations of a resource type. For example, if two resource objects of different Python class types share the same interface, you can use the same view configuration to specify both of them as a context.

In order to make use of interfaces in your application during view dispatch, you must create an interface and mark up your resource classes or instances with interface declarations that refer to this interface.

To attach an interface to a resource *class*, you define the interface and use the zope.interface.implements() function to associate the interface with the class.

To attach an interface to a resource *instance*, you define the interface and use the zope.interface.alsoProvides() function to associate the interface with the instance. This function mutates the instance in such a way that the interface is attached to it.

```
from zope.interface import Interface
1
  from zope.interface import alsoProvides
2
3
  class IHello(Interface):
4
       """ A marker interface """
5
6
  class Hello(object):
7
      pass
8
9
10
  def make_hello():
      hello = Hello()
11
      alsoProvides (hello, IHello)
12
      return hello
13
```

Regardless of how you associate an interface, with a resource instance, or a resource class, the resulting code to associate that interface with a view callable is the same. Assuming the above code that defines an IHello interface lives in the root of your application, and its module is named "resources.py", the interface declaration below will associate the mypackage.views.hello_world view with resources that implement, or provide, this interface.

```
1 # config is an instance of pyramid.config.Configurator
2
3 config.add_view('mypackage.views.hello_world', name='hello.html',
4 context='mypackage.resources.IHello')
```

Any time a resource that is determined to be the *context* provides this interface, and a view named hello.html is looked up against it as per the URL, the mypackage.views.hello_world view callable will be invoked.

Note, in cases where a view is registered against a resource class, and a view is also registered against an interface that the resource class implements, an ambiguity arises. Views registered for the resource class take precedence over any views registered for any interface the resource class implements. Thus, if one view configuration names a context of both the class type of a resource, and another view configuration names a context of interface implemented by the resource's class, and both view configurations are otherwise identical, the view registered for the context's class will "win".

For more information about defining resources with interfaces for use within view configuration, see *Resources Which Implement Interfaces*.

22.4 References

A tutorial showing how *traversal* can be used within a Pyramid application exists in *ZODB* + *Traversal* Wiki Tutorial.

See the View Configuration chapter for detailed information about view lookup.

The pyramid.traversal module contains API functions that deal with traversal, such as traversal invocation from within application code.

The $pyramid.url.resource_url()$ function generates a URL when given a resource retrieved from a resource tree.

CHAPTER TWENTYTHREE

SECURITY

Pyramid provides an optional declarative authorization system that can prevent a *view* from being invoked based on an *authorization policy*. Before a view is invoked, the authorization system can use the credentials in the *request* along with the *context* resource to determine if access will be allowed. Here's how it works at a high level:

- A *request* is generated when a user visits the application.
- Based on the request, a *context* resource is located through *resource location*. A context is located differently depending on whether the application uses *traversal* or *URL dispatch*, but a context is ultimately found in either case. See the *URL Dispatch* chapter for more information.
- A view callable is located by view lookup using the context as well as other attributes of the request.
- If an *authentication policy* is in effect, it is passed the request; it returns some number of *principal* identifiers.
- If an *authorization policy* is in effect and the *view configuration* associated with the view callable that was found has a *permission* associated with it, the authorization policy is passed the *context*, some number of *principal* identifiers returned by the authentication policy, and the *permission* associated with the view; it will allow or deny access.
- If the authorization policy allows access, the view callable is invoked.
- If the authorization policy denies access, the view callable is not invoked; instead the *forbidden view* is invoked.

Security in Pyramid, unlike many systems, cleanly and explicitly separates authentication and authorization. Authentication is merely the mechanism by which credentials provided in the *request* are resolved to one or more *principal* identifiers. These identifiers represent the users and groups in effect during the request. Authorization then determines access based on the *principal* identifiers, the *view callable* being invoked, and the *context* resource.

Authorization is enabled by modifying your application to include an *authentication policy* and *authorization policy*. Pyramid comes with a variety of implementations of these policies. To provide maximal flexibility, Pyramid also allows you to create custom authentication policies and authorization policies.

23.1 Enabling an Authorization Policy

By default, Pyramid enables no authorization policy. All views are accessible by completely anonymous users. In order to begin protecting views from execution based on security settings, you need to enable an authorization policy.

23.1.1 Enabling an Authorization Policy Imperatively

Passing an authorization_policy argument to the constructor of the Configurator class enables an authorization policy.

You must also enable an *authentication policy* in order to enable the authorization policy. This is because authorization, in general, depends upon authentication. Use the authentication_policy argument to the Configurator class during application setup to specify an authentication policy.

For example:

the authentication_policy and authorization_policy arguments may also be passed to the Configurator as *dotted Python name* values, each representing the dotted name path to a suitable implementation global defined at Python module scope.

The above configuration enables a policy which compares the value of an "auth ticket" cookie passed in the request's environment which contains a reference to a single *principal* against the principals present in any *ACL* found in the resource tree when attempting to call some *view*.

While it is possible to mix and match different authentication and authorization policies, it is an error to pass an authentication policy without the authorization policy or vice versa to a *Configurator* constructor.

See also the pyramid.authorization and pyramid.authentication modules for alternate implementations of authorization and authentication policies.

23.2 Protecting Views with Permissions

To protect a *view callable* from invocation based on a user's security settings when a particular type of resource becomes the *context*, you must pass a *permission* to *view configuration*. Permissions are usually just strings, and they have no required composition: you can name permissions whatever you like.

For example, the following view declaration protects the view named add_entry.html when the context resource is of type Blog with the add permission using the pyramid.config.Configurator.add_view() API:

```
1 # config is an instance of pyramid.config.Configurator
2
3 config.add_view('mypackage.views.blog_entry_add_view',
4 name='add_entry.html',
5 context='mypackage.resources.Blog',
6 permission='add')
```

The equivalent view registration including the add permission name may be performed via the @view_config decorator:

```
1 from pyramid.view import view_config
2 from resources import Blog
3
4 @view_config(context=Blog, name='add_entry.html', permission='add')
5 def blog_entry_add_view(request):
6 """ Add blog entry code goes here """
7 pass
```

As a result of any of these various view configuration statements, if an authorization policy is in place when the view callable is found during normal application operations, the requesting user will need to possess the add permission against the *context* resource in order to be able to invoke the blog_entry_add_view view. If he does not, the *Forbidden view* will be invoked.

23.2.1 Setting a Default Permission

If a permission is not supplied to a view configuration, the registered view will always be executable by entirely anonymous users: any authorization policy in effect is ignored.

In support of making it easier to configure applications which are "secure by default", Pyramid allows you to configure a *default* permission. If supplied, the default permission is used as the permission string to all view registrations which don't otherwise name a permission argument.

These APIs are in support of configuring a default permission for an application:

- The default_permission constructor argument to the Configurator constructor.
- The pyramid.config.Configurator.set_default_permission() method.

When a default permission is registered:

- If a view configuration names an explicit permission, the default permission is ignored for that view registration, and the view-configuration-named permission is used.

When you register a default permission, *all* views (even *exception view* views) are protected by a permission. For all views which are truly meant to be anonymously accessible, you will need to associate the view's configuration with the __no_permission_required__ permission.

23.3 Assigning ACLs to your Resource Objects

When the default Pyramid *authorization policy* determines whether a user possesses a particular permission with respect to a resource, it examines the *ACL* associated with the resource. An ACL is associated with a resource by adding an __acl__ attribute to the resource object. This attribute can be defined on the resource *instance* if you need instance-level security, or it can be defined on the resource *class* if you just need type-level security.

For example, an ACL might be attached to the resource for a blog via its class:

```
from pyramid.security import Everyone
1
 from pyramid.security import Allow
2
3
 class Blog(object):
4
      ___acl__ = [
5
           (Allow, Everyone, 'view'),
6
          (Allow, 'group:editors', 'add'),
7
          (Allow, 'group:editors', 'edit'),
8
          1
```

Or, if your resources are persistent, an ACL might be specified via the <u>__acl__</u> attribute of an *instance* of a resource:

```
from pyramid.security import Everyone
1
  from pyramid.security import Allow
2
3
  class Blog (object):
4
      pass
5
6
  bloq = Bloq()
7
8
  blog._acl_= [
9
           (Allow, Everyone, 'view'),
10
           (Allow, 'group:editors', 'add'),
11
           (Allow, 'group:editors', 'edit'),
12
           1
13
```

Whether an ACL is attached to a resource's class or an instance of the resource itself, the effect is the same. It is useful to decorate individual resource instances with an ACL (as opposed to just decorating their class) in applications such as "CMS" systems where fine-grained access is required on an object-by-object basis.

23.4 Elements of an ACL

Here's an example ACL:

The example ACL indicates that the pyramid.security.Everyone principal – a special systemdefined principal indicating, literally, everyone – is allowed to view the blog, the group:editors principal is allowed to add to and edit the blog.

Each element of an ACL is an ACE or access control entry. For example, in the above code block, there are three ACEs: (Allow, Everyone, 'view'), (Allow, 'group:editors', 'add'), and (Allow, 'group:editors', 'edit').

The first element of any ACE is either pyramid.security.Allow, or pyramid.security.Deny, representing the action to take when the ACE matches. The second element is a *principal*. The third argument is a permission or sequence of permission names.

A principal is usually a user id, however it also may be a group id if your authentication system provides group information and the effective *authentication policy* policy is written to respect group information. For example, the pyramid.authentication.RepozeWholAuthenicationPolicy respects group information if you configure it with a callback.

Each ACE in an ACL is processed by an authorization policy *in the order dictated by the ACL*. So if you have an ACL like this:

```
from pyramid.security import Everyone
from pyramid.security import Allow
from pyramid.security import Deny

accl__ = [
    (Allow, Everyone, 'view'),
    (Deny, Everyone, 'view'),
    ]
```

The default authorization policy will *allow* everyone the view permission, even though later in the ACL you have an ACE that denies everyone the view permission. On the other hand, if you have an ACL like this:

```
from pyramid.security import Everyone
from pyramid.security import Allow
from pyramid.security import Deny

acl__ = [
    (Deny, Everyone, 'view'),
    (Allow, Everyone, 'view'),
    ]
```

The authorization policy will deny everyone the view permission, even though later in the ACL is an ACE that allows everyone.

The third argument in an ACE can also be a sequence of permission names instead of a single permission name. So instead of creating multiple ACEs representing a number of different permission grants to a single group:editors group, we can collapse this into a single ACE, as below.

23.5 Special Principal Names

Special principal names exist in the pyramid.security module. They can be imported for use in your own code to populate ACLs, e.g. pyramid.security.Everyone.

```
pyramid.security.Everyone
```

Literally, everyone, no matter what. This object is actually a string "under the hood" (system.Everyone). Every user "is" the principal named Everyone during every request, even if a security policy is not in use.

```
pyramid.security.Authenticated
```

Any user with credentials as determined by the current security policy. You might think of it as any user that is "logged in". This object is actually a string "under the hood" (system.Authenticated).

23.6 Special Permissions

Special permission names exist in the pyramid.security module. These can be imported for use in ACLs. pyramid.security.ALL_PERMISSIONS

An object representing, literally, *all* permissions. Useful in an ACL like so: (Allow, 'fred', ALL_PERMISSIONS). The ALL_PERMISSIONS object is actually a stand-in object that has a __contains__ method that always returns True, which, for all known authorization policies, has the effect of indicating that a given principal "has" any permission asked for by the system.

23.7 Special ACEs

A convenience *ACE* is defined representing a deny to everyone of all permissions in pyramid.security.DENY_ALL. This ACE is often used as the *last* ACE of an ACL to explicitly cause inheriting authorization policies to "stop looking up the traversal tree" (effectively breaking any inheritance). For example, an ACL which allows *only* fred the view permission for a particular resource despite what inherited ACLs may say when the default authorization policy is in effect might look like so:

```
1 from pyramid.security import Allow
2 from pyramid.security import DENY_ALL
3
4 __acl__ = [ (Allow, 'fred', 'view'), DENY_ALL ]
```

"Under the hood", the pyramid.security.DENY_ALL ACE equals the following:

```
1 from pyramid.security import ALL_PERMISSIONS
2 ____acl__ = [ (Deny, Everyone, ALL_PERMISSIONS) ]
```

23.8 ACL Inheritance and Location-Awareness

While the default *authorization policy* is in place, if a resource object does not have an ACL when it is the context, its *parent* is consulted for an ACL. If that object does not have an ACL, *its* parent is consulted for an ACL, ad infinitum, until we've reached the root and there are no more parents left.

In order to allow the security machinery to perform ACL inheritance, resource objects must provide *location-awareness*. Providing *location-awareness* means two things: the root object in the resource tree must have a <u>______amame___</u> attribute and a <u>_____amame___</u> attribute.

```
1 class Blog(object):
2 ____name__ = ''
3 ____parent__ = None
```

An object with a __parent__ attribute and a __name__ attribute is said to be *location-aware*. Location-aware objects define an __parent__ attribute which points at their parent object. The root object's __parent__ is None.

See *pyramid.location* for documentations of functions which use location-awareness. See also *Location-Aware Resources*.

23.9 Changing the Forbidden View

When Pyramid denies a view invocation due to an authorization denial, the special forbidden view is invoked. "Out of the box", this forbidden view is very plain. See *Changing the Forbidden View* within *Using Hooks* for instructions on how to create a custom forbidden view and arrange for it to be called when view authorization is denied.

23.10 Debugging View Authorization Failures

If your application in your judgment is allowing or denying view access inappropriately, start your application under a shell using the PYRAMID_DEBUG_AUTHORIZATION environment variable set to 1. For example:

\$ PYRAMID_DEBUG_AUTHORIZATION=1 bin/paster serve myproject.ini

When any authorization takes place during a top-level view rendering, a message will be logged to the console (to stderr) about what ACE in which ACL permitted or denied the authorization based on authentication information.

This behavior can also be turned on in the application .ini file by setting the debug_authorization key to true within the application's configuration section, e.g.:

```
1 [app:main]
2 use = egg:MyProject#app
3 debug_authorization = true
```

With this debug flag turned on, the response sent to the browser will also contain security debugging information in its body.

23.11 Debugging Imperative Authorization Failures

The pyramid.security.has_permission() API is used to check security within view functions imperatively. It returns instances of objects that are effectively booleans. But these objects are not raw True or False objects, and have information attached to them about why the permission was allowed or denied. The object will be one of pyramid.security.ACLAllowed, pyramid.security.ACLDenied, pyramid.security.Allowed, or pyramid.security.Denied, as documented in pyra*mid.security*. At the very minimum these objects will have a msg attribute, which is a string indicating why the permission was denied or allowed. Introspecting this information in the debugger or via print statements when a call to has permission () fails is often useful.

23.12 Creating Your Own Authentication Policy

Pyramid ships with a number of useful out-of-the-box security policies (see pyramid.authentication). However, creating your own authentication policy is often necessary when you want to control the "horizontal and vertical" of how your users authenticate. Doing so is a matter of creating an instance of something that implements the following interface:

```
class IAuthenticationPolicy(object):
       """ An object representing a Pyramid authentication policy. """
2
3
      def authenticated_userid(self, request):
4
          """ Return the authenticated userid or ''None'' if no
5
          authenticated userid can be found. This method of the policy
6
          should ensure that a record exists in whatever persistent store is
7
          used related to the user (the user should not have been deleted);
8
          if a record associated with the current id does not exist in a
9
          persistent store, it should return ''None''."""
10
11
      def unauthenticated_userid(self, request):
12
           """ Return the *unauthenticated* userid. This method performs the
13
          same duty as ''authenticated_userid'' but is permitted to return the
14
          userid based only on data present in the request; it needn't (and
15
          shouldn't) check any persistent store to ensure that the user record
16
          related to the request userid exists."""
17
18
      def effective_principals(self, request):
19
           """ Return a sequence representing the effective principals
20
          including the userid and any groups belonged to by the current
21
          user, including 'system' groups such as
22
           ''pyramid.security.Everyone'' and
23
           ''pyramid.security.Authenticated''.
                                                n n n
24
25
      def remember(self, request, principal, **kw):
26
           """ Return a set of headers suitable for 'remembering' the
27
          principal named ''principal'' when set in a response. An
28
          individual authentication policy and its consumers can decide
29
          on the composition and meaning of **kw. """
30
31
      def forget(self, request):
32
           """ Return a set of headers suitable for 'forgetting' the
33
          current user on subsequent requests.
                                                 34
```

After you do so, you can pass an instance of such a class into the Configurator class at configuration time as authentication_policy to use it.

23.13 Creating Your Own Authorization Policy

An authorization policy is a policy that allows or denies access after a user has been authenticated. By default, Pyramid will use the pyramid.authorization.ACLAuthorizationPolicy if an authentication policy is activated and an authorization policy isn't otherwise specified.

In some cases, it's useful to be able to use a different authorization policy than the default ACLAuthorizationPolicy. For example, it might be desirable to construct an alternate authorization policy which allows the application to use an authorization mechanism that does not involve *ACL* objects.

Pyramid ships with only a single default authorization policy, so you'll need to create your own if you'd like to use a different one. Creating and using your own authorization policy is a matter of creating an instance of an object that implements the following interface:

```
class IAuthorizationPolicy(object):
1
      """ An object representing a Pyramid authorization policy. """
2
      def permits(self, context, principals, permission):
3
          """ Return ''True'' if any of the ''principals'' is allowed the
4
           ''permission'' in the current ''context'', else return ''False''
5
          .....
6
7
      def principals_allowed_by_permission(self, context, permission):
8
          """ Return a set of principal identifiers allowed by the
9
           "permission" in "context". This behavior is optional; if you
10
          choose to not implement it you should define this method as
11
          something which raises a ''NotImplementedError''. This method
12
          will only be called when the
13
           ''pyramid.security.principals_allowed_by_permission'' API is
14
          used."""
15
```

After you do so, you can pass an instance of such a class into the Configurator class at configuration time as authorization_policy to use it.

COMBINING TRAVERSAL AND URL DISPATCH

When you write most Pyramid applications, you'll be using one or the other of two available *resource location* subsystems: traversal or URL dispatch. However, to solve a limited set of problems, it's useful to use *both* traversal and URL dispatch together within the same application. Pyramid makes this possible via *hybrid* applications.

Reasoning about the behavior of a "hybrid" URL dispatch + traversal application can be challenging. To successfully reason about using URL dispatch and traversal together, you need to understand URL pattern matching, root factories, and the *traversal* algorithm, and the potential interactions between them. Therefore, we don't recommend creating an application that relies on hybrid behavior unless you must.

24.1 A Review of Non-Hybrid Applications

When used according to the tutorials in its documentation Pyramid is a "dual-mode" framework: the tutorials explain how to create an application in terms of using either *url dispatch or traversal*. This chapter details how you might combine these two dispatch mechanisms, but we'll review how they work in isolation before trying to combine them.

24.1.1 URL Dispatch Only

An application that uses *url dispatch* exclusively to map URLs to code will often have statements like this within application startup configuration:

```
1 # config is an instance of pyramid.config.Configurator
2
3 config.add_route('foobar', '{foo}/{bar}')
4 config.add_route('bazbuz', '{baz}/{buz}')
5
6 config.add_view('myproject.views.foobar', route_name='foobar')
7 config.add_view('myproject.views.bazbuz', route_name='bazbuz')
```

Each *route* corresponds to one or more view callables. Each view callable is associated with a route by passing a route_name parameter that matches its name during a call to add_view(). When a route is matched during a request, *view lookup* is used to match the request to its associated view callable. The presence of calls to add_route() signify that an application is using URL dispatch.

24.1.2 Traversal Only

An application that uses only traversal will have view configuration declarations that look like this:

```
1 # config is an instance of pyramid.config.Configurator
2
3 config.add_view('mypackage.views.foobar', name='foobar')
4 config.add_view('mypackage.views.bazbuz', name='bazbuz')
```

When the above configuration is applied to an application, the mypackage.views.foobar view callable above will be called when the URL /foobar is visited. Likewise, the view mypackage.views.bazbuz will be called when the URL /bazbuz is visited.

Typically, an application that uses traversal exclusively won't perform any calls to pyramid.config.Configurator.add_route() in its startup code.

24.2 Hybrid Applications

Either traversal or url dispatch alone can be used to create a Pyramid application. However, it is also possible to combine the concepts of traversal and url dispatch when building an application: the result is a hybrid application. In a hybrid application, traversal is performed *after* a particular route has matched.

A hybrid application is a lot more like a "pure" traversal-based application than it is like a "pure" URLdispatch based application. But unlike in a "pure" traversal-based application, in a hybrid application, *traversal* is performed during a request after a route has already matched. This means that the URL pattern that represents the pattern argument of a route must match the PATH_INFO of a request, and after the route pattern has matched, most of the "normal" rules of traversal with respect to *resource location* and *view lookup* apply.

There are only four real differences between a purely traversal-based application and a hybrid application:

- In a purely traversal based application, no routes are defined; in a hybrid application, at least one route will be defined.
- In a purely traversal based application, the root object used is global, implied by the *root factory* provided at startup time; in a hybrid application, the *root* object at which traversal begins may be varied on a per-route basis.
- In a purely traversal-based application, the PATH_INFO of the underlying *WSGI* environment is used wholesale as a traversal path; in a hybrid application, the traversal path is not the entire PATH_INFO string, but a portion of the URL determined by a matching pattern in the matched route configuration's pattern.
- In a purely traversal based application, view configurations which do not mention a route_name argument are considered during *view lookup*; in a hybrid application, when a route is matched, only view configurations which mention that route's name as a route_name are considered during *view lookup*.

More generally, a hybrid application *is* a traversal-based application except:

- the traversal *root* is chosen based on the route configuration of the route that matched instead of from the root_factory supplied during application startup configuration.
- the traversal *path* is chosen based on the route configuration of the route that matched rather than from the PATH_INFO of a request.
- the set of views that may be chosen during *view lookup* when a route matches are limited to those which specifically name a route_name in their configuration that is the same as the matched route's name.

To create a hybrid mode application, use a *route configuration* that implies a particular *root factory* and which also includes a pattern argument that contains a special dynamic part: either *traverse or *subpath.

24.2.1 The Root Object for a Route Match

A hybrid application implies that traversal is performed during a request after a route has matched. Traversal, by definition, must always begin at a root object. Therefore it's important to know *which* root object will be traversed after a route has matched.

Figuring out which *root* object results from a particular route match is straightforward. When a route is matched:

- If the route's configuration has a factory argument which points to a *root factory* callable, that callable will be called to generate a *root* object.
- If the route's configuration does not have a factory argument, the *global root factory* will be called to generate a *root* object. The global root factory is the callable implied by the root_factory argument passed to the Configurator at application startup time.
- If a root_factory argument is not provided to the Configurator at startup time, a *default* root factory is used. The default root factory is used to generate a root object.

• Root factories related to a route were explained previously within *Route Factories*. Both the global root factory and default root factory were explained previously within *The Resource Tree*.

24.2.2 Using *traverse In a Route Pattern

A hybrid application most often implies the inclusion of a route configuration that contains the special token *traverse at the end of a route's pattern:

```
config.add_route('home', '{foo}/{bar}/*traverse')
```

A *traverse token at the end of the pattern in a route's configuration implies a "remainder" *capture* value. When it is used, it will match the remainder of the path segments of the URL. This remainder becomes the path used to perform traversal.

The *remainder route pattern syntax is explained in more detail within Route Pattern Syntax.

A hybrid mode application relies more heavily on *traversal* to do *resource location* and *view lookup* than most examples indicate within *URL Dispatch*.

Because the pattern of the above route ends with *traverse, when this route configuration is matched during a request, Pyramid will attempt to use *traversal* against the *root* object implied by the *root factory* that is implied by the route's configuration. Since no root_factory argument is explicitly specified for this route, this will either be the *global* root factory for the application, or the *default* root factory. Once *traversal* has found a *context* resource, *view lookup* will be invoked in almost exactly the same way it would have been invoked in a "pure" traversal-based application.

Let's assume there is no *global root factory* configured in this application. The *default root factory* cannot be traversed: it has no useful ____getitem___ method. So we'll need to associate this route configuration with a custom root factory in order to create a useful hybrid application. To that end, let's imagine that we've created a root factory that looks like so in a module named routes.py:

```
class Resource (object):
1
      def __init__(self, subobjects):
2
          self.subobjects = subobjects
3
4
      def __getitem__(self, name):
5
          return self.subobjects[name]
6
7
  root = Resource(
8
           {'a': Resource({'b': Resource({'c': Resource({})})})
9
          )
10
11
  def root_factory(request):
12
      return root
13
```

Above, we've defined a (bogus) resource tree that can be traversed, and a root_factory function that can be used as part of a particular route configuration statement:

```
1 config.add_route('home', '{foo}/{bar}/*traverse',
2 factory='mypackage.routes.root_factory')
```

The factory above points at the function we've defined. It will return an instance of the Resource class as a root object whenever this route is matched. Instances of the Resource class can be used for tree traversal because they have a ______ method that does something nominally useful. Since traversal uses _______ to walk the resources of a resource tree, using traversal against the root resource implied by our route statement is a reasonable thing to do.

We could have also used our root_factory function as the root_factory argument of the Configurator constructor, instead of associating it with a particular route inside the route's configuration. Every hybrid route configuration that is matched but which does *not* name a factory attribute will use the use global root_factory function to generate a root object.

24. COMBINING TRAVERSAL AND URL DISPATCH

When the route configuration named home above is matched during a request, the matchdict generated will be based on its pattern: {foo}/{bar}/*traverse. The "capture value" implied by the *traverse element in the pattern will be used to traverse the resource tree in order to find a context resource, starting from the root object returned from the root factory. In the above example, the *root* object found will be the instance named root in routes.py.

If the URL that matched a route with the pattern $\{foo\}/\{bar\}/*traverse$, is http://example.com/one/two/a/b/c, the traversal path used against the root object will be a/b/c. As a result, Pyramid will attempt to traverse through the edges 'a', 'b', and 'c', beginning at the root object.

In our above example, this particular set of traversal steps will mean that the *context* resource of the view would be the Resource object we've named 'c' in our bogus resource tree and the *view name* resulting from traversal will be the empty string; if you need a refresher about why this outcome is presumed, see *The Traversal Algorithm*.

At this point, a suitable view callable will be found and invoked using *view lookup* as described in *View Configuration*, but with a caveat: in order for view lookup to work, we need to define a view configuration that will match when *view lookup* is invoked after a route matches:

```
1 config.add_route('home', '{foo}/{bar}/*traverse',
2 factory='mypackage.routes.root_factory')
3 config.add_view('mypackage.views.myview', route_name='home')
```

Note that the above call to add_view() includes a route_name argument. View configurations that include a route_name argument are meant to associate a particular view declaration with a route, using the route's name, in order to indicate that the view should *only be invoked when the route matches*.

Calls to add_view() may pass a route_name attribute, which refers to the value of an existing route's name argument. In the above example, the route name is home, referring to the name of the route defined above it.

The above mypackage.views.myview view callable will be invoked when:

- the route named "home" is matched
- the view name resulting from traversal is the empty string.
- the *context* resource is any object.

It is also possible to declare alternate views that may be invoked when a hybrid route is matched:

```
1 config.add_route('home', '{foo}/{bar}/*traverse',
2 factory='mypackage.routes.root_factory')
3 config.add_view('mypackage.views.myview', route_name='home')
4 config.add_view('mypackage.views.another_view', route_name='home',
5 name='another')
```

The add_view call for mypackage.views.another_view above names a different view and, more importantly, a different view name. The above mypackage.views.another_view view will be invoked when:

- the route named "home" is matched
- the view name resulting from traversal is another.
- the *context* resource is any object.

For instance, if the URL http://example.com/one/two/a/another is provided to an application that uses the previously mentioned resource tree, the mypackage.views.another view callable will be called instead of the mypackage.views.myview view callable because the *view name* will be another instead of the empty string.

More complicated matching can be composed. All arguments to *route* configuration statements and *view* configuration statements are supported in hybrid applications (such as *predicate* arguments).

24.2.3 Using the traverse Argument In a Route Definition

Rather than using the *traverse remainder marker in a pattern, you can use the traverse argument to the add_route() method.

When you use the *traverse* remainder marker, the traversal path is limited to being the remainder segments of a request URL when a route matches. However, when you use the *traverse* argument or attribute, you have more control over how to compose a traversal path.

Here's a use of the traverse pattern in a call to add_route():

1

2

24. COMBINING TRAVERSAL AND URL DISPATCH

The syntax of the traverse argument is the same as it is for pattern.

If, as above, the pattern provided is /articles/{article}/edit, and the traverse argument provided is /{article}, when a request comes in that causes the route to match in such a way that the article match value is 1 (when the request URI is /articles/1/edit), the traversal path will be generated as /1. This means that the root object's __getitem__ will be called with the name 1 during the traversal phase. If the 1 object exists, it will become the *context* of the request. The *Traversal* chapter has more information about traversal.

If the traversal path contains segment marker names which are not present in the pattern argument, a runtime error will occur. The traverse pattern should not contain segment markers that do not exist in the path.

Note that the traverse argument is ignored when attached to a route that has a *traverse remainder marker in its pattern.

Traversal will begin at the root object implied by this route (either the global root, or the object returned by the factory associated with this route).

Making Global Views Match

By default, only view configurations that mention a route_name will be found during view lookup when a route that has a *traverse in its pattern matches. You can allow views without a route_name attribute to match a route by adding the use_global_views flag to the route definition. For example, the myproject.views.bazbuz view below will be found if the route named abc below is matched and the PATH_INFO is /abc/bazbuz, even though the view configuration statement does not have the route_name="abc" attribute.

```
1 config.add_route('abc', '/abc/*traverse', use_global_views=True)
2 config.add_view('myproject.views.bazbuz', name='bazbuz')
```

24.2.4 Using *subpath in a Route Pattern

There are certain extremely rare cases when you'd like to influence the traversal *subpath* when a route matches without actually performing traversal. For instance, the pyramid.wsgi.wsgiapp2() decorator and the pyramid.static.static_view helper attempt to compute PATH_INFO from the request's subpath when its use_subpath argument is True, so it's useful to be able to influence this value.

When **subpath* exists in a pattern, no path is actually traversed, but the traversal algorithm will return a *subpath* list implied by the capture value of **subpath*. You'll see this pattern most commonly in route declarations that look like this:

```
from pryamid.static import static_view
www = static_view('mypackage:static', use_subpath=True)
s config.add_route('static', '/static/*subpath')
config.add_view(www, route_name='static')
```

mypackage.views.www is an instance of pyramid.static.static_view. This effectively tells the static helper to traverse everything in the subpath as a filename.

24.3 Corner Cases

A number of corner case "gotchas" exist when using a hybrid application. We'll detail them here.

24.3.1 Registering a Default View for a Route That Has a view Attribute

As of Pyramid 1.1 this section is slated to be removed in a later documentation release because the the ability to add views directly to the *route configuration* by passing a view argument to add_route has been deprecated.

It is an error to provide *both* a view argument to a *route configuration and* a *view configuration* which names a route_name that has no name value or the empty name value. For example, this pair of declarations will generate a conflict error at startup time.

```
1 config.add_route('home', '{foo}/{bar}/*traverse',
2 view='myproject.views.home')
3 config.add_view('myproject.views.another', route_name='home')
```

This is because the view argument to the add_route() above is an *implicit* default view when that route matches. add_route calls don't *need* to supply a view attribute. For example, this add_route call:

```
1 config.add_route('home', '{foo}/{bar}/*traverse',
2 view='myproject.views.home')
```

Can also be spelled like so:

24. COMBINING TRAVERSAL AND URL DISPATCH

```
1 config.add_route('home', '{foo}/{bar}/*traverse')
2 config.add_view('myproject.views.home', route_name='home')
```

The two spellings are logically equivalent. In fact, the former is just a syntactical shortcut for the latter.

24.3.2 Binding Extra Views Against a Route Configuration that Doesn't Have a *traverse Element In Its Pattern

Here's another corner case that just makes no sense:

```
1 config.add_route('abc', '/abc', view='myproject.views.abc')
2 config.add_view('myproject.views.bazbuz', name='bazbuz',
3 route_name='abc')
```

The above view declaration is useless, because it will never be matched when the route it references has matched. Only the view associated with the route itself (myproject.views.abc) will ever be invoked when the route matches, because the default view is always invoked when a route matches and when no post-match traversal is performed.

To make the above view declaration useful, the special *traverse token must end the route's pattern. For example:

```
1 config.add_route('abc', '/abc/*traverse', view='myproject.views.abc')
2 config.add_view('myproject.views.bazbuz', name='bazbuz',
3 route_name='abc')
```

With the above configuration, the myproject.views.bazbuz view will be invoked when the request URI is /abc/bazbuz, assuming there is no object contained by the root object with the key bazbuz. A different request URI, such as /abc/foo/bar, would invoke the default myproject.views.abc view.

CHAPTER TWENTYFIVE

USING HOOKS

"Hooks" can be used to influence the behavior of the Pyramid framework in various ways.

25.1 Changing the Not Found View

When Pyramid can't map a URL to view code, it invokes a *not found view*, which is a *view callable*. A default notfound view exists. The default not found view can be overridden through application configuration.

The *not found view* callable is a view callable like any other. The *view configuration* which causes it to be a "not found" view consists only of naming the pyramid.httpexceptions.HTTPNotFound class as the context of the view configuration.

If your application uses *imperative configuration*, you can replace the Not Found view by using the pyramid.config.Configurator.add_view() method to register an "exception view":

```
1 from pyramid.httpexceptions import HTTPNotFound
2 from helloworld.views import notfound_view
3 config.add_view(notfound_view, context=HTTPNotFound)
```

Replace helloworld.views.notfound_view with a reference to the *view callable* you want to use to represent the Not Found view.

Like any other view, the notfound view must accept at least a request parameter, or both context and request. The request is the current *request* representing the denied action. The context (if used in the call signature) will be the instance of the HTTPNotFound exception that caused the view to be called.

Here's some sample code that implements a minimal NotFound view callable:

2

3

```
from pyramid.httpexceptions import HTTPNotFound
 def notfound_view(request):
      return HTTPNotFound()
4
```

(i) When a NotFound view callable is invoked, it is passed a *request*. The exception attribute of the request will be an instance of the HTTPNotFound exception that caused the not found view to be called. The value of request.exception.message will be a value explaining why the not found error was raised. This message will be different when the debug_notfound environment setting is true than it is when it is false.

4 When a NotFound view callable accepts an argument list as described in Alternate View Callable Argument/Calling Conventions, the context passed as the first argument to the view callable will be the HTTPNotFound exception instance. If available, the resource context will still be available as request.context.

25.2 Changing the Forbidden View

When Pyramid can't authorize execution of a view based on the *authorization policy* in use, it invokes a forbidden view. The default forbidden response has a 403 status code and is very plain, but the view which generates it can be overridden as necessary.

The forbidden view callable is a view callable like any other. The view configuration which causes it to be a "forbidden" view consists only of naming the pyramid. httpexceptions. HTTPForbidden class as the context of the view configuration.

You can replace the forbidden view by using the pyramid.config.Configurator.add view() method to register an "exception view":

```
1 from helloworld.views import forbidden_view
2 from pyramid.httpexceptions import HTTPForbidden
 config.add_view(forbidden_view, context=HTTPForbidden)
3
```

Replace helloworld.views.forbidden_view with a reference to the Python *view callable* you want to use to represent the Forbidden view.

Like any other view, the forbidden view must accept at least a request parameter, or both context and request. The context (available as request.context if you're using the request-only view argument pattern) is the context found by the router when the view invocation was denied. The request is the current *request* representing the denied action.

Here's some sample code that implements a minimal forbidden view:

```
1 from pyramid.views import view_config
2 from pyramid.response import Response
3 def forbidden_view(request):
5 return Response('forbidden')
```

When a forbidden view callable is invoked, it is passed a *request*. The exception attribute of the request will be an instance of the HTTPForbidden exception that caused the forbidden view to be called. The value of request.exception.message will be a value explaining why the forbidden was raised and request.exception.result will be extended information about the forbidden exception. These messages will be different when the debug_authorization environment setting is true than it is when it is false.

25.3 Changing the Request Factory

Whenever Pyramid handles a *WSGI* request, it creates a *request* object based on the WSGI environment it has been passed. By default, an instance of the pyramid.request.Request class is created to represent the request object.

The class (aka "factory") that Pyramid uses to create a request object instance can be changed by passing a request_factory argument to the constructor of the *configurator*. This argument can be either a callable or a *dotted Python name* representing a callable.

```
from pyramid.request import Request
class MyRequest(Request):
    pass
    config = Configurator(request_factory=MyRequest)
```

If you're doing imperative configuration, and you'd rather do it after vou've already constructed а *configurator* it can also be registered via the pyramid.config.Configurator.set request factory() method:

```
1 from pyramid.config import Configurator
2 from pyramid.request import Request
3
4 class MyRequest(Request):
5     pass
6
7 config = Configurator()
8 config.set_request_factory(MyRequest)
```

25.4 Using The Before Render Event

Subscribers to the pyramid.events.BeforeRender event may introspect and modify the set of *renderer globals* before they are passed to a *renderer*. This event object iself has a dictionary-like interface that can be used for this purpose. For example:

```
1 from pyramid.events import subscriber
2 from pyramid.events import BeforeRender
3
4 @subscriber(BeforeRender)
5 def add_global(event):
6 event['mykey'] = 'foo'
```

An object of this type is sent as an event just before a *renderer* is invoked (but *after* the application-level renderer globals factory added via set_renderer_globals_factory, if any, has injected its own keys into the renderer globals dictionary).

If a subscriber attempts to add a key that already exist in the renderer globals dictionary, a KeyError is raised. This limitation is enforced because event subscribers do not possess any relative ordering. The set of keys added to the renderer globals dictionary by all pyramid.events.BeforeRender subscribers and renderer globals factories must be unique.

See the API documentation for the BeforeRender event interface at pyramid.interfaces.IBeforeRender.

Another (deprecated) mechanism which allows event subscribers more control when adding renderer global values exists in *Adding Renderer Globals (Deprecated)*.

25.5 Adding Renderer Globals (Deprecated)

this feature is deprecated as of Pyramid 1.1. A non-deprecated mechanism which allows event subscribers to add renderer global values is documented in *Using The Before Render Event*.

Whenever Pyramid handles a request to perform a rendering (after a view with a renderer= configuration attribute is invoked, or when any of the methods beginning with render within the pyramid.renderers module are called), *renderer globals* can be injected into the *system* values sent to the renderer. By default, no renderer globals are injected, and the "bare" system values (such as request, context, and renderer_name) are the only values present in the system dictionary passed to every renderer.

A callback that Pyramid will call every time a renderer is invoked can be added by passing a renderer_globals_factory argument to the constructor of the *configurator*. This callback can either be a callable object or a *dotted Python name* representing such a callable.

```
def renderer_globals_factory(system):
    return {'a': 1}
    config = Configurator(
        renderer_globals_factory=renderer_globals_factory)
```

Such a callback must accept a single positional argument (notionally named system) which will contain the original system values. It must return a dictionary of values that will be merged into the system dictionary. See *System Values Used During Rendering* for description of the values present in the system dictionary.

If you're doing imperative configuration, and you'd rather do it after vou've already constructed configurator also be registered via the а it can pyramid.config.Configurator.set renderer globals factory() method:

```
from pyramid.config import Configurator
def renderer_globals_factory(system):
    return {'a': 1}
config = Configurator()
config.set_renderer_globals_factory(renderer_globals_factory)
```

25.6 Using Response Callbacks

Unlike many other web frameworks, Pyramid does not eagerly create a global response object. Adding a *response callback* allows an application to register an action to be performed against whatever response object is returned by a view, usually in order to mutate the response.

The pyramid.request.Request.add_response_callback() method is used to register a response callback.

A response callback is a callable which accepts two positional parameters: request and response. For example:

```
def cache_callback(request, response):
    """Set the cache_control max_age for the response"""
    if request.exception is not None:
        response.cache_control.max_age = 360
    request.add_response_callback(cache_callback)
```

No response callback is called if an unhandled exception happens in application code, or if the response object returned by a *view callable* is invalid. Response callbacks *are*, however, invoked when a *exception view* is rendered successfully: in such a case, the request.exception attribute of the request when it enters a response callback will be an exception object instead of its default value of None.

Response callbacks are called in the order they're added (first-to-most-recently-added). All response callbacks are called *after* the NewResponse event is sent. Errors raised by response callbacks are not handled specially. They will be propagated to the caller of the Pyramid router application.

A response callback has a lifetime of a *single* request. If you want a response callback to happen as the result of *every* request, you must re-register the callback into every new request (perhaps within a subscriber of a NewRequest event).

25.7 Using Finished Callbacks

A *finished callback* is a function that will be called unconditionally by the Pyramid *router* at the very end of request processing. A finished callback can be used to perform an action at the end of a request unconditionally.

The pyramid.request.Request.add_finished_callback() method is used to register a finished callback.

A finished callback is a callable which accepts a single positional parameter: request. For example:

```
import transaction
1
2
 def commit_callback(request):
3
      '''commit or abort the transaction associated with request'''
4
      if request.exception is not None:
5
          transaction.abort()
6
      else:
7
          transaction.commit()
8
 request.add_finished_callback(commit_callback)
```

Finished callbacks are called in the order they're added (first-to-most-recently-added). Finished callbacks (unlike a *response callback*) are *always* called, even if an exception happens in application code that prevents a response from being generated.

The set of finished callbacks associated with a request are called *very late* in the processing of that request; they are essentially the very last thing called by the *router* before a request "ends". They are called after response processing has already occurred in a top-level finally: block within the router request processing code. As a result, mutations performed to the request provided to a finished callback will have no meaningful effect, because response processing will have already occurred, and the request's scope will expire almost immediately after all finished callbacks have been processed.

It is often necessary to tell whether an exception occurred within *view callable* code from within a finished callback: in such a case, the request.exception attribute of the request when it enters a response callback will be an exception object instead of its default value of None.

Errors raised by finished callbacks are not handled specially. They will be propagated to the caller of the Pyramid router application.

A finished callback has a lifetime of a *single* request. If you want a finished callback to happen as the result of *every* request, you must re-register the callback into every new request (perhaps within a subscriber of a NewRequest event).

25.8 Changing the Traverser

The default *traversal* algorithm that Pyramid uses is explained in *The Traversal Algorithm*. Though it is rarely necessary, this default algorithm can be swapped out selectively for a different traversal pattern via configuration.

```
from pyramid.interfaces import ITraverser
from zope.interface import Interface
from myapp.traversal import Traverser
from myapp.traversal imp
```

In the example above, myapp.traversal.Traverser is assumed to be a class that implements the following interface:

1	class T	raverser(object):
2	def	<pre>init(self, root):</pre>
3		""" Accept the root object returned from the root factory """
4		
5	def	<pre>call(self, request):</pre>
6		""" Return a dictionary with (at least) the keys ''root'',
7		<pre>''context'', ''view_name'', ''subpath'', ''traversed'',</pre>
8		''virtual_root'', and ''virtual_root_path''. These values are
9		typically the result of a resource tree traversal. ''root''
10		is the physical root object, ''context'' will be a resource
11		object, ''view_name'' will be the view name used (a Unicode
12		name), ''subpath'' will be a sequence of Unicode names that
13		followed the view name but were not traversed, ''traversed''
14		will be a sequence of Unicode names that were traversed
15		(including the virtual root path, if any) ''virtual_root''
16		will be a resource object representing the virtual root (or the
17		physical root if traversal was not performed), and
18		''virtual_root_path'' will be a sequence representing the
19		virtual root path (a sequence of Unicode names) or None if
20		traversal was not performed.
21		
22		Extra keys for special purpose functionality can be added as
23		necessary.
24		
25		All values returned in the dictionary will be made available
26		as attributes of the ''request'' object.
27		"""

More than one traversal algorithm can be active at the same time. For instance, if your *root factory* returns more than one type of object conditionally, you could claim that an alternate traverser adapter is for only one particular class or interface. When the root factory returned an object that implemented that class or interface, a custom traverser would be used. Otherwise, the default traverser would be used. For example:

```
1 from pyramid.interfaces import ITraverser
```

```
2 from zope.interface import Interface
```

```
3 from myapp.traversal import Traverser
4 from myapp.resources import MyRoot
5 
6 config.registry.registerAdapter(Traverser, (MyRoot,), ITraverser)
```

If the above stanza was added to a Pyramid ___init___.py file's main function, Pyramid would use the myapp.traversal.Traverser only when the application *root factory* returned an instance of the myapp.resources.MyRoot object. Otherwise it would use the default Pyramid traverser to do traversal.

25.9 Changing How pyramid.url.resource_url Generates a URL

When you add a traverser as described in *Changing the Traverser*, it's often convenient to continue to use the pyramid.url.resource_url() API. However, since the way traversal is done will have been modified, the URLs it generates by default may be incorrect.

If you've added a traverser, you can change how resource_url() generates a URL for a specific type of resource by adding a registerAdapter call for pyramid.interfaces.IContextURL to your application:

In the above example, the myapp.traversal.URLGenerator class will be used to provide services to resource_url() any time the *context* passed to resource_url is of class myapp.resources.MyRoot. The second argument in the (MyRoot, Interface) tuple represents the type of interface that must be possessed by the *request* (in this case, any interface, represented by zope.interface.Interface).

The API that must be implemented by a class that provides IContextURL is as follows:

```
from zope.interface import Interface
1
2
  class IContextURL(Interface):
3
      """ An adapter which deals with URLs related to a context.
4
      .....
5
      def __init__(self, context, request):
6
           """ Accept the context and request """
7
8
      def virtual_root(self):
9
           """ Return the virtual root object related to a request and the
10
           current context"""
11
12
      def __call__(self):
13
           """ Return a URL that points to the context """
14
```

The default context URL generator is available for perusal as the class pyramid.traversal.TraversalContextURL in the traversal module of the *Pylons* GitHub Pyramid repository.

25.10 Changing How Pyramid Treats View Responses

It is possible to control how Pyramid treats the result of calling a view callable on a per-type basis by using a hook involving pyramid.config.Configurator.add_response_adapter().

This feature is new as of Pyramid 1.1.

Pyramid, in various places, adapts the result of calling a view callable to the IResponse interface to ensure that the object returned by the view callable is a "true" response object. The vast majority of time, the result of this adaptation is the result object itself, as view callables written by "civilians" who read the narrative documentation contained in this manual will always return something that implements the IResponse interface. Most typically, this will be an instance of the pyramid.response.Response class or a subclass. If a civilian returns a non-Response object from a view callable that isn't configured to use a *renderer*, he will typically expect the router to raise an error. However, you can hook Pyramid in such a way that users can return arbitrary values from a view callable by providing an adapter which converts the arbitrary return value into something that implements IResponse.

For example, if you'd like to allow view callables to return bare string objects (without requiring a a *renderer* to convert a string to a response object), you can register an adapter which converts the string to a Response:

```
from pyramid.response import Response
def string_response_adapter(s):
    response = Response(s)
    return response
    # config is an instance of pyramid.config.Configurator
    config.add_response_adapter(string_response_adapter, str)
```

Likewise, if you want to be able to return a simplified kind of response object from view callables, you can use the IResponse hook to register an adapter to the more complex IResponse interface:

```
from pyramid.response import Response
1
2
  class SimpleResponse(object):
3
      def __init__(self, body):
4
          self.body = body
5
6
7
  def simple_response_adapter(simple_response):
      response = Response(simple_response.body)
8
      return response
9
10
  # config is an instance of pyramid.config.Configurator
11
12
  config.add_response_adapter(simple_response_adapter, SimpleResponse)
13
```

If you want to implement your own Response object instead of using the pyramid.response.Response object in any capacity at all, you'll have to make sure the object implements every attribute and method outlined in pyramid.interfaces.IResponse and you'll have to ensure that it's marked up with zope.interface.implements (IResponse):

from pyramid.interfaces import IResponse from zope.interface import implements

class MyResponse(object): implements(IResponse) # ... an implementation of every method and attribute # documented in IResponse should follow ...

When an alternate response object implementation is returned by a view callable, if that object asserts that it implements IResponse (via zope.interface.implements(IResponse)), an adapter needn't be registered for the object; Pyramid will use it directly.

An IResponse adapter for webob.Response (as opposed to pyramid.response.Response) is registered by Pyramid by default at startup time, as by their nature, instances of this class (and instances of subclasses of the class) will natively provide IResponse. The adapter registered for webob.Response simply returns the response object.

25.11 Using a View Mapper

The default calling conventions for view callables are documented in the *Views* chapter. You can change the way users define view callables by employing a *view mapper*.

A view mapper is an object that accepts a set of keyword arguments and which returns a callable. The returned callable is called with the *view callable* object. The returned callable should itself return another callable which can be called with the "internal calling protocol" (context, request).

You can use a view mapper in a number of ways:

- by setting a ____view_mapper___ attribute (which is the view mapper object) on the view callable itself
- by passing the mapper object to pyramid.config.Configurator.add_view() (or its declarative/decorator equivalents) as the mapper argument.
- by registering a *default* view mapper.

Here's an example of a view mapper that emulates (somewhat) a Pylons "controller". The mapper is initialized with some keyword arguments. Its <u>call</u> method accepts the view object (which will be a class). It uses the attr keyword argument it is passed to determine which attribute should be used as an action method. The wrapper method it returns accepts (context, request) and returns the result of calling the action method with keyword arguments implied by the *matchdict* after popping the action out of it. This somewhat emulates the Pylons style of calling action methods with routing parameters pulled out of the route matching dict as keyword arguments.

```
# framework
1
2
  class PylonsControllerViewMapper(object):
3
      def __init__(self, **kw):
4
           self.kw = kw
5
6
      def __call__(self, view):
7
           attr = self.kw['attr']
8
           def wrapper(context, request):
9
               matchdict = request.matchdict.copy()
10
               matchdict.pop('action', None)
11
               inst = view()
12
               meth = getattr(inst, attr)
13
               return meth(**matchdict)
14
           return wrapper
15
16
  class BaseController(object):
17
      ___view_mapper___ = PylonsControllerViewMapper
18
```

A user might make use of these framework components like so:

```
# user application
1
2
  from pyramid.response import Response
3
  from pyramid.config import Configurator
4
  import pyramid handlers
  from paste.httpserver import serve
6
7
  class MyController(BaseController):
8
      def index(self, id):
9
          return Response(id)
10
11
12 if name == ' main ':
13
      config = Configurator()
      config.include(pyramid_handlers)
14
      config.add_handler('one', '/{id}', MyController, action='index')
15
      config.add_handler('two', '/{action}/{id}', MyController)
16
      serve(config.make_wsgi_app())
17
```

The pyramid.config.Configurator.set_view_mapper() method can be used to set a *de-fault* view mapper (overriding the superdefault view mapper used by Pyramid itself).

A *single* view registration can use a view mapper by passing the mapper as the mapper argument to add_view().

25.12 Registering Configuration Decorators

Decorators such as view_config don't change the behavior of the functions or classes they're decorating. Instead, when a *scan* is performed, a modified version of the function or class is registered with Pyramid.

You may wish to have your own decorators that offer such behaviour. This is possible by using the *Venusian* package in the same way that it is used by Pyramid.

By way of example, let's suppose you want to write a decorator that registers the function it wraps with a *Zope Component Architecture* "utility" within the *application registry* provided by Pyramid. The application registry and the utility inside the registry is likely only to be available once your application's configuration is at least partially completed. A normal decorator would fail as it would be executed before the configuration had even begun.

However, using Venusian, the decorator could be written as follows:

```
import venusian
1
  from mypackage.interfaces import IMyUtility
2
3
  class registerFunction(object):
4
5
      def __init__(self, path):
6
           self.path = path
7
8
      def register(self, scanner, name, wrapped):
9
           registry = scanner.config.registry
10
           registry.getUtility(IMyUtility).register(
11
               self.path, wrapped)
12
13
      def __call__(self, wrapped):
14
          venusian.attach(wrapped, self.register)
15
           return wrapped
16
```

This decorator could then be used to register functions throughout your code:

```
1 @registerFunction('/some/path')
2 def my_function():
3 do_stuff()
```

However, the utility would only be looked up when a *scan* was performed, enabling you to set up the utility in advance:

```
from paste.httpserver import serve
1
2 from pyramid.config import Configurator
  from mypackage.interfaces import IMyUtility
3
4
  class UtilityImplementation:
5
6
      implements(IMyUtility)
7
8
      def __init__(self):
9
         self.registrations = {}
10
11
      def register(self, path, callable_):
12
         self.registrations[path] = callable_
13
14
  if __name__ == '__main__':
15
      config = Configurator()
16
      config.registry.registerUtility(UtilityImplementation())
17
      config.scan()
18
```

```
app = config.make_wsgi_app()
serve(app, host='0.0.0.0')
```

For full details, please read the Venusian documentation.

25. USING HOOKS

CHAPTER

TWENTYSIX

ADVANCED CONFIGURATION

To support application extensibility, the Pyramid *Configurator*, by default, detects configuration conflicts and allows you to include configuration imperatively from other packages or modules. It also, by default, performs configuration in two separate phases. This allows you to ignore relative configuration statement ordering in some circumstances.

26.1 Conflict Detection

Here's a familiar example of one of the simplest Pyramid applications, configured imperatively:

```
1
  from paste.httpserver import serve
  from pyramid.config import Configurator
2
  from pyramid.response import Response
3
4
  def hello_world(request):
5
      return Response('Hello world!')
6
7
  if __name__ == '__main__':
8
      config = Configurator()
9
      config.add_view(hello_world)
10
      app = config.make_wsgi_app()
11
      serve(app, host='0.0.0.0')
12
```

When you start this application, all will be OK. However, what happens if we try to add another view to the configuration with the same set of *predicate* arguments as one we've already added?

```
from paste.httpserver import serve
2 from pyramid.config import Configurator
  from pyramid.response import Response
3
  def hello_world(request):
5
      return Response('Hello world!')
6
7
  def goodbye_world(request):
8
      return Response('Goodbye world!')
9
10
  if __name__ == '__main__':
11
      config = Configurator()
12
13
      config.add_view(hello_world, name='hello')
14
15
      # conflicting view configuration
16
      config.add_view(goodbye_world, name='hello')
17
18
      app = config.make_wsgi_app()
19
      serve(app, host='0.0.0.0')
20
```

The application now has two conflicting view configuration statements. When we try to start it again, it won't start. Instead, we'll receive a traceback that ends something like this:

```
Traceback (most recent call last):
1
    File "app.py", line 12, in <module>
2
      app = config.make_wsgi_app()
3
    File "pyramid/config.py", line 839, in make_wsgi_app
4
      self.commit()
5
    File "pyramid/pyramid/config.py", line 473, in commit
6
      self._ctx.execute_actions()
7
    File "zope/configuration/config.py", line 600, in execute_actions
8
      for action in resolveConflicts(self.actions):
9
    File "zope/configuration/config.py", line 1507, in resolveConflicts
10
      raise ConfigurationConflictError(conflicts)
11
  zope.configuration.config.ConfigurationConflictError:
12
          Conflicting configuration actions
13
    For: ('view', None, '', None, <InterfaceClass pyramid.interfaces.IView>,
14
          None, None, None, None, False, None, None, None)
15
   ('app.py', 14, '<module>', 'config.add_view(hello_world)')
16
   ('app.py', 17, '<module>', 'config.add_view(hello_world)')
17
```

This traceback is trying to tell us:

• We've got conflicting information for a set of view configuration statements (The For: line).

 There are two statements which conflict. shown beneath the For: line: config.add view(hello world. 'hello') line 14 on of app.py, and config.add view(goodbye world, 'hello') on line 17 of app.py.

These two configuration statements are in conflict because we've tried to tell the system that the set of *predicate* values for both view configurations are exactly the same. Both the hello_world and goodbye_world views are configured to respond under the same set of circumstances. This circumstance: the *view name* (represented by the name= predicate) is hello.

This presents an ambiguity that Pyramid cannot resolve. Rather than allowing the circumstance to go unreported, by default Pyramid raises a ConfigurationConflictError error and prevents the application from running.

Conflict detection happens for any kind of configuration: imperative configuration or configuration that results from the execution of a *scan*.

26.1.1 Manually Resolving Conflicts

There are a number of ways to manually resolve conflicts: the "right" way, by strategically using pyramid.config.Configurator.commit(), or by using an "autocommitting" configurator.

The Right Thing

The most correct way to resolve conflicts is to "do the needful": change your configuration code to not have conflicting configuration statements. The details of how this is done depends entirely on the configuration statements made by your application. Use the detail provided in the ConfigurationConflictError to track down the offending conflicts and modify your configuration code accordingly.

If you're getting a conflict while trying to extend an existing application, and that application has a function which performs configuration like this one:

```
1 def add_routes(config):
2 config.add_route(...)
```

Don't call this function directly with config as an argument. Instead, use pyramid.config.Configuration.include():

26. ADVANCED CONFIGURATION

config.include(add_routes)

Using include () instead of calling the function directly provides a modicum of automated conflict resolution, with the configuration statements you define in the calling code overriding those of the included function. See also *Automatic Conflict Resolution* and *Including Configuration from External Sources*.

Using config.commit()

You can manually commit a configuration by using the commit() method between configuration calls. For example, we prevent conflicts from occurring in the application we examined previously as the result of adding a commit. Here's the application that generates conflicts:

```
from paste.httpserver import serve
1
  from pyramid.config import Configurator
2
  from pyramid.response import Response
3
4
  def hello_world(request):
5
      return Response('Hello world!')
6
7
8
  def goodbye_world(request):
      return Response('Goodbye world!')
9
10
  if __name__ == '__main__':
11
      config = Configurator()
12
13
      config.add_view(hello_world, name='hello')
14
15
       # conflicting view configuration
16
      config.add_view(goodbye_world, name='hello')
17
18
      app = config.make_wsgi_app()
19
      serve(app, host='0.0.0.0')
20
```

We can prevent the two add_view calls from conflicting by issuing a call to commit () between them:

```
1 from paste.httpserver import serve
2 from pyramid.config import Configurator
3 from pyramid.response import Response
4 
5 def hello_world(request):
6 return Response('Hello world!')
```

```
7
  def goodbye_world(request):
8
      return Response('Goodbye world!')
9
10
  if __name__ == '__main__':
11
      config = Configurator()
12
13
      config.add_view(hello_world, name='hello')
14
15
      config.commit() # commit any pending configuration actions
16
17
       # no-longer-conflicting view configuration
18
      config.add_view(goodbye_world, name='hello')
19
20
21
      app = config.make_wsgi_app()
      serve(app, host='0.0.0.0')
22
```

In the above example we've issued a call to commit() between the two add_view calls. commit() will cause any pending configuration statements.

Calling commit() is safe at any time. It executes all pending configuration actions and leaves the configuration action list "clean".

Note that commit() has no effect when you're using an *autocommitting* configurator (see *Using An Autocommitting Configurator*).

Using An Autocommitting Configurator

You can also use a heavy hammer to circumvent conflict detection by using a configurator constructor parameter: autocommit=True. For example:

```
i from pyramid.config import Configurator
2
3
if __name__ == '__main__':
4 config = Configurator(autocommit=True)
```

When the autocommit parameter passed to the Configurator is True, conflict detection (and *Two-Phase Configuration*) is disabled. Configuration statements will be executed immediately, and succeeding statements will override preceding ones.

commit () has no effect when autocommit is True.

If you use a Configurator in code that performs unit testing, it's usually a good idea to use an autocommitting Configurator, because you are usually unconcerned about conflict detection or two-phase configuration in test code.

26.1.2 Automatic Conflict Resolution

If your code uses the include () method to include external configuration, some conflicts are automatically resolved. Configuration statements that are made as the result of an "include" will be overridden by configuration statements that happen within the caller of the "include" method.

Automatic conflict resolution supports this goal: if a user wants to reuse a Pyramid application, and they want to customize the configuration of this application without hacking its code "from outside", they can "include" a configuration function from the package and override only some of its configuration statements within the code that does the include. No conflicts will be generated by configuration statements within the code which does the including, even if configuration statements in the included code would conflict if it was moved "up" to the calling code.

26.1.3 Methods Which Provide Conflict Detection

These are the methods of the configurator which provide conflict detection:

```
add_view(), add_route(), add_renderer(), set_request_factory(),
set_renderer_globals_factory(), set_locale_negotiator() and
set_default_permission().
```

add_static_view() also indirectly provides conflict detection, because it's implemented in terms of the conflict-aware add_route and add_view methods.

26.2 Including Configuration from External Sources

Some application programmers will factor their configuration code in such a way that it is easy to reuse and override configuration statements. For example, such a developer might factor out a function used to add routes to his application:

```
1 def add_routes(config):
2 config.add_route(...)
```

Rather than calling this function directly with config as an argument. Instead, use pyramid.config.Configuration.include():

```
config.include(add_routes)
```

Using include rather than calling the function directly will allow *Automatic Conflict Resolution* to work.

include () can also accept a module as an argument:

```
import myapp
2
3 config.include(myapp)
```

For this to work properly, the myapp module must contain a callable with the special name includeme, which should perform configuration (like the add_routes callable we showed above as an example).

include () can also accept a *dotted Python name* to a function or a module.

26.3 Two-Phase Configuration

When a non-autocommitting *Configurator* is used to do configuration (the default), configuration execution happens in two phases. In the first phase, "eager" configuration actions (actions that must happen before all others, such as registering a renderer) are executed, and *discriminators* are computed for each of the actions that depend on the result of the eager actions. In the second phase, the discriminators of all actions are compared to do conflict detection.

Due to this, for configuration methods that have no internal ordering constraints, execution order of configuration method calls is not important. For example, the relative ordering of add_view() and add_renderer() is unimportant when a non-autocommitting configurator is used. This code snippet:

```
1 config.add_view('some.view', renderer='path_to_custom/renderer.rn')
2 config.add_renderer('.rn', SomeCustomRendererFactory)
```

Has the same result as:

```
1 config.add_renderer('.rn', SomeCustomRendererFactory)
2 config.add_view('some.view', renderer='path_to_custom/renderer.rn')
```

26. ADVANCED CONFIGURATION

Even though the view statement depends on the registration of a custom renderer, due to two-phase configuration, the order in which the configuration statements are issued is not important. add_view will be able to find the .rn renderer even if add_renderer is called after add_view.

The same is untrue when you use an *autocommitting* configurator (see *Using An Autocommitting Configurator*). When an autocommitting configurator is used, two-phase configuration is disabled, and configuration statements must be ordered in dependency order.

Some configuration methods, such as add_route() have internal ordering constraints: the routes they imply require relative ordering. Such ordering constraints are not absolved by two-phase configuration. Routes are still added in configuration execution order.

26.4 Adding Methods to the Configurator via add_directive

Framework extension writers can add arbitrary methods to a *Configurator* by using the pyramid.config.Configurator.add_directive() method of the configurator. This makes it possible to extend a Pyramid configurator in arbitrary ways, and allows it to perform application-specific tasks more succinctly.

The add_directive() method accepts two positional arguments: a method name and a callable object. The callable object is usually a function that takes the configurator instance as its first argument and accepts other arbitrary positional and keyword arguments. For example:

Once add_directive() is called, a user can then call the method by its given name as if it were a built-in method of the Configurator:

```
def mysubscriber(event):
    print event.request
    config.add_newrequest_subscriber(mysubscriber)
```

A call to add_directive() is often "hidden" within an includeme function within a "frameworky" package meant to be included as per *Including Configuration from External Sources* via include(). For example, if you put this code in a package named pyramid_subscriberhelpers:

The user of the add-on package pyramid_subscriberhelpers would then be able to install it and subsequently do:

```
def mysubscriber(event):
    print event.request

from pyramid.config import Configurator
config = Configurator()
config.include('pyramid_subscriberhelpers')
config.add_newrequest_subscriber(mysubscriber)
```

26. ADVANCED CONFIGURATION

CHAPTER

TWENTYSEVEN

EXTENDING AN EXISTING PYRAMID APPLICATION

If a Pyramid developer has obeyed certain constraints while building an application, a third party should be able to change the application's behavior without needing to modify its source code. The behavior of a Pyramid application that obeys certain constraints can be *overridden* or *extended* without modification.

We'll define some jargon here for the benefit of identifying the parties involved in such an effort.

Developer The original application developer.

Integrator Another developer who wishes to reuse the application written by the original application developer in an unanticipated context. He may also wish to modify the original application without changing the original application's source code.

27.1 The Difference Between "Extensible" and "Pluggable" Applications

Other web frameworks, such as *Django*, advertise that they allow developers to create "pluggable applications". They claim that if you create an application in a certain way, it will be integratable in a sensible, structured way into another arbitrarily-written application or project created by a third-party developer.

Pyramid, as a platform, does not claim to provide such a feature. The platform provides no guarantee that you can create an application and package it up such that an arbitrary integrator can use it as a subcomponent in a larger Pyramid application or project. Pyramid does not mandate the constraints necessary

for such a pattern to work satisfactorily. Because Pyramid is not very "opinionated", developers are able to use wildly different patterns and technologies to build an application. A given Pyramid application may happen to be reusable by a particular third party integrator, because the integrator and the original developer may share similar base technology choices (such as the use of a particular relational database or ORM). But the same application may not be reusable by a different developer, because he has made different technology choices which are incompatible with the original developer's.

As a result, the concept of a "pluggable application" is left to layers built above Pyramid, such as a "CMS" layer or "application server" layer. Such layers are apt to provide the necessary "opinions" (such as mandating a storage layer, a templating system, and a structured, well-documented pattern of registering that certain URLs map to certain bits of code) which makes the concept of a "pluggable application" possible. "Pluggable applications", thus, should not plug in to Pyramid itself but should instead plug into a system written atop Pyramid.

Although it does not provide for "pluggable applications", Pyramid *does* provide a rich set of mechanisms which allows for the extension of a single existing application. Such features can be used by frameworks built using Pyramid as a base. All Pyramid applications may not be *pluggable*, but all Pyramid applications are *extensible*.

27.2 Rules for Building An Extensible Application

There is only one rule you need to obey if you want to build a maximally extensible Pyramid application: as a developer, you should factor any overrideable *imperative configuration* you've created into functions which can be used via pyramid.config.Configurator.include() rather than inlined as calls to methods of a *Configurator* within the main function in your application's __init__.py. For example, rather than:

```
from pyramid.config import Configurator

if __name__ == '__main__':
    config = Configurator()
    config.add_view('myapp.views.view1', name='view1')
    config.add_view('myapp.views.view2', name='view2')
```

You should do move the calls to add_view outside of the (non-reusable) if __name__ == '__main__' block, and into a reusable function:

```
1 from pyramid.config import Configurator
2
3 if __name__ == '__main__':
```

```
4 config = Configurator()
5 config.include(add_views)
6
7 def add_views(config):
8 config.add_view('myapp.views.view1', name='view1')
9 config.add_view('myapp.views.view2', name='view2')
```

Doing this allows an integrator to maximally reuse the configuration statements that relate to your application by allowing him to selectively include or disinclude the configuration functions you've created from an "override package".

Alternately, you can use *ZCML* for the purpose of making configuration extensible and overrideable. *ZCML* declarations that belong to an application can be overridden and extended by integrators as necessary in a similar fashion. If you use only *ZCML* to configure your application, it will automatically be maximally extensible without any manual effort. See *pyramid_zcml* for information about using ZCML.

27.2.1 Fundamental Plugpoints

The fundamental "plug points" of an application developed using Pyramid are *routes*, *views*, and *assets*. Routes are declarations made using the pyramid.config.Configurator.add_route() method. Views are declarations made using the pyramid.config.Configurator.add_view() method. Assets are files that are accessed by Pyramid using the *pkg_resources* API such as static files and templates via a *asset specification*. Other directives and configurator methods also deal in routes, views, and assets. For example, the add_handler directive of the pyramid_handlers package adds a single route, and some number of views.

27.3 Extending an Existing Application

The steps for extending an existing application depend largely on whether the application does or does not use configuration decorators and/or imperative code.

27.3.1 If The Application Has Configuration Decorations

You've inherited a Pyramid application which you'd like to extend or override that uses pyramid.view.view_config decorators or other *configuration decoration* decorators.

If you just want to *extend* the application, you can run a *scan* against the application's package, then add additional configuration that registers more views or routes.

```
if __name__ == '__main__':
    config.scan('someotherpackage')
    config.add_view('mypackage.views.myview', name='myview')
```

If you want to *override* configuration in the application, you *may* need to run pyramid.config.Configurator.commit() after performing the scan of the original package, then add additional configuration that registers more views or routes which performs overrides.

if __name__ == '__main__':
 config.scan('someotherpackage')
 config.commit()
 config.add_view('mypackage.views.myview', name='myview')

Once this is done, you should be able to extend or override the application like any other (see *Extending the Application*).

You can alternately just prevent a *scan* from happening (by omitting any call to the pyramid.config.Configurator.scan() method). This will cause the decorators attached to objects in the target application to do nothing. At this point, you will need to convert all the configuration done in decorators into equivalent imperative configuration or ZCML and add that configuration or ZCML to a separate Python package as described in *Extending the Application*.

27.3.2 Extending the Application

To extend or override the behavior of an existing application, you will need to create a new package which includes the configuration of the old package, and you'll perhaps need to create implementations of the types of things you'd like to override (such as views), which are referred to within the original package.

The general pattern for extending an existing application looks something like this:

- Create a new Python package. The easiest way to do this is to create a new Pyramid application using the scaffold mechanism. See *Creating the Project* for more information.
- In the new package, create Python files containing views and other overridden elements, such as templates and static assets as necessary.
- Install the new package into the same Python environment as the original application (e.g. python setup.py develop or python setup.py install).

- Change the main function in the new package's __init__.py to include the original Pyramid application's configuration functions via pyramid.config.Configurator.include() statements or a *scan*.
- Wire the new views and assets created in the new package up using imperative registrations within the main function of the __init__.py file of the new application. These wiring should happen *after* including the configuration functions of the old application. These registrations will extend or override any registrations performed by the original application. See *Overriding Views*, *Overriding Routes* and *Overriding Assets*.

27.3.3 Overriding Views

The *view configuration* declarations you make which *override* application behavior will usually have the same *view predicate* attributes as the original you wish to override. These <view> declarations will point at "new" view code, in the override package you've created. The new view code itself will usually be cut-n-paste copies of view callables from the original application with slight tweaks.

For example, if the original application has the following configure_views configuration method:

You can override the first view configuration statement made by configure_views within the override package, after loading the original configuration function:

```
from pyramid.config import Configurator
from originalapp import configure_views
if __name == '__main__':
    config = Configurator()
    config.include(configure_views)
    config.add_view('theoverrideapp.views.theview', name='theview')
```

In this case, the theoriginalapp.views.theview view will never be executed. Instead, a new view, theoverrideapp.views.theview will be executed instead, when request circumstances dictate.

A similar pattern can be used to *extend* the application with add_view declarations. Just register a new view against some other set of predicates to make sure the URLs it implies are available on some other page rendering.

27.3.4 Overriding Routes

Route setup is currently typically performed in a sequence of ordered calls to add_route(). Because these calls are ordered relative to each other, and because this ordering is typically important, you should retain their relative ordering when performing an override. Typically, this means *copying* all the add_route statements into the override package's file and changing them as necessary. Then disinclude any add_route statements from the original application.

27.3.5 Overriding Assets

Assets are files on the filesystem that are accessible within a Python *package*. An entire chapter is devoted to assets: *Static Assets*. Within this chapter is a section named *Overriding Assets*. This section of that chapter describes in detail how to override package assets with other assets by using the pyramid.config.Configurator.override_asset() method. Add such override_asset calls to your override package's __init__.py to perform overrides.

CHAPTER

TWENTYEIGHT

STARTUP

When you cause a Pyramid application to start up in a console window, you'll see something much like this show up on the console:

```
$ paster serve myproject/MyProject.ini
Starting server in PID 16601.
serving on 0.0.0.0:6543 view at http://127.0.0.1:6543
```

This chapter explains what happens between the time you press the "Return" key on your keyboard after typing paster serve myproject/MyProject.ini and the time the line serving on 0.0.0.0:6543 ... is output to your console.

28.1 The Startup Process

The easiest and best-documented way to start and serve a Pyramid application is to use the paster serve command against a *PasteDeploy* .ini file. This uses the .ini file to infer settings and starts a server listening on a port. For the purposes of this discussion, we'll assume that you are using this command to run your Pyramid application.

Here's a high-level time-ordered overview of what happens when you press return after running paster serve development.ini.

1. The *PasteDeploy* paster command is invoked under your shell with the arguments serve and development.ini. As a result, the *PasteDeploy* framework recognizes that it is meant to begin to run and serve an application using the information contained within the development.ini file.

- 2. The PasteDeploy framework finds a section named either [app:main], [pipeline:main], or [composite:main] in the .ini file. This section represents the configuration of a WSGI application that will be served. If you're using a simple application (e.g. [app:main]), the application *entry point* or *dotted Python name* will be named on the use= line within the section's configuration. If, instead of a simple application, you're using a WSGI *pipeline* (e.g. a [pipeline:main] section), the application named on the "last" element will refer to your Pyramid application. If instead of a simple application or a pipeline, you're using a Paste "composite" (e.g. [composite:main]), refer to the documentation for that particular composite to understand how to make it refer to your Pyramid application.
- 3. The PasteDeploy framework finds all logging related configuration in the .ini file and uses it to configure the Python standard library logging system for this application.
- 4. The application's *constructor* (named by the entry point reference or dotted Python name on the use= line of the section representing your Pyramid application) is passed the key/value parameters mentioned within the section in which it's defined. The constructor is meant to return a *router* instance, which is a *WSGI* application.

For Pyramid applications, the constructor will be a function named main in the __init__.py file within the *package* in which your application lives. If this function succeeds, it will return a Pyramid *router* instance. Here's the contents of an example __init__.py module:

```
from pyramid.config import Configurator
1
  from myproject.resources import Root
2
3
  def main(global_config, **settings):
4
      """ This function returns a Pyramid WSGI application.
5
      .....
6
      config = Configurator(root_factory=Root, settings=settings)
7
      config.add_view('myproject.views.my_view',
8
                       context='myproject.resources.Root',
9
                       renderer='myproject:templates/mytemplate.pt')
10
      config.add_static_view('static', 'myproject:static')
11
      return config.make_wsgi_app()
12
```

Note that the constructor function accepts a global_config argument, which is a dictionary of key/value pairs mentioned in the [DEFAULT] section of an .ini file. It also accepts a **settings argument, which collects another set of arbitrary key/value pairs. The arbitrary key/value pairs received by this function in **settings will be composed of all the key/value pairs that are present in the [app:MyProject] section (except for the use= setting) when this function is called by the *PasteDeploy* framework when you run paster serve.

Our generated development.ini file looks like so:

```
[app:MyProject]
use = egg:MyProject
reload_templates = true
debug_authorization = false
debug_notfound = false
debug_routematch = false
debug_templates = true
default_locale_name = en
[pipeline:main]
pipeline =
    egg:WebError#evalerror
    MyProject
[server:main]
use = egg:Paste#http
host = 0.0.0.0
port = 6543
# Begin logging configuration
[loggers]
keys = root, myproject
[handlers]
keys = console
[formatters]
keys = generic
[logger_root]
level = INFO
handlers = console
[logger_myproject]
level = DEBUG
handlers =
qualname = myproject
[handler_console]
class = StreamHandler
args = (sys.stderr,)
level = NOTSET
formatter = generic
[formatter_generic]
```

```
format = %(asctime)s %(levelname)-5.5s [%(name)s] %(message)s
# End logging configuration
```

In this case, the myproject.__init__:main function referred to by the entry point URI egg:MyProject (see *development.ini* for more information about entry point URIs, and how they relate to callables), will receive the key/value pairs {'reload_templates':'true', 'debug_authorization':'false', 'debug_notfound':'false', 'debug_routematch':'false', 'debug_templates':'true', 'default_locale_name':'en'}.

5. The main function first constructs a Configurator instance, passing a root resource factory (constructor) to it as its root_factory argument, and settings dictionary captured via the **settings kwarg as its settings argument.

The root resource factory is invoked on every request to retrieve the application's root resource. It is not called during startup, only when a request is handled.

The settings dictionary contains all the options in the [app:MyProject] section of our .ini file except the use option (which is internal to Paste) such as reload_templates, debug_authorization, etc.

- 6. The main function then calls various methods on the an instance of the class Configurator method. The intent of calling these methods is to populate an *application registry*, which represents the Pyramid configuration related to the application.
- 7. The make_wsgi_app() method is called. The result is a *router* instance. The router is associated with the *application registry* implied by the configurator previously populated by other methods run against the Configurator. The router is a WSGI application.
- 8. A ApplicationCreated event is emitted (see *Using Events* for more information about events).
- 9. Assuming there were no errors, the main function in myproject returns the router instance created by make_wsgi_app back to PasteDeploy. As far as PasteDeploy is concerned, it is "just another WSGI application".
- 10. PasteDeploy starts the WSGI server defined within the [server:main] section. In our case, this is the Paste#http server (use = egg:Paste#http), and it will listen on all interfaces (host = 0.0.0.0), on port number 6543 (port = 6543). The server code itself is what prints serving on 0.0.0.0:6543 view at http://127.0.0.1:6543. The server serves the application, and the application is running, waiting to receive requests.

28.2 Deployment Settings

Note that an augmented version of the values passed as **settings to the Configurator constructor will be available in Pyramid *view callable* code as request.registry.settings. You can create objects you wish to access later from view code, and put them into the dictionary you pass to the configurator as settings. They will then be present in the request.registry.settings dictionary at application runtime.

CHAPTER

TWENTYNINE

THREAD LOCALS

A *thread local* variable is a variable that appears to be a "global" variable to an application which uses it. However, unlike a true global variable, one thread or process serving the application may receive a different value than another thread or process when that variable is "thread local".

When a request is processed, Pyramid makes two *thread local* variables available to the application: a "registry" and a "request".

29.1 Why and How Pyramid Uses Thread Local Variables

How are thread locals beneficial to Pyramid and application developers who use Pyramid? Well, usually they're decidedly **not**. Using a global or a thread local variable in any application usually makes it a lot harder to understand for a casual reader. Use of a thread local or a global is usually just a way to avoid passing some value around between functions, which is itself usually a very bad idea, at least if code readability counts as an important concern.

For historical reasons, however, thread local variables are indeed consulted by various Pyramid API functions. For example, the implementation of the pyramid.security function named authenticated_userid() retrieves the thread local *application registry* as a matter of course to find an *authentication policy*. It uses the pyramid.threadlocal.get_current_registry() function to retrieve the application registry, from which it looks up the authentication policy; it then uses the authenticated user id. This is how Pyramid allows arbitrary authentication policies to be "plugged in".

When they need to do so, Pyramid internals use two API functions to retrieve the *request* and *application registry*: get_current_request() and get_current_registry(). The former returns the

29. THREAD LOCALS

"current" request; the latter returns the "current" registry. Both get_current_* functions retrieve an object from a thread-local data structure. These API functions are documented in *pyramid.threadlocal*.

These values are thread locals rather than true globals because one Python process may be handling multiple simultaneous requests or even multiple Pyramid applications. If they were true globals, Pyramid could not handle multiple simultaneous requests or allow more than one Pyramid application instance to exist in a single Python process.

Because one Pyramid application is permitted to call *another* Pyramid application from its own *view* code (perhaps as a *WSGI* app with help from the pyramid.wsgi.wsgiapp2() decorator), these variables are managed in a *stack* during normal system operations. The stack instance itself is a threading.local.

During normal operations, the thread locals stack is managed by a *Router* object. At the beginning of a request, the Router pushes the application's registry and the request on to the stack. At the end of a request, the stack is popped. The topmost request and registry on the stack are considered "current". Therefore, when the system is operating normally, the very definition of "current" is defined entirely by the behavior of a pyramid *Router*.

However, during unit testing, no Router code is ever invoked, and the definition of "current" is defined by the boundary between calls to the pyramid.config.Configurator.begin() and pyramid.config.Configurator.end() methods (or between calls to the pyramid.testing.setUp() and pyramid.testing.tearDown() functions). These functions push and pop the threadlocal stack when the system is under test. See *Test Set Up and Tear Down* for the definitions of these functions.

Scripts which use Pyramid machinery but never actually start a WSGI server or receive requests via HTTP such as scripts which use the pyramid.scripting API will never cause any Router code to be executed. However, the pyramid.scripting APIs also push some values on to the thread locals stack as a matter of course. Such scripts should expect the get_current_request() function to always return None, and should expect the get_current_registry() function to return exactly the same *application registry* for every request.

29.2 Why You Shouldn't Abuse Thread Locals

You probably should almost never use the get_current_request() or get_current_registry() functions, except perhaps in tests. In particular, it's almost always a mistake to use get_current_request or get_current_registry in application code because its usage makes it possible to write code that can be neither easily tested nor scripted. Inappropriate usage is defined as follows:

- get_current_request should never be called within the body of a *view callable*, or within code called by a view callable. View callables already have access to the request (it's passed in to each as request).
- get_current_request should never be called in *resource* code. If a resource needs access to the request, it should be passed the request by a *view callable*.
- get_current_request function should never be called because it's "easier" or "more elegant" to think about calling it than to pass a request through a series of function calls when creating some API design. Your application should instead almost certainly pass data derived from the request around rather than relying on being able to call this function to obtain the request in places that actually have no business knowing about it. Parameters are *meant* to be passed around as function arguments, this is why they exist. Don't try to "save typing" or create "nicer APIs" by using this function in the place where a request is required; this will only lead to sadness later.
- Neither get_current_request nor get_current_registry should ever be called within application-specific forks of third-party library code. The library you've forked almost certainly has nothing to do with Pyramid, and making it dependent on Pyramid (rather than making your pyramid application depend upon it) means you're forming a dependency in the wrong direction.

Use of the get_current_request () function in application code *is* still useful in very limited circumstances. As a rule of thumb, usage of get_current_request is useful within code which is meant to eventually be removed. For instance, you may find yourself wanting to deprecate some API that expects to be passed a request object in favor of one that does not expect to be passed a request object. But you need to keep implementations of the old API working for some period of time while you deprecate the older API. So you write a "facade" implementation of the new API which calls into the code which implements the older API. Since the new API does not require the request, your facade implementation. After some period of time, the older implementation code is disused and the hack that uses get_current_request is removed. This would be an appropriate place to use the get_current_request.

Use of the get_current_registry() function should be limited to testing scenarios. The registry made current by use of the pyramid.config.Configurator.begin() method during a test (or via pyramid.testing.setUp()) when you do not pass one in is available to you via this API.

CHAPTER

THIRTY

USING THE ZOPE COMPONENT ARCHITECTURE IN PYRAMID

Under the hood, Pyramid uses a *Zope Component Architecture* component registry as its *application registry*. The Zope Component Architecture is referred to colloquially as the "ZCA."

The zope.component API used to access data in a traditional Zope application can be opaque. For example, here is a typical "unnamed utility" lookup using the zope.component.getUtility() global API as it might appear in a traditional Zope application:

```
1 from pyramid.interfaces import ISettings
2 from zope.component import getUtility
3 settings = getUtility(ISettings)
```

After this code runs, settings will be a Python dictionary. But it's unlikely that any "civilian" will be able to figure this out just by reading the code casually. When the <code>zope.component.getUtility</code> API is used by a developer, the conceptual load on a casual reader of code is high.

While the ZCA is an excellent tool with which to build a *framework* such as Pyramid, it is not always the best tool with which to build an *application* due to the opacity of the zope.component APIs. Accordingly, Pyramid tends to hide the presence of the ZCA from application developers. You needn't understand the ZCA to create a Pyramid application; its use is effectively only a framework implementation detail.

However, developers who are already used to writing *Zope* applications often still wish to use the ZCA while building a Pyramid application; pyramid makes this possible.

30.1 Using the ZCA Global API in a Pyramid Application

Zope uses a single ZCA registry – the "global" ZCA registry – for all Zope applications that run in the same Python process, effectively making it impossible to run more than one Zope application in a single process.

However, for ease of deployment, it's often useful to be able to run more than a single application per process. For example, use of a *Paste* "composite" allows you to run separate individual WSGI applications in the same process, each answering requests for some URL prefix. This makes it possible to run, for example, a TurboGears application at /turbogears and a Pyramid application at /pyramid, both served up using the same *WSGI* server within a single Python process.

Most production Zope applications are relatively large, making it impractical due to memory constraints to run more than one Zope application per Python process. However, a Pyramid application may be very small and consume very little memory, so it's a reasonable goal to be able to run more than one Pyramid application per process.

In order to make it possible to run more than one Pyramid application in a single process, Pyramid defaults to using a separate ZCA registry *per application*.

While this services a reasonable goal, it causes some issues when trying to use patterns which you might use to build a typical *Zope* application to build a Pyramid application. Without special help, ZCA "global" APIs such as <code>zope.component.getUtility</code> and <code>zope.component.getSiteManager</code> will use the ZCA "global" registry. Therefore, these APIs will appear to fail when used in a Pyramid application, because they'll be consulting the ZCA global registry rather than the component registry associated with your Pyramid application.

There are three ways to fix this: by disusing the ZCA global API entirely, by using pyramid.config.Configurator.hook_zca() or by passing the ZCA global registry to the *Configurator* constructor at startup time. We'll describe all three methods in this section.

30.1.1 Disusing the Global ZCA API

ZCA "global" API functions such as zope.component.getSiteManager, zope.component.getUtility, zope.component.getAdapter, and zope.component.getMultiAdapter aren't strictly necessary. Every component registry has a method API that offers the same functionality; it can be used instead. For example, presuming the registry value below is a Zope Component Architecture component registry, the following bit of code is equivalent to zope.component.getUtility(IFoo):

```
registry.getUtility(IFoo)
```

The full method API is documented in the zope.component package, but it largely mirrors the "global" API almost exactly.

If you are willing to disuse the "global" ZCA APIs and use the method interface of a registry instead, you need only know how to obtain the Pyramid component registry.

There are two ways of doing so:

- use the pyramid.threadlocal.get_current_registry() function within Pyramid view or resource code. This will always return the "current" Pyramid application registry.
- use the attribute of the *request* object named registry in your Pyramid view code, eg. request.registry. This is the ZCA component registry related to the running Pyramid application.

See Thread Locals for more information about pyramid.threadlocal.get_current_registry().

30.1.2 Enabling the ZCA Global API by Using hook_zca

Consider the following bit of idiomatic Pyramid startup code:

```
from zope.component import getGlobalSiteManager
from pyramid.config import Configurator
def app(global_settings, **settings):
    config = Configurator(settings=settings)
    config.include('some.other.package')
    return config.make_wsgi_app()
```

When the app function above is run, a *Configurator* is constructed. When the configurator is created, it creates a *new application registry* (a ZCA component registry). A new registry is constructed whenever the registry argument is omitted when a *Configurator* constructor is called, or when a registry argument with a value of None is passed to a *Configurator* constructor.

During a request, the application registry created by the Configurator is "made current". This means calls to get_current_registry () in the thread handling the request will return the component registry associated with the application.

30. USING THE ZOPE COMPONENT ARCHITECTURE IN PYRAMID

As a result, application developers can use get_current_registry to get the registry and thus get access to utilities and such, as per *Disusing the Global ZCA API*. But they still cannot use the global ZCA API. Without special treatment, the ZCA global APIs will always return the global ZCA registry (the one in zope.component.globalregistry.base).

To "fix" this and make the ZCA global APIs use the "current" Pyramid registry, you need to call hook_zca() within your setup code. For example:

```
from zope.component import getGlobalSiteManager
from pyramid.config import Configurator
def app(global_settings, **settings):
    config = Configurator(settings=settings)
    config.hook_zca()
    config.include('some.other.application')
    return config.make_wsgi_app()
```

We've added a line to our original startup code, line number 6, which calls config.hook_zca(). The effect of this line under the hood is that an analogue of the following code is executed:

```
1 from zope.component import getSiteManager
2 from pyramid.threadlocal import get_current_registry
3 getSiteManager.sethook(get_current_registry)
```

This causes the ZCA global API to start using the Pyramid application registry in threads which are running a Pyramid request.

Calling hook_zca is usually sufficient to "fix" the problem of being able to use the global ZCA API within a Pyramid application. However, it also means that a Zope application that is running in the same process may start using the Pyramid global registry instead of the Zope global registry, effectively inverting the original problem. In such a case, follow the steps in the next section, *Enabling the ZCA Global API by Using The ZCA Global Registry*.

30.1.3 Enabling the ZCA Global API by Using The ZCA Global Registry

You can tell your Pyramid application to use the ZCA global registry at startup time instead of constructing a new one:

```
from zope.component import getGlobalSiteManager
  from pyramid.config import Configurator
2
3
  def app(global_settings, **settings):
4
      globalreg = getGlobalSiteManager()
5
      config = Configurator(registry=globalreg)
6
      config.setup_registry(settings=settings)
7
      config.hook_zca()
8
      config.include('some.other.application')
9
      return config.make_wsgi_app()
10
```

Lines 5, 6, and 7 above are the interesting ones. Line 5 retrieves the global ZCA component registry. Line 6 creates a *Configurator*, passing the global ZCA registry into its constructor as the registry argument. Line 7 "sets up" the global registry with Pyramid-specific registrations; this is code that is normally executed when a registry is constructed rather than created, but we must call it "by hand" when we pass an explicit registry.

At this point, Pyramid will use the ZCA global registry rather than creating a new application-specific registry; since by default the ZCA global API will use this registry, things will work as you might expect a Zope app to when you use the global ZCA API.

30. USING THE ZOPE COMPONENT ARCHITECTURE IN PYRAMID

Part II

Tutorials

CHAPTER

THIRTYONE

ZODB + TRAVERSAL WIKI TUTORIAL

This tutorial introduces a *traversal* -based Pyramid application to a developer familiar with Python. It will be most familiar to developers with previous *Zope* experience. When we're done with the tutorial, the developer will have created a basic Wiki application with authentication.

For cut and paste purposes, the source code for all stages of this tutorial can be browsed at http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki/src/.

31.1 Background

This version of the Pyramid wiki tutorial presents a Pyramid application that uses technologies which will be familiar to someone with *Zope* experience. It uses *ZODB* as a persistence mechanism and *traversal* to map URLs to code. It can also be followed by people without any prior Python web framework experience.

To code along with this tutorial, the developer will need a UNIX machine with development tools (Mac OS X with XCode, any Linux or BSD variant, etc) *or* a Windows system of any kind.

This tutorial targets Pyramid version 1.0.

Have fun!

31.2 Installation

For the most part, the installation process for this tutorial duplicates the steps described in *Installing Pyramid* and *Creating a Pyramid Project*, however it also explains how to install additional libraries for tutorial purposes.

31.2.1 Preparation

Please take the following steps to prepare for the tutorial. The steps to prepare for the tutorial are slightly different depending on whether you're using UNIX or Windows.

Preparation, UNIX

- 1. If you don't already have a Python 2.6 interpreter installed on your system, obtain, install, or find Python 2.6 for your system.
- 2. Make sure the Python development headers are installed on your system. If you've installed Python from source, these will already be installed. If you're using a system Python, you may have to install a python-dev package (e.g. apt-get python-dev). The headers are not required for Pyramid itself, just for dependencies of the tutorial.
- 3. Install the latest *setuptools* into the Python you obtained/installed/found in the step above: download ez_setup.py and run it using the python interpreter of your Python 2.6 installation:

\$ /path/to/my/Python-2.6/bin/python ez_setup.py

4. Use that Python's *bin/easy_install* to install *virtualenv*:

\$ /path/to/my/Python-2.6/bin/easy_install virtualenv

5. Use that Python's virtualenv to make a workspace:

6. Switch to the pyramidtut directory:

\$ cd pyramidtut

- 7. (Optional) Consider using source bin/activate to make your shell environment wired to use the virtualenv.
- 8. Use easy_install to get Pyramid and its direct dependencies installed:

```
$ bin/easy_install pyramid
```

9. Use easy_install to install docutils, repoze.tm2, repoze.zodbconn, nose and coverage:

Preparation, Windows

- 1. Install, or find Python 2.6 for your system.
- 2. Install the latest *setuptools* into the Python you obtained/installed/found in the step above: down-load ez_setup.py and run it using the python interpreter of your Python 2.6 installation using a command prompt:

c:\> c:\Python26\python ez_setup.py

3. Use that Python's *bin/easy_install* to install *virtualenv*:

c:\> c:\Python26\Scripts\easy_install virtualenv

4. Use that Python's virtualenv to make a workspace:

c:\> c:\Python26\Scripts\virtualenv --no-site-packages pyramidtut

5. Switch to the pyramidtut directory:

c:\> cd pyramidtut

- 6. (Optional) Consider using bin\activate.bat to make your shell environment wired to use the virtualenv.
- 7. Use easy_install to get Pyramid and its direct dependencies installed:

```
c:\pyramidtut> Scripts\easy_install pyramid
```

 Use easy_install to install docutils, repoze.tm2, repoze.zodbconn, nose and coverage:

```
c:\pyramidtut> Scripts\easy_install docutils repoze.tm2 ^
    repoze.zodbconn nose coverage
```

31.2.2 Making a Project

Your next step is to create a project. Pyramid supplies a variety of scaffolds to generate sample projects. For this tutorial, we will use the *ZODB* -oriented scaffold named pyramid_zodb.

The below instructions assume your current working directory is the "virtualenv" named "pyramidtut".

On UNIX:

```
$ bin/paster create -t pyramid_zodb tutorial
```

On Windows:

```
c:\pyramidtut> Scripts\paster create -t pyramid_zodb tutorial
```

U If you are using Windows, the pyramid_zodb Paster scaffold doesn't currently deal gracefully with installation into a location that contains spaces in the path. If you experience startup problems, try putting both the virtualenv and the project into directories that do not contain spaces in their paths.

31.2.3 Installing the Project in "Development Mode"

In order to do development on the project easily, you must "register" the project as a development egg in your workspace using the setup.py develop command. In order to do so, cd to the "tutorial" directory you created in *Making a Project*, and run the "setup.py develop" command using virtualenv Python interpreter.

On UNIX:

```
$ cd tutorial
$ ../bin/python setup.py develop
```

On Windows:

```
C:\pyramidtut> cd tutorial
C:\pyramidtut\tutorial> ..\Scripts\python setup.py develop
```

31.2.4 Running the Tests

After you've installed the project in development mode, you may run the tests for the project.

On UNIX:

```
$ ../bin/python setup.py test -q
```

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\python setup.py test -q

31.2.5 Starting the Application

Start the application.

On UNIX:

\$../bin/paster serve development.ini --reload

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\paster serve development.ini --reload

31.2.6 Exposing Test Coverage Information

You can run the nosetests command to see test coverage information. This runs the tests in the same way that setup.py test does but provides additional "coverage" information, exposing which lines of your project are "covered" (or not covered) by the tests.

On UNIX:

\$../bin/nosetests --cover-package=tutorial --cover-erase --with-coverage

On Windows:

Looks like the code in the pyramid_zodb scaffold for ZODB projects is missing some test coverage, particularly in the file named models.py.

31.2.7 Visit the Application in a Browser

In a browser, visit http://localhost:6543/. You will see the generated application's default page.

31.2.8 Decisions the pyramid_zodb Scaffold Has Made For You

Creating a project using the pyramid_zodb scaffold makes the following assumptions:

- you are willing to use ZODB as persistent storage
- you are willing to use *traversal* to map URLs to code.
- you want to use imperative code plus a scan to perform configuration.

Pyramid supports any persistent storage mechanism (e.g. a SQL database or filesystem files, etc). Pyramid also supports an additional mechanism to map URLs to code (*URL dispatch*). However, for the purposes of this tutorial, we'll only be using traversal and ZODB.

31.3 Basic Layout

The starter files generated by the pyramid_zodb scaffold are basic, but they provide a good orientation for the high-level patterns common to most *traversal* -based Pyramid (and *ZODB* based) projects.

The source code for this tutorial stage can be browsed via http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki/src/basiclayout/.

31.3.1 App Startup with __init__.py

A directory on disk can be turned into a Python *package* by containing an __init__.py file. Even if empty, this marks a directory as a Python package. Our application uses __init__.py as both a package marker, as well as to contain application configuration code.

When you run the application using the paster command using the development.ini generated config file, the application configuration points at a Setuptools *entry point* described as egg:tutorial. In our application, because the application's setup.py file says so, this entry point happens to be the main function within the file named _____init___.py:

```
1 from pyramid.config import Configurator
<sup>2</sup> from repoze.zodbconn.finder import PersistentApplicationFinder
  from tutorial.models import appmaker
3
4
  def main(global_config, **settings):
5
      """ This function returns a Pyramid WSGI application.
6
      .....
7
      zodb_uri = settings.get('zodb_uri', False)
8
      if zodb_uri is False:
9
          raise ValueError ("No 'zodb_uri' in application configuration.")
10
11
12
      finder = PersistentApplicationFinder(zodb_uri, appmaker)
13
      def get root(request):
          return finder(request.environ)
14
      config = Configurator(root_factory=get_root, settings=settings)
15
      config.add_static_view('static', 'tutorial:static')
16
      config.scan('tutorial')
17
      return config.make_wsgi_app()
18
```

- 1. Lines 1-3. Perform some dependency imports.
- Line 8. Get the ZODB configuration from the development.ini file's [app:main] section represented by the settings dictionary passed to our app function. This will be a URI (something like file:///path/to/Data.fs).

- 3. *Line 12*. We create a "finder" object using the PersistentApplicationFinder helper class, passing it the ZODB URI and the "appmaker" we've imported from models.py.
- 4. Lines 13 14. We create a root factory which uses the finder to return a ZODB root object.
- 5. *Line 15.* We construct a *Configurator* with a *root factory* and the settings keywords parsed by PasteDeploy. The root factory is named get_root.
- 6. *Line 16.* Register a 'static view' which answers requests which start with with URL path /static using the pyramid.config.Configurator.add_static_view method(). This statement registers a view that will serve up static assets, such as CSS and image files, for us, in this case, at http://localhost:6543/static/ and below. The first argument is the "name" static, which indicates that the URL path prefix of the view will be /static. the The second argument of this tag is the "path", which is an *asset specification*, so it finds the resources it should serve within the static directory inside the tutorial package.
- 7. *Line 17.* Perform a *scan.* A scan will find *configuration decoration*, such as view configuration decorators (e.g. @view_config) in the source code of the tutorial package and will take actions based on these decorators. The argument to scan() is the package name to scan, which is tutorial.
- 8. *Line 18.* Use the pyramid.config.Configurator.make_wsgi_app() method to return a *WSGI* application.

31.3.2 Resources and Models with models.py

Pyramid uses the word *resource* to describe objects arranged hierarchically in a *resource tree*. This tree is consulted by *traversal* to map URLs to code. In this application, the resource tree represents the site structure, but it *also* represents the *domain model* of the application, because each resource is a node stored persistently in a *ZODB* database. The models.py file is where the pyramid_zodb scaffold put the classes that implement our resource objects, each of which happens also to be a domain model object.

Here is the source for models.py:

```
from persistent.mapping import PersistentMapping
class MyModel(PersistentMapping):
    ___parent___ = __name___ = None
def appmaker(zodb_root):
    if not 'app_root' in zodb_root:
```

```
8 app_root = MyModel()
9 zodb_root['app_root'] = app_root
10 import transaction
11 transaction.commit()
12 return zodb_root['app_root']
```

- 1. *Lines 3-4.* The MyModel *resource* class is implemented here. Instances of this class will be capable of being persisted in *ZODB* because the class inherits from the persistent.mapping.PersistentMapping class. The __parent__ and __name__ are important parts of the *traversal* protocol. By default, have these as None indicating that this is the *root* object.
- 2. *Lines 6-12.* appmaker is used to return the *application root* object. It is called on *every request* to the Pyramid application. It also performs bootstrapping by *creating* an application root (inside the ZODB root object) if one does not already exist.

We do so by first seeing if the database has the persistent application root. If not, we make an instance, store it, and commit the transaction. We then return the application root object.

31.3.3 Views With views.py

Our scaffold generated a default views.py on our behalf. It contains a single view, which is used to render the page shown when you visit the URL http://localhost:6543/.

Here is the source for views.py:

Let's try to understand the components in this module:

1. Lines 1-2. Perform some dependency imports.

31. ZODB + TRAVERSAL WIKI TUTORIAL

2. *Line 4.* Use the pyramid.view.view_config() *configuration decoration* to perform a *view configuration* registration. This view configuration registration will be activated when the application is started. It will be activated by virtue of it being found as the result of a *scan* (when Line 17 of ____init___.py is run).

The @view_config decorator accepts a number of keyword arguments. We use two keyword arguments here: context and renderer.

The context argument signifies that the decorated view callable should only be run when *traversal* finds the tutorial.models.MyModel *resource* to be the *context* of a request. In English, this means that when the URL / is visited, because MyModel is the root model, this view callable will be invoked.

The renderer argument names an *asset specification* of tutorial:templates/mytemplate.pt. This asset specification points at a *Chameleon* template which lives in the mytemplate.pt file within the templates directory of the tutorial package. And indeed if you look in the templates directory of this package, you'll see a mytemplate.pt template file, which renders the default home page of the generated project.

Since this call to @view_config doesn't pass a name argument, the my_view function which it decorates represents the "default" view callable used when the context is of the type MyModel.

3. *Lines 5-6.* We define a *view callable* named my_view, which we decorated in the step above. This view callable is a *function* we write generated by the pyramid_zodb scaffold that is given a request and which returns a dictionary. The mytemplate.pt *renderer* named by the asset specification in the step above will convert this dictionary to a *response* on our behalf.

The function returns the dictionary { 'project': 'tutorial' }. This dictionary is used by the template named by the mytemplate.pt asset specification to fill in certain values on the page.

31.3.4 The WSGI Pipeline in development.ini

The development.ini (in the tutorial *project* directory, as opposed to the tutorial *package* directory) looks like this:

```
[app:tutorial]
use = egg:tutorial
reload_templates = true
debug_authorization = false
debug_notfound = false
debug_routematch = false
```

```
debug_templates = true
default_locale_name = en
zodb_uri = file://%(here)s/Data.fs?connection_cache_size=20000
[pipeline:main]
pipeline =
    egg:WebError#evalerror
    egg:repoze.zodbconn#closer
    egg:repoze.retry#retry
    t.m
    tutorial
[filter:tm]
use = eqq:repoze.tm2#tm
commit_veto = repoze.tm:default_commit_veto
[server:main]
use = egg:Paste#http
host = 0.0.0.0
port = 6543
# Begin logging configuration
[loggers]
keys = root
[handlers]
keys = console
[formatters]
keys = generic
[logger_root]
level = INFO
handlers = console
[handler_console]
class = StreamHandler
args = (sys.stderr,)
level = NOTSET
formatter = generic
[formatter_generic]
format = %(asctime)s %(levelname)-5.5s [%(name)s] %(message)s
# End logging configuration
```

31. ZODB + TRAVERSAL WIKI TUTORIAL

Note the existence of a [pipeline:main] section which specifies our WSGI pipeline. This "pipeline" will be served up as our WSGI application. As far as the WSGI server is concerned the pipeline *is* our application. Simpler configurations don't use a pipeline: instead they expose a single WSGI application as "main". Our setup is more complicated, so we use a pipeline composed of *middleware*.

The egg: WebError#evalerror middleware is at the "top" of the pipeline. This is middleware which displays debuggable errors in the browser while you're developing (not recommended for a production system).

The egg:repoze.zodbconn#closer middleware is in the middle of the pipeline. This is a piece of middleware which closes the ZODB connection opened by the PersistentApplicationFinder at the end of the request.

The egg:repoze.retry#retry middleware catches ConflictError exceptions from ZODB and retries the request up to three times (ZODB is an optimistic concurrency database that relies on application-level transaction retries when a conflict occurs).

The tm middleware is the last piece of middleware in the pipeline. This commits a transaction near the end of the request unless there's an exception raised or the HTTP response code is an error code. The tm refers to the [filter:tm] section beneath the pipeline declaration, which configures the transaction manager.

The final line in the [pipeline:main] section is tutorial, which refers to the [app:tutorial] section above it. The [app:tutorial] section is the section which actually defines our application settings. The values within this section are passed as **settings to the main function we defined in __init__.py when the server is started via paster serve.

31.4 Defining the Domain Model

The first change we'll make to our stock paster-generated application will be to define two *resource* constructors, one representing a wiki page, and another representing the wiki as a mapping of wiki page names to page objects. We'll do this inside our models.py file.

Because we're using ZODB to represent our *resource tree*, each of these resource constructors represents a *domain model* object, so we'll call these constructors "model constructors". Both our Page and Wiki constructors will be class objects. A single instance of the "Wiki" class will serve as a container for "Page" objects, which will be instances of the "Page" class.

The source code for this tutorial stage can be browsed via http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki/src/models/.

31.4.1 Deleting the Database

In the next step, we're going to remove the MyModel Python model class from our models.py file. Since this class is referred to within our persistent storage (represented on disk as a file named Data.fs), we'll have strange things happen the next time we want to visit the application in a browser. Remove the Data.fs from the tutorial directory before proceeding any further. It's always fine to do this as long as you don't care about the content of the database; the database itself will be recreated as necessary.

31.4.2 Making Edits to models.py

There is nothing automagically special about the filename models.py. A project may have many models throughout its codebase in arbitrarily-named files. Files implementing models often have model in their filenames, or they may live in a Python subpackage of your application package named models, but this is only by convention.

The first thing we want to do is remove the MyModel class from the generated models.py file. The MyModel class is only a sample and we're not going to use it.

Then, we'll add a Wiki class. We want it to inherit from the persistent.mapping.PersistentMapping class because it provides mapping behavior, and it makes sure that our Wiki page is stored as a "first-class" persistent object in our ZODB database.

Our Wiki class should have two attributes set to None at class scope: __parent__ and __name__. If a model has a __parent__ attribute of None in a traversal-based Pyramid application, it means that it's the *root* model. The __name__ of the root model is also always None.

Then we'll add a Page class. This class should inherit from the persistent.Persistent class. We'll also give it an __init__ method that accepts a single parameter named data. This parameter will contain the *ReStructuredText* body representing the wiki page content. Note that Page objects don't have an initial __name__ or __parent__ attribute. All objects in a traversal graph must have a __name__ and a __parent__ attribute. We don't specify these here because both __name__ and __parent__ will be set by by a *view* function when a Page is added to our Wiki mapping.

As a last step, we want to change the appmaker function in our models.py file so that the *root resource* of our application is a Wiki instance. We'll also slot a single page object (the front page) into the Wiki within the appmaker. This will provide *traversal* a *resource tree* to work against when it attempts to resolve URLs to resources.

We're using a mini-framework callable named PersistentApplicationFinder in our application (see __init__.py). A PersistentApplicationFinder accepts a ZODB URL as well as an "appmaker" callback. This callback typically lives in the models.py file. We'll just change this function, making the necessary edits.

31.4.3 Looking at the Result of Our Edits to models.py

The result of all of our edits to models.py will end up looking something like this:

```
from persistent import Persistent
  from persistent.mapping import PersistentMapping
2
3
  class Wiki (PersistentMapping):
4
      ___name___ = None
5
      ___parent___ = None
6
7
  class Page (Persistent):
8
      def __init__(self, data):
9
           self.data = data
10
11
  def appmaker(zodb_root):
12
       if not 'app_root' in zodb_root:
13
           app_root = Wiki()
14
           frontpage = Page('This is the front page')
15
           app_root['FrontPage'] = frontpage
16
           frontpage.___name__ = 'FrontPage'
17
           frontpage.___parent___ = app_root
18
           zodb_root['app_root'] = app_root
19
           import transaction
20
           transaction.commit()
21
      return zodb_root['app_root']
22
```

31.4.4 Viewing the Application in a Browser

We can't. At this point, our system is in a "non-runnable" state; we'll need to change view-related files in the next chapter to be able to start the application successfully. If you try to start the application, you'll wind up with a Python traceback on your console that ends with this exception:

ImportError: cannot import name MyModel

This will also happen if you attempt to run the tests.

31.5 Defining Views

A view callable in a traversal -based Pyramid application is typically a simple Python function that accepts two parameters: context and request. A view callable is assumed to return a response object.

• A Pyramid view can also be defined as callable which accepts *only* a *request* argument. You'll see this one-argument pattern used in other Pyramid tutorials and applications. Either calling convention will work in any Pyramid application; the calling conventions can be used interchangeably as necessary. In *traversal* based applications, URLs are mapped to a context *resource*, and since our *resource tree* also represents our application's "domain model", we're often interested in the context, because it represents the persistent storage of our application. For this reason, in this tutorial we define views as callables that accept context in the callable argument list. If you do need the context within a view function that only takes the request as a single argument, you can obtain it via request.context.

We're going to define several *view callable* functions, then wire them into Pyramid using some *view configuration*.

The source code for this tutorial stage can be browsed via http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki/src/views/.

31.5.1 Declaring Dependencies in Our setup.py File

The view code in our application will depend on a package which is not a dependency of the original "tutorial" application. The original "tutorial" application was generated by the paster create command; it doesn't know about our custom application requirements. We need to add a dependency on the docutils package to our tutorial package's setup.py file by assigning this dependency to the install_requires parameter in the setup function.

Our resulting setup.py should look like so:

```
import os
1
2
  from setuptools import setup, find_packages
3
4
5
  here = os.path.abspath(os.path.dirname(___file___))
  README = open(os.path.join(here, 'README.txt')).read()
6
  CHANGES = open(os.path.join(here, 'CHANGES.txt')).read()
7
8
  requires = [
9
      'pyramid',
10
      'repoze.zodbconn',
11
       'repoze.tm2>=1.0b1', # default_commit_veto
12
       'repoze.retry',
13
       'ZODB3',
14
       'WebError',
15
```

```
'docutils',
16
       1
17
18
  setup(name='tutorial',
19
         version='0.0',
20
         description='tutorial',
21
         long_description=README + '\n\n' + CHANGES,
22
         classifiers=[
23
           "Intended Audience :: Developers",
24
           "Framework :: Pylons",
25
           "Programming Language :: Python",
26
           "Topic :: Internet :: WWW/HTTP",
27
           "Topic :: Internet :: WWW/HTTP :: WSGI :: Application",
28
           1,
29
         author='',
30
         author_email='',
31
         url='',
32
         keywords='web pylons pyramid',
33
         packages=find_packages(),
34
         include_package_data=True,
35
         zip_safe=False,
36
         install_requires=requires,
37
         tests_require=requires,
38
         test_suite="tutorial",
39
         entry_points = """\
40
         [paste.app_factory]
41
         main = tutorial:main
42
         """,
43
         paster_plugins=['pyramid'],
44
         )
45
```

• After these new dependencies are added, you will need to rerun python setup.py develop inside the root of the tutorial package to obtain and register the newly added dependency package.

31.5.2 Adding View Functions

We're going to add four *view callable* functions to our views.py module. One view named view_wiki will display the wiki itself (it will answer on the root URL), another named view_page will display an individual page, another named add_page will allow a page to be added, and a final view named edit_page will allow a page to be edited.

U There is nothing special about the filename views.py. A project may have many view callables throughout its codebase in arbitrarily-named files. Files implementing view callables often have view in their filenames (or may live in a Python subpackage of your application package named views), but this is only by convention.

The view_wiki view function

The view_wiki function will be configured to respond as the default view callable for a Wiki resource. We'll provide it with a @view_config decorator which names the class tutorial.models.Wiki as its context. This means that when a Wiki resource is the context, and no *view name* exists in the request, this view will be used. The view configuration associated with view_wiki does not use a renderer because the view callable always returns a *response* object rather than a dictionary. No renderer is necessary when a view returns a response object.

The view_wiki view callable always redirects to the URL of a Page resource named "Front-Page". To do so, it returns an instance of the pyramid.httpexceptions.HTTPFound class (instances of which implement the pyramid.interfaces.IResponse interface like pyramid.response.Response does). The pyramid.url.resource_url() API. pyramid.url.resource_url() constructs a URL to the FrontPage page resource (e.g. http://localhost:6543/FrontPage), and uses it as the "location" of the HTTPFound response, forming an HTTP redirect.

The view_page view function

The view_page function will be configured to respond as the default view of a Page resource. We'll provide it with a @view_config decorator which names the class tutorial.models.Page as its context. This means that when a Page resource is the context, and no *view name* exists in the request, this view will be used. We inform Pyramid this view will use the templates/view.pt template file as a renderer.

The view_page function generates the *ReStructuredText* body of a page (stored as the data attribute of the context passed to the view; the context will be a Page resource) as HTML. Then it substitutes an HTML anchor for each *WikiWord* reference in the rendered HTML using a compiled regular expression.

The curried function named check is used as the first argument to wikiwords.sub, indicating that it should be called to provide a value for each WikiWord match found in the content. If the wiki (our page's _______) already contains a page with the matched WikiWord name, the check function generates a view link to be used as the substitution value and returns it. If the wiki does not already contain a page

31. ZODB + TRAVERSAL WIKI TUTORIAL

with with the matched WikiWord name, the function generates an "add" link as the substitution value and returns it.

As a result, the content variable is now a fully formed bit of HTML containing various view and add links for WikiWords based on the content of our current page resource.

We then generate an edit URL (because it's easier to do here than in the template), and we wrap up a number of arguments in a dictionary and return it.

The arguments we wrap into a dictionary include page, content, and edit_url. As a result, the *template* associated with this view callable (via renderer= in its configuration) will be able to use these names to perform various rendering tasks. The template associated with this view callable will be a template which lives in templates/view.pt.

Note the contrast between this view callable and the view_wiki view callable. In the view_wiki view callable, we unconditionally return a *response* object. In the view_page view callable, we return a *dictionary*. It is *always* fine to return a *response* object from a Pyramid view. Returning a dictionary is allowed only when there is a *renderer* associated with the view callable in the view configuration.

The add_page view function

The add_page function will be configured to respond when the context resource is a Wiki and the *view name* is add_page. We'll provide it with a @view_config decorator which names the string add_page as its *view name* (via name=), the class tutorial.models.Wiki as its context, and the renderer named templates/edit.pt. This means that when a Wiki resource is the context, and a *view name* named add_page exists as the result of traversal, this view will be used. We inform Pyramid this view will use the templates/edit.pt template file as a renderer. We share the same template between add and edit views, thus edit.pt instead of add.pt.

The add_page function will be invoked when a user clicks on a WikiWord which isn't yet represented as a page in the system. The check function within the view_page view generates URLs to this view. It also acts as a handler for the form that is generated when we want to add a page resource. The context of the add_page view is always a Wiki resource (*not* a Page resource).

The request *subpath* in Pyramid is the sequence of names that are found *after* the *view name* in the URL segments given in the PATH_INFO of the WSGI request as the result of *traversal*. If our add view is invoked via, e.g. http://localhost:6543/add_page/SomeName, the *subpath* will be a tuple: ('SomeName',).

The add view takes the zeroth element of the subpath (the wiki page name), and aliases it to the name attribute in order to know the name of the page we're trying to add.

If the view rendering is *not* a result of a form submission (if the expression 'form.submitted' in request.params is False), the view renders a template. To do so, it generates a "save url" which the template use as the form post URL during rendering. We're lazy here, so we're trying to use the same template (templates/edit.pt) for the add view as well as the page edit view. To do so, we create a dummy Page resource object in order to satisfy the edit form's desire to have *some* page object exposed as page, and we'll render the template to a response.

If the view rendering *is* a result of a form submission (if the expression 'form.submitted' in request.params is True), we scrape the page body from the form data, create a Page object using the name in the subpath and the page body, and save it into "our context" (the Wiki) using the ____setitem___ method of the context. We then redirect back to the view_page view (the default view for a page) for the newly created page.

The edit_page view function

The edit_page function will be configured to respond when the context is a Page resource and the *view name* is edit_page. We'll provide it with a @view_config decorator which names the string edit_page as its *view name* (via name=), the class tutorial.models.Page as its context, and the renderer named templates/edit.pt. This means that when a Page resource is the context, and a *view name* exists as the result of traversal named edit_page, this view will be used. We inform Pyramid this view will use the templates/edit.pt template file as a renderer.

The edit_page function will be invoked when a user clicks the "Edit this Page" button on the view form. It renders an edit form but it also acts as the form post view callable for the form it renders. The context of the edit_page view will *always* be a Page resource (never a Wiki resource).

If the view execution is *not* a result of a form submission (if the expression 'form.submitted' in request.params is False), the view simply renders the edit form, passing the page resource, and a save_url which will be used as the action of the generated form.

If the view execution is a result of a form submission (if the expression 'form.submitted' in request.params is True), the view grabs the body element of the request parameter and sets it as the data attribute of the page context. It then redirects to the default view of the context (the page), which will always be the view_page view.

31.5.3 Viewing the Result of all Our Edits to views.py

The result of all of our edits to views.py will leave it looking like this:

```
from docutils.core import publish_parts
  import re
2
3
4 from pyramid. httpexceptions import HTTPFound
  from pyramid.url import resource_url
5
  from pyramid.view import view_config
6
  from tutorial.models import Page
8
10
  # regular expression used to find WikiWords
  wikiwords = re.compile (r'' b ([A-Z] w+[A-Z]+w+)'')
11
12
  @view_config(context='tutorial.models.Wiki')
13
  def view_wiki(context, request):
14
      return HTTPFound(location=resource_url(context, request, 'FrontPage'))
15
16
  @view_config(context='tutorial.models.Page',
17
                renderer='tutorial:templates/view.pt')
18
  def view_page(context, request):
19
      wiki = context.__parent__
20
21
      def check(match):
22
23
           word = match.group(1)
24
           if word in wiki:
               page = wiki[word]
25
               view_url = resource_url(page, request)
26
               return '<a href="%s">%s</a>' % (view_url, word)
27
           else:
28
               add_url = request.application_url + '/add_page/' + word
29
               return ' <a href="%s">%s</a>' % (add_url, word)
30
31
      content = publish_parts(context.data, writer_name='html')['html_body']
32
      content = wikiwords.sub(check, content)
33
      edit_url = resource_url(context, request, 'edit_page')
34
      return dict(page = context, content = content, edit_url = edit_url)
35
36
  @view_config(name='add_page', context='tutorial.models.Wiki',
37
                renderer='tutorial:templates/edit.pt')
38
  def add_page(context, request):
39
      name = request.subpath[0]
40
      if 'form.submitted' in request.params:
41
          body = request.params['body']
42
           page = Page(body)
43
          page.___name___ = name
44
          page.__parent__ = context
45
          context[name] = page
46
```

```
47
           return HTTPFound(location = resource_url(page, request))
      save_url = resource_url(context, request, 'add_page', name)
48
      page = Page('')
49
      page.___name___ = name
50
      page.__parent__ = context
51
      return dict (page = page, save_url = save_url)
52
53
  @view_config(name='edit_page', context='tutorial.models.Page',
54
                renderer='tutorial:templates/edit.pt')
55
  def edit_page(context, request):
56
      if 'form.submitted' in request.params:
57
           context.data = request.params['body']
58
           return HTTPFound(location = resource_url(context, request))
59
60
      return dict(page = context,
61
                   save_url = resource_url(context, request, 'edit_page'))
62
```

31.5.4 Adding Templates

Most view callables we've added expected to be rendered via a *template*. The default templating systems in Pyramid are *Chameleon* and *Mako*. Chameleon is a variant of *ZPT*, which is an XML-based templating language. Mako is a non-XML-based templating language. Because we had to pick one, we chose Chameleon for this tutorial.

The templates we create will live in the templates directory of our tutorial package. Chameleon templates must have a .pt extension to be recognized as such.

The view.pt Template

The view.pt template is used for viewing a single Page. It is used by the view_page view function. It should have a div that is "structure replaced" with the content value provided by the view. It should also have a link on the rendered page that points at the "edit" URL (the URL which invokes the edit_page view for the page being viewed).

Once we're done with the view.pt template, it will look a lot like the below:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
      xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
  <title>${page. name } - Pyramid tutorial wiki (based on
      TurboGears 20-Minute Wiki) </title>
  <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
  <meta name="keywords" content="python web application" />
  <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
        type="text/css" media="screen" charset="utf-8" />
  <!--[if lte IE 6]>
  <link rel="stylesheet"
        href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
  <![endifl-->
</head>
<bodv>
 <div id="wrap">
    <div id="top-small">
      <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
        src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
      </div>
    </div>
    <div id="middle">
      <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
          Viewing <b><span tal:replace="page.__name__">Page Name Goes
         Here</span></b><br/>
          You can return to the
          <a href="${request.application_url}">FrontPage</a>.<br/>></pr>
        </div>
        <div id="right" class="app-welcome align-right"></div>
      </div>
    </div>
    <div id="bottom">
      <div class="bottom">
        <div tal:replace="structure content">
          Page text goes here.
```

```
</div>
</div>
</div>
</div
</div>
```

• The names available for our use in a template are always those that are present in the dictionary returned by the view callable. But our templates make use of a request object that none of our tutorial views return in their dictionary. This value appears as if "by magic". However, request is one of several names that are available "by default" in a template when a template renderer is used. See *.*pt or* *.*txt: Chameleon Template Renderers* for more information about other names that are available by default in a template is used as a renderer.

The edit.pt Template

The edit.pt template is used for adding and editing a Page. It is used by the add_page and edit_page view functions. It should display a page containing a form that POSTs back to the "save_url" argument supplied by the view. The form should have a "body" textarea field (the page data), and a submit button that has the name "form.submitted". The textarea in the form should be filled with any existing page data when it is rendered.

Once we're done with the edit.pt template, it will look a lot like the below:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
   "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
        xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
   <title>${page.__name__} - Pyramid tutorial wiki (based on
        TurboGears 20-Minute Wiki)</title>
```

```
<meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
  <meta name="keywords" content="python web application" />
  <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
        type="text/css" media="screen" charset="utf-8" />
  <!--[if lte IE 6]>
  <link rel="stylesheet"
        href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endifl-->
</head>
<body>
 <div id="wrap">
    <div id="top-small">
      <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
        src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
      </div>
    </div>
    <div id="middle">
      <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
          Editing <b><span tal:replace="page.__name__">Page Name Goes
            Here</span></b><br/>
          You can return to the
          <a href="${request.application_url}">FrontPage</a>.<br/>></pr>
        </div>
        <div id="right" class="app-welcome align-right"></div>
      </div>
    </div>
    <div id="bottom">
      <div class="bottom">
        <form action="${save_url}" method="post">
          <textarea name="body" tal:content="page.data" rows="10"
                    cols="60"/><br/>
          <input type="submit" name="form.submitted" value="Save"/>
        </form>
      </div>
   </div>
  </div>
  <div id="footer">
```

Static Assets

Our templates name a single static asset named pylons.css. We don't need to create this file within our package's static directory because it was provided at the time we created the project. This file is a little too long to replicate within the body of this guide, however it is available online.

This CSS file will be accessed via e.g. http://localhost:6543/static/pylons.css by virtue of the call to add_static_view directive we've made in the __init__.py file. Any number and type of static assets can be placed in this directory (or subdirectories) and are just referred to by URL or by using the convenience method static_url e.g. request.static_url('{{package}}:static/foo.css') within templates.

31.5.5 Viewing the Application in a Browser

We can finally examine our application in a browser. The views we'll try are as follows:

- Visiting http://localhost:6543/ in a browser invokes the view_wiki view. This always redirects to the view_page view of the FrontPage Page resource.
- Visiting http://localhost:6543/FrontPage/ in a browser invokes the view_page view of the front page resource. This is because it's the *default view* (a view without a name) for Page resources.
- Visiting http://localhost:6543/FrontPage/edit_page in a browser invokes the edit view for the FrontPage Page resource.
- Visiting http://localhost:6543/add_page/SomePageName in a browser invokes the add view for a Page.
- To generate an error, visit http://localhost:6543/add_page which will generate an IndexError for the expression request.subpath[0]. You'll see an interactive traceback facility provided by *WebError*.

31.6 Adding Authorization

Our application currently allows anyone with access to the server to view, edit, and add pages to our wiki. For purposes of demonstration we'll change our application to allow people whom are members of a *group* named group:editors to add and edit wiki pages but we'll continue allowing anyone with access to the server to view pages. Pyramid provides facilities for *authorization* and *authentication*. We'll make use of both features to provide security to our application.

We will add an *authentication policy* and an *authorization policy* to our *application registry*, add a security.py module and give our *root* resource an *ACL*.

Then we will add login and logout views, and modify the existing views to make them return a logged_in flag to the renderer and add *permission* declarations to their view_config decorators.

Finally, we will add a login.pt template and change the existing view.pt and edit.pt to show a "Logout" link when not logged in.

The source code for this tutorial stage can be browsed via http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki/src/authorization/.

31.6.1 Adding Authentication and Authorization Policies

We'll change our package's __init__.py file to enable an AuthTktAuthenticationPolicy and an ACLAuthorizationPolicy to enable declarative security checking. We need to import the new policies:

```
1 from pyramid.authentication import AuthTktAuthenticationPolicy
2 from pyramid.authorization import ACLAuthorizationPolicy
```

3 from tutorial.security import groupfinder

Then, we'll add those policies to the configuration:

Note that the creation of an AuthTktAuthenticationPolicy requires two arguments: secret and callback. secret is a string representing an encryption key used by the "authentication ticket" machinery represented by this policy: it is required. The callback is a reference to a groupfinder function in the tutorial package's security.py file. We haven't added that module yet, but we're about to.

When you're done, your _____init____.py will look like so:

```
1
  from repoze.zodbconn.finder import PersistentApplicationFinder
2
  from pyramid.config import Configurator
3
  from pyramid.authentication import AuthTktAuthenticationPolicy
4
  from pyramid.authorization import ACLAuthorizationPolicy
  from tutorial.models import appmaker
7
  from tutorial.security import groupfinder
8
  def main(global_config, **settings):
10
      """ This function returns a WSGI application.
11
12
      It is usually called by the PasteDeploy framework during
13
       ''paster serve''.
14
      .....
15
      authn_policy = AuthTktAuthenticationPolicy(secret='sosecret',
16
                                                    callback=groupfinder)
17
      authz_policy = ACLAuthorizationPolicy()
18
      zodb_uri = settings.get('zodb_uri', False)
19
      if zodb uri is False:
20
          raise ValueError ("No 'zodb_uri' in application configuration.")
21
22
      finder = PersistentApplicationFinder(zodb_uri, appmaker)
23
      def get_root (request):
24
           return finder(request.environ)
25
      config = Configurator(root_factory=get_root, settings=settings,
26
                              authentication_policy=authn_policy,
27
                              authorization_policy=authz_policy)
28
      config.add_static_view('static', 'tutorial:static')
29
      config.scan('tutorial')
30
      return config.make_wsgi_app()
31
```

31.6.2 Adding security.py

Add a security.py module within your package (in the same directory as __init__.py, views.py, etc.) with the following content:

The groupfinder function defined here is an *authentication policy* "callback"; it is a callable that accepts a userid and a request. If the userid exists in the system, the callback will return a sequence of group identifiers (or an empty sequence if the user isn't a member of any groups). If the userid *does not* exist in the system, the callback will return None. In a production system, user and group data will most often come from a database, but here we use "dummy" data to represent user and groups sources. Note that the editor user is a member of the group:editors group in our dummy group data (the GROUPS data structure).

31.6.3 Giving Our Root Resource an ACL

We need to give our root resource object an *ACL*. This ACL will be sufficient to provide enough information to the Pyramid security machinery to challenge a user who doesn't have appropriate credentials when he attempts to invoke the add_page or edit_page views.

We need to perform some imports at module scope in our models.py file:

```
1 from pyramid.security import Allow
2 from pyramid.security import Everyone
```

Our root resource object is a Wiki instance. We'll add the following line at class scope to our Wiki class:

It's only happenstance that we're assigning this ACL at class scope. An ACL can be attached to an object *instance* too; this is how "row level security" can be achieved in Pyramid applications. We actually only need *one* ACL for the entire system, however, because our security requirements are simple, so this feature is not demonstrated.

Our resulting models.py file will now look like so:

```
from persistent import Persistent
1
  from persistent.mapping import PersistentMapping
2
3
  from pyramid.security import Allow
4
  from pyramid.security import Everyone
5
6
  class Wiki(PersistentMapping):
7
      ___name___ = None
8
      ___parent___ = None
9
10
      __acl__ = [ (Allow, Everyone, 'view'),
                    (Allow, 'group:editors', 'edit') ]
11
12
  class Page(Persistent):
13
      def __init__(self, data):
14
           self.data = data
15
16
  def appmaker(zodb_root):
17
      if not 'app_root' in zodb_root:
18
           app_root = Wiki()
19
           frontpage = Page('This is the front page')
20
           app_root['FrontPage'] = frontpage
21
           frontpage.___name___ = 'FrontPage'
22
23
           frontpage.___parent___ = app_root
           zodb_root['app_root'] = app_root
24
           import transaction
25
           transaction.commit()
26
      return zodb_root['app_root']
27
```

31.6.4 Adding Login and Logout Views

We'll add a login view which renders a login form and processes the post from the login form, checking credentials.

We'll also add a logout view to our application and provide a link to it. This view will clear the credentials of the logged in user and redirect back to the front page.

We'll add a different file (for presentation convenience) to add login and logout views. Add a file named login.py to your application (in the same directory as views.py) with the following content:

```
1 from pyramid.httpexceptions import HTTPFound
2
3 from pyramid.security import remember
```

```
4 from pyramid.security import forget
  from pyramid.view import view_config
  from pyramid.url import resource_url
  from tutorial.security import USERS
8
9
  @view_config(context='tutorial.models.Wiki', name='login',
10
                renderer='templates/login.pt')
11
  @view_config(context='pyramid.httpexceptions.HTTPForbidden',
12
                renderer='templates/login.pt')
13
  def login(request):
14
      login_url = resource_url(request.context, request, 'login')
15
      referrer = request.url
16
      if referrer == login_url:
17
           referrer = '/' # never use the login form itself as came from
18
      came_from = request.params.get('came_from', referrer)
19
      message = ''
20
      login = ''
21
      password = ''
22
      if 'form.submitted' in request.params:
23
           login = request.params['login']
24
           password = request.params['password']
25
           if USERS.get(login) == password:
26
               headers = remember(request, login)
27
               return HTTPFound(location = came_from,
28
                                 headers = headers)
29
           message = 'Failed login'
30
31
      return dict (
32
           message = message,
33
           url = request.application_url + '/login',
34
           came_from = came_from,
35
           login = login,
36
           password = password,
37
           )
38
39
  (view_config(context='tutorial.models.Wiki', name='logout')
40
  def logout(request):
41
      headers = forget (request)
42
      return HTTPFound(location = resource_url(request.context, request),
43
                         headers = headers)
44
```

Note that the login view callable in the login.py file has *two* view configuration decorators. The order of these decorators is unimportant. Each just adds a different *view configuration* for the login view callable.

The first view configuration decorator configures the login view callable so it will be invoked when someone visits /login (when the context is a Wiki and the view name is login). The second decorator (with context of pyramid.httpexceptions.HTTPForbidden) specifies a *forbidden view*. This configures our login view to be presented to the user when Pyramid detects that a view invocation can not be authorized. Because we've configured a forbidden view, the login view callable will be invoked whenever one of our users tries to execute a view callable that they are not allowed to invoke as determined by the *authorization policy* in use. In our application, for example, this means that if a user has not logged in, and he tries to add or edit a Wiki page, he will be shown the login form. Before being allowed to continue on to the add or edit form, he will have to provide credentials that give him permission to add or edit via this login form.

31.6.5 Changing Existing Views

Then we need to change each of our view_page, edit_page and add_page views in views.py to pass a "logged in" parameter into its template. We'll add something like this to each view body:

```
1 from pyramid.security import authenticated_userid
2 logged_in = authenticated_userid(request)
```

We'll then change the return value of each view that has an associated renderer to pass the resulting logged_in value to the template. For example:

```
1 return dict(page = context,
2 content = content,
3 logged_in = logged_in,
4 edit_url = edit_url)
```

31.6.6 Adding permission Declarations to our view_config Decorators

To protect each of our views with a particular permission, we need to pass a permission argument to each of our pyramid.view.view_config decorators. To do so, within views.py:

• We add permission='view' to the decorator attached to the view_wiki and view_page view functions. This makes the assertion that only users who possess the view permission against the context resource at the time of the request may invoke these views. We've granted pyramid.security.Everyone the view permission at the root model via its ACL, so everyone will be able to invoke the view_wiki and view_page views.

• We add permission='edit' to the decorator attached to the add_page and edit_page view functions. This makes the assertion that only users who possess the effective edit permission against the context resource at the time of the request may invoke these views. We've granted the group:editors principal the edit permission at the root model via its ACL, so only a user whom is a member of the group named group:editors will able to invoke the add_page or edit_page views. We've likewise given the editor user membership to this group via the security.py file by mapping him to the group:editors group in the GROUPS data structure (GROUPS = {'editor':['group:editors']}); the groupfinder function consults the GROUPS data structure. This means that the editor user can add and edit pages.

31.6.7 Adding the login.pt Template

Add a login.pt template to your templates directory. It's referred to within the login view we just added to login.py.

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
     xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
 <title>Login - Pyramid tutorial wiki (based on TurboGears
   20-Minute Wiki) </title>
 <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
 <meta name="keywords" content="python web application" />
 <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
       type="text/css" media="screen" charset="utf-8" />
 <!--[if lte IE 6]>
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endif]-->
</head>
<body>
 <div id="wrap">
   <div id="top-small">
     <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
       src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
```

```
</div>
    </div>
    <div id="middle">
      <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
          <b>Login</b><br/>>
          <span tal:replace="message"/>
        </div>
        <div id="right" class="app-welcome align-right"></div>
      </div>
    </div>
    <div id="bottom">
      <div class="bottom">
        <form action="${url}" method="post">
          <input type="hidden" name="came_from" value="${came_from}"/>
          <input type="text" name="login" value="${login}"/><br/>>
          <input type="password" name="password"
                 value="${password}"/><br/>
          <input type="submit" name="form.submitted" value="Log In"/>
        </form>
      </div>
    </div>
  </div>
  <div id="footer">
    <div class="footer"
         >© Copyright 2008-2011, Agendaless Consulting.</div>
  </div>
</body>
</html>
```

31.6.8 Change view.pt and edit.pt

We'll also need to change our edit.pt and view.pt templates to display a "Logout" link if someone is logged in. This link will invoke the logout view.

To do so we'll add this to both templates within the <div id="right" class="app-welcome align-right">div:

31.6.9 Seeing Our Changes To views.py and our Templates

Our views.py module will look something like this when we're done:

```
1 from docutils.core import publish_parts
  import re
2
  from pyramid. httpexceptions import HTTPFound
4
5 from pyramid.url import resource_url
  from pyramid.view import view_config
6
  from pyramid.security import authenticated_userid
  from tutorial.models import Page
9
10
  # regular expression used to find WikiWords
11
 wikiwords = re.compile(r"\b([A-Z] \setminus w+ [A-Z] + \setminus w+)")
12
13
  @view config(context='tutorial.models.Wiki', permission='view')
14
  def view_wiki(context, request):
15
      return HTTPFound(location=resource_url(context, request, 'FrontPage'))
16
17
  @view_config(context='tutorial.models.Page',
18
                renderer='templates/view.pt', permission='view')
19
  def view_page(context, request):
20
      wiki = context.__parent__
21
22
      def check(match):
23
          word = match.group(1)
24
           if word in wiki:
25
               page = wiki[word]
26
               view_url = resource_url(page, request)
27
               return '<a href="%s">%s</a>' % (view_url, word)
28
           else:
29
               add_url = request.application_url + '/add_page/' + word
30
               return ' <a href="%s">%s</a>' % (add_url, word)
31
32
      content = publish_parts(context.data, writer_name='html')['html_body']
33
      content = wikiwords.sub(check, content)
34
      edit_url = resource_url(context, request, 'edit_page')
35
36
      logged_in = authenticated_userid(request)
37
38
      return dict (page = context, content = content, edit_url = edit_url,
39
                   logged_in = logged_in)
40
41
  @view_config(name='add_page', context='tutorial.models.Wiki',
42
```

```
43
                renderer='templates/edit.pt',
                permission='edit')
44
  def add_page(context, request):
45
      name = request.subpath[0]
46
      if 'form.submitted' in request.params:
47
          body = request.params['body']
48
          page = Page(body)
49
          page.___name___ = name
50
          page.__parent__ = context
51
           context[name] = page
52
           return HTTPFound(location = resource_url(page, request))
53
      save_url = resource_url(context, request, 'add_page', name)
54
      page = Page('')
55
      page.___name___ = name
56
      page.__parent__ = context
57
58
      logged_in = authenticated_userid(request)
59
60
      return dict(page = page, save_url = save_url, logged_in = logged_in)
61
62
  @view_config(name='edit_page', context='tutorial.models.Page',
63
                renderer='templates/edit.pt',
64
                permission='edit')
65
  def edit_page(context, request):
66
      if 'form.submitted' in request.params:
67
           context.data = request.params['body']
68
           return HTTPFound(location = resource_url(context, request))
69
70
      logged_in = authenticated_userid(request)
71
72
      return dict (page = context,
73
                   save_url = resource_url(context, request, 'edit_page'),
74
                   logged_in = logged_in)
75
```

Our edit.pt template will look something like this when we're done:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
1
    "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
2
  <html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
3
        xmlns:tal="http://xml.zope.org/namespaces/tal">
4
  <head>
5
    <title>${page.__name__} - Pyramid tutorial wiki (based on
6
        TurboGears 20-Minute Wiki) </title>
7
    <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
8
    <meta name="keywords" content="python web application" />
9
    <meta name="description" content="pyramid web application" />
10
```

31. ZODB + TRAVERSAL WIKI TUTORIAL

```
<link rel="shortcut icon"
11
          href="${request.static_url('tutorial:static/favicon.ico')}" />
12
    <link rel="stylesheet"
13
           href="${request.static_url('tutorial:static/pylons.css')}"
14
           type="text/css" media="screen" charset="utf-8" />
15
    <!--[if lte IE 6]>
16
    <link rel="stylesheet"
17
           href="${request.static_url('tutorial:static/ie6.css')}"
18
           type="text/css" media="screen" charset="utf-8" />
19
    <! [endifl-->
20
  </head>
21
  <body>
22
    <div id="wrap">
23
       <div id="top-small">
24
         <div class="top-small align-center">
25
           <div>
26
             <img width="220" height="50" alt="pyramid"
27
           src="${request.static_url('tutorial:static/pyramid-small.png')}" />
28
           </div>
29
         </div>
30
       </div>
31
       <div id="middle">
32
         <div class="middle align-right">
33
           <div id="left" class="app-welcome align-left">
34
             Editing <b><span tal:replace="page.__name__">Page Name
35
               Goes Here</span></b><br/>
36
             You can return to the
37
             <a href="${request.application_url}">FrontPage</a>.<br/>
38
           </div>
39
           <div id="right" class="app-welcome align-right">
40
             <span tal:condition="logged_in">
41
                 <a href="${request.application_url}/logout">Logout</a>
42
             </span>
43
           </div>
44
         </div>
45
       </div>
46
       <div id="bottom">
47
         <div class="bottom">
48
           <form action="${save_url}" method="post">
49
             <textarea name="body" tal:content="page.data" rows="10"
50
                        cols="60"/><br/>
51
             <input type="submit" name="form.submitted" value="Save"/>
52
           </form>
53
         </div>
54
       </div>
55
    </div>
56
```

```
57 <div id="footer">
58 <div class="footer"
59 >&copy; Copyright 2008-2011, Agendaless Consulting.</div>
60 </div>
61 </body>
62 </html>
```

Our view.pt template will look something like this when we're done:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
1
     "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
2
  <html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
3
        xmlns:tal="http://xml.zope.org/namespaces/tal">
4
  <head>
5
    <title>${page.__name__} - Pyramid tutorial wiki (based on
6
      TurboGears 20-Minute Wiki) </title>
7
    <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
8
    <meta name="keywords" content="python web application" />
9
    <meta name="description" content="pyramid web application" />
10
    <link rel="shortcut icon"
11
          href="${request.static_url('tutorial:static/favicon.ico')}" />
12
    <link rel="stylesheet"
13
           href="${request.static_url('tutorial:static/pylons.css')}"
14
           type="text/css" media="screen" charset="utf-8" />
15
    <!--[if lte IE 6]>
16
    <link rel="stylesheet"
17
           href="${request.static_url('tutorial:static/ie6.css')}"
18
           type="text/css" media="screen" charset="utf-8" />
19
    <![endif]-->
20
  </head>
21
  <body>
22
    <div id="wrap">
23
      <div id="top-small">
24
         <div class="top-small align-center">
25
26
           <div>
             <img width="220" height="50" alt="pyramid"
27
           src="${request.static_url('tutorial:static/pyramid-small.png')}" />
28
           </div>
29
         </div>
30
      </div>
31
      <div id="middle">
32
        <div class="middle align-right">
33
           <div id="left" class="app-welcome align-left">
34
             Viewing <b><span tal:replace="page.__name__">Page Name
35
               Goes Here</span></b><br/>
36
             You can return to the
37
```

```
<a href="${request.application_url}">FrontPage</a>.<br/>>
38
           </div>
39
           <div id="right" class="app-welcome align-right">
40
             <span tal:condition="logged_in">
41
                <a href="${request.application_url}/logout">Logout</a>
42
             </span>
43
           </div>
44
         </div>
45
       </div>
46
       <div id="bottom">
47
         <div class="bottom">
48
           <div tal:replace="structure content">
49
             Page text goes here.
50
           </div>
51
           52
             <a tal:attributes="href edit_url" href="">
53
                Edit this page
54
             </a>
55
           56
         </div>
57
       </div>
58
     </div>
59
     <div id="footer">
60
       <div class="footer"
61
            > & copy; Copyright 2008-2011, Agendaless Consulting. </div>
62
    </div>
63
  </bodv>
64
  </html>
65
```

31.6.10 Viewing the Application in a Browser

We can finally examine our application in a browser. The views we'll try are as follows:

- Visiting http://localhost:6543/ in a browser invokes the view_wiki view. This always redirects to the view_page view of the FrontPage page resource. It is executable by any user.
- Visiting http://localhost:6543/FrontPage/ in a browser invokes the view_page view of the FrontPage Page resource. This is because it's the *default view* (a view without a name) for Page resources. It is executable by any user.
- Visiting http://localhost:6543/FrontPage/edit_page in a browser invokes the edit view for the FrontPage Page resource. It is executable by only the editor user. If a different user (or the anonymous user) invokes it, a login form will be displayed. Supplying the credentials with the username editor, password editor will show the edit page form being displayed.

- Visiting http://localhost:6543/add_page/SomePageName in a browser invokes the add view for a page. It is executable by only the editor user. If a different user (or the anonymous user) invokes it, a login form will be displayed. Supplying the credentials with the username editor, password editor will show the edit page form being displayed.
- After logging in (as a result of hitting an edit or add page and submitting the login form with the editor credentials), we'll see a Logout link in the upper right hand corner. When we click it, we're logged out, and redirected back to the front page.

31.7 Adding Tests

We will now add tests for the models and the views and a few functional tests in the tests.py. Tests ensure that an application works, and that it continues to work after some changes are made in the future.

31.7.1 Testing the Models

We write tests for the model classes and the appmaker. Changing tests.py, we'll write a separate test class for each model class, and we'll write a test class for the appmaker.

To do so, we'll retain the tutorial.tests.ViewTests class provided as a result of the pyramid_zodb project generator. We'll add three test classes: one for the Page model named PageModelTests, one for the Wiki model named WikiModelTests, and one for the appmaker named AppmakerTests.

31.7.2 Testing the Views

We'll modify our tests.py file, adding tests for each view function we added above. As a result, we'll *delete* the ViewTests test in the file, and add four other test classes: ViewWikiTests, ViewPageTests, AddPageTests, and EditPageTests. These test the view_wiki, view_page, add_page, and edit_page views respectively.

31.7.3 Functional tests

We test the whole application, covering security aspects that are not tested in the unit tests, like logging in, logging out, checking that the viewer user cannot add or edit pages, but the editor user can, and so on.

31.7.4 Viewing the results of all our edits to tests.py

Once we're done with the tests.py module, it will look a lot like the below:

```
import unittest
1
2
  from pyramid import testing
3
4
  class PageModelTests(unittest.TestCase):
5
6
      def _getTargetClass(self):
7
           from tutorial.models import Page
8
           return Page
9
10
      def _makeOne(self, data=u'some data'):
11
           return self._getTargetClass() (data=data)
12
13
      def test_constructor(self):
14
           instance = self._makeOne()
15
           self.assertEqual(instance.data, u'some data')
16
17
  class WikiModelTests(unittest.TestCase):
18
19
      def _getTargetClass(self):
20
           from tutorial.models import Wiki
21
           return Wiki
22
23
      def _makeOne(self):
24
           return self._getTargetClass()()
25
26
      def test_it(self):
27
           wiki = self._makeOne()
28
           self.assertEqual(wiki.__parent__, None)
29
           self.assertEqual(wiki.__name__, None)
30
31
  class AppmakerTests(unittest.TestCase):
32
      def _callFUT(self, zodb_root):
33
           from tutorial.models import appmaker
34
           return appmaker(zodb_root)
35
36
      def test_it(self):
37
           root = \{\}
38
           self._callFUT(root)
39
           self.assertEqual(root['app_root']['FrontPage'].data,
40
                              'This is the front page')
41
42
```

```
class ViewWikiTests(unittest.TestCase):
43
      def test it (self):
44
           from tutorial.views import view_wiki
45
           context = testing.DummyResource()
46
           request = testing.DummyRequest()
47
           response = view_wiki(context, request)
48
           self.assertEqual(response.location, 'http://example.com/FrontPage')
49
50
  class ViewPageTests (unittest.TestCase):
51
      def _callFUT(self, context, request):
52
           from tutorial.views import view_page
53
           return view_page(context, request)
54
55
      def test_it(self):
56
           wiki = testing.DummyResource()
57
           wiki['IDoExist'] = testing.DummyResource()
58
           context = testing.DummyResource(data='Hello CruelWorld IDoExist')
59
           context.___parent___ = wiki
60
           context.___name__ = 'thepage'
61
           request = testing.DummyRequest()
62
           info = self._callFUT(context, request)
63
           self.assertEqual(info['page'], context)
64
           self.assertEqual(
65
               info['content'],
66
               '<div class="document">\n'
67
               Hello <a href="http://example.com/add_page/CruelWorld">'
68
               'CruelWorld</a> '
69
               '<a href="http://example.com/IDoExist/">'
70
               'IDoExist</a>'
71
               '\n</div>\n')
72
           self.assertEqual(info['edit_url'],
73
                             'http://example.com/thepage/edit_page')
74
75
76
  class AddPageTests(unittest.TestCase):
77
      def _callFUT(self, context, request):
78
           from tutorial.views import add_page
79
           return add_page(context, request)
80
81
      def test it notsubmitted(self):
82
           from pyramid.url import resource_url
83
           context = testing.DummyResource()
84
           request = testing.DummyRequest()
85
           request.subpath = ['AnotherPage']
86
           info = self._callFUT(context, request)
87
           self.assertEqual(info['page'].data,'')
88
```

31. ZODB + TRAVERSAL WIKI TUTORIAL

```
self.assertEqual(
89
                info['save url'],
90
                resource_url(context, request, 'add_page', 'AnotherPage'))
91
92
       def test_it_submitted(self):
93
           context = testing.DummyResource()
94
           request = testing.DummyRequest({'form.submitted':True,
95
                                              'body':'Hello yo!'})
96
           request.subpath = ['AnotherPage']
97
           self._callFUT(context, request)
98
           page = context['AnotherPage']
99
           self.assertEqual(page.data, 'Hello yo!')
100
           self.assertEqual(page.___name___, 'AnotherPage')
101
           self.assertEqual(page.__parent__, context)
102
103
   class EditPageTests(unittest.TestCase):
104
       def callFUT(self, context, request):
105
           from tutorial.views import edit_page
106
           return edit_page(context, request)
107
108
       def test_it_notsubmitted(self):
109
           from pyramid.url import resource_url
110
           context = testing.DummyResource()
111
           request = testing.DummyRequest()
112
           info = self._callFUT(context, request)
113
           self.assertEqual(info['page'], context)
114
           self.assertEqual(info['save_url'],
115
                              resource_url(context, request, 'edit_page'))
116
117
       def test_it_submitted(self):
118
           context = testing.DummyResource()
119
           request = testing.DummyRequest({'form.submitted':True,
120
                                              'body':'Hello vo!'})
121
           response = self._callFUT(context, request)
122
           self.assertEqual(response.location, 'http://example.com/')
123
           self.assertEqual(context.data, 'Hello yo!')
124
125
   class FunctionalTests(unittest.TestCase):
126
127
       viewer_login = '/login?login=viewer&password=viewer' \
128
                       '&came from=FrontPage&form.submitted=Login'
129
       viewer_wrong_login = '/login?login=viewer&password=incorrect' \
130
                        '&came from=FrontPage&form.submitted=Login'
131
       editor_login = '/login?login=editor&password=editor' \
132
                       '&came_from=FrontPage&form.submitted=Login'
133
134
```

```
135
       def setUp(self):
            import tempfile
136
            import os.path
137
            from tutorial import main
138
            self.tmpdir = tempfile.mkdtemp()
139
140
           dbpath = os.path.join( self.tmpdir, 'test.db')
141
            from repoze.zodbconn.uri import db_from_uri
142
           db = db_from_uri('file://' + dbpath)
143
           settings = { 'zodb_uri' : None }
144
145
            app = main({}, **settings)
146
            from repoze.zodbconn.connector import Connector
147
            app = Connector(app, db)
148
            self.db = db
149
            from webtest import TestApp
150
            self.testapp = TestApp(app)
151
152
       def tearDown(self):
153
            import shutil
154
            self.db.close()
155
            shutil.rmtree( self.tmpdir )
156
157
       def test_root(self):
158
           res = self.testapp.get('/', status=302)
159
            self.assertEqual(res.location, 'http://localhost/FrontPage')
160
161
       def test_FrontPage(self):
162
            res = self.testapp.get('/FrontPage', status=200)
163
            self.assertTrue('FrontPage' in res.body)
164
165
       def test_unexisting_page(self):
166
            res = self.testapp.get('/SomePage', status=404)
167
            self.assertTrue('Not Found' in res.body)
168
169
       def test_successful_log_in(self):
170
171
            res = self.testapp.get( self.viewer_login, status=302)
            self.assertEqual(res.location, 'http://localhost/FrontPage')
172
173
       def test_failed_log_in(self):
174
            res = self.testapp.get( self.viewer_wrong_login, status=200)
175
            self.assertTrue('login' in res.body)
176
177
       def test_logout_link_present_when_logged_in(self):
178
           res = self.testapp.get( self.viewer_login, status=302)
179
           res = self.testapp.get('/FrontPage', status=200)
180
```

```
self.assertTrue('Logout' in res.body)
181
182
       def test_logout_link_not_present_after_logged_out(self):
183
           res = self.testapp.get( self.viewer_login, status=302)
184
           res = self.testapp.get('/FrontPage', status=200)
185
           res = self.testapp.get('/logout', status=302)
186
           self.assertTrue('Logout' not in res.body)
187
188
       def test_anonymous_user_cannot_edit(self):
189
           res = self.testapp.get('/FrontPage/edit_page', status=200)
190
           self.assertTrue('Login' in res.body)
191
192
       def test_anonymous_user_cannot_add(self):
193
           res = self.testapp.get('/add_page/NewPage', status=200)
194
           self.assertTrue('Login' in res.body)
195
196
       def test_viewer_user_cannot_edit(self):
197
           res = self.testapp.get( self.viewer_login, status=302)
198
           res = self.testapp.get('/FrontPage/edit_page', status=200)
199
           self.assertTrue('Login' in res.body)
200
201
       def test_viewer_user_cannot_add(self):
202
           res = self.testapp.get( self.viewer_login, status=302)
203
           res = self.testapp.get('/add_page/NewPage', status=200)
204
           self.assertTrue('Login' in res.body)
205
206
       def test_editors_member_user_can_edit(self):
207
           res = self.testapp.get( self.editor_login, status=302)
208
           res = self.testapp.get('/FrontPage/edit_page', status=200)
209
           self.assertTrue('Editing' in res.body)
210
211
       def test_editors_member_user_can_add(self):
212
           res = self.testapp.get( self.editor_login, status=302)
213
           res = self.testapp.get('/add_page/NewPage', status=200)
214
           self.assertTrue('Editing' in res.body)
215
216
       def test_editors_member_user_can_view(self):
217
           res = self.testapp.get( self.editor_login, status=302)
218
           res = self.testapp.get('/FrontPage', status=200)
219
           self.assertTrue('FrontPage' in res.body)
220
```

31.7.5 Running the Tests

We can run these tests by using setup.py test in the same way we did in *Running the Tests*. However, first we must edit our setup.py to include a dependency on WebTest, which we've used in our tests.py. Change the requires list in setup.py to include WebTest.

```
requires = [
1
      'pyramid',
2
      'repoze.zodbconn',
3
      'repoze.tm2>=1.0b1',
4
      'repoze.retry',
5
      'ZODB3',
6
      'WebError',
7
      'docutils',
8
      'WebTest', # add this
9
       1
10
```

After we've added a dependency on WebTest in setup.py, we need to rerun setup.py develop to get WebTest installed into our virtualenv. Assuming our shell's current working directory is the "tutorial" distribution directory:

On UNIX:

```
$ ../bin/python setup.py develop
```

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\python setup.py develop

Once that command has completed successfully, we can run the tests themselves:

On UNIX:

\$../bin/python setup.py test -q

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\python setup.py test -q

The expected result looks something like:

```
.....Ran 23 tests in 1.653s
OK
```

31.8 Distributing Your Application

Once your application works properly, you can create a "tarball" from it by using the setup.py sdist command. The following commands assume your current working directory is the tutorial package we've created and that the parent directory of the tutorial package is a virtualenv representing a Pyramid environment.

On UNIX:

\$../bin/python setup.py sdist

On Windows:

c:\pyramidtut> ..\Scripts\python setup.py sdist

The output of such a command will be something like:

```
running sdist
# .. more output ..
creating dist
tar -cf dist/tutorial-0.1.tar tutorial-0.1
gzip -f9 dist/tutorial-0.1.tar
removing 'tutorial-0.1' (and everything under it)
```

Note that this command creates a tarball in the "dist" subdirectory named tutorial-0.1.tar.gz. You can send this file to your friends to show them your cool new application. They should be able to install it by pointing the <code>easy_install</code> command directly at it. Or you can upload it to PyPI and share it with the rest of the world, where it can be downloaded via <code>easy_install</code> remotely like any other package people download from PyPI.

CHAPTER

THIRTYTWO

SQLALCHEMY + URL DISPATCH WIKI TUTORIAL

This tutorial introduces a *SQLAlchemy* and *url dispatch* -based Pyramid application to a developer familiar with Python, and will be most familiar to developers who have used the *Pylons* 1.X web framework. When the tutorial is finished, the developer will have created a basic Wiki application with authentication.

For cut and paste purposes, the source code for all stages of this tutorial can be browsed at http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki2/src/.

32.1 Background

This tutorial presents a Pyramid application that uses technologies which will be familiar to someone with *Pylons* experience. It uses *SQLAlchemy* as a persistence mechanism and *url dispatch* to map URLs to code. It can also be followed by people without any prior Python web framework experience.

To code along with this tutorial, the developer will need a UNIX machine with development tools (Mac OS X with XCode, any Linux or BSD variant, etc) *or* a Windows system of any kind.

This tutorial is targeted at Pyramid version 1.0.

Have fun!

32.2 Installation

This tutorial assumes that Python and virtualenv are already installed and working in your system. If you need help setting this up, you should refer to the chapters on *Installing Pyramid*.

32.2.1 Preparation

Please take the following steps to prepare for the tutorial. The steps are slightly different depending on whether you're using UNIX or Windows.

Preparation, UNIX

- 1. Install SQLite3 and its development packages if you don't already have them installed. Usually this is via your system's package manager. For example, on a Debian Linux system, do sudo apt-get install libsqlite3-dev.
- 2. Use your Python's virtualenv to make a workspace:

\$ path/to/my/Python-2.6/bin/virtualenv --no-site-packages pyramidtut

3. Switch to the pyramidtut directory:

```
$ cd pyramidtut
```

4. Use easy_install to get Pyramid and its direct dependencies installed:

\$ bin/easy_install pyramid

5. Use easy_install to install various packages from PyPI.

```
$ bin/easy_install docutils nose coverage zope.sqlalchemy \
        SQLAlchemy repoze.tm2
```

Preparation, Windows

1. Use your Python's virtualenv to make a workspace:

c:\> c:\Python26\Scripts\virtualenv --no-site-packages pyramidtut

2. Switch to the pyramidtut directory:

```
c:\> cd pyramidtut
```

3. Use <code>easy_install</code> to get Pyramid and its direct dependencies installed:

c:\pyramidtut> Scripts\easy_install pyramid

4. Use easy_install to install various packages from PyPI.

c:\pyramidtut> Scripts\easy_install docutils ^ nose coverage zope.sqlalchemy SQLAlchemy repoze.tm2

32.2.2 Making a Project

Your next step is to create a project. Pyramid supplies a variety of scaffolds to generate sample projects. We will use the pyramid_routesalchemy scaffold, which generates an application that uses *SQLAlchemy* and *URL dispatch*.

The below instructions assume your current working directory is the "virtualenv" named "pyramidtut".

On UNIX:

\$ bin/paster create -t pyramid_routesalchemy tutorial

On Windows:

```
c:\pyramidtut> Scripts\paster create -t pyramid_routesalchemy tutorial
```

■ If you are using Windows, the pyramid_routesalchemy scaffold may not deal gracefully with installation into a location that contains spaces in the path. If you experience startup problems, try putting both the virtualenv and the project into directories that do not contain spaces in their paths.

32.2.3 Installing the Project in "Development Mode"

In order to do development on the project easily, you must "register" the project as a development egg in your workspace using the setup.py develop command. In order to do so, cd to the "tutorial" directory you created in *Making a Project*, and run the "setup.py develop" command using virtualenv Python interpreter.

On UNIX:

```
$ cd tutorial
$ ../bin/python setup.py develop
```

On Windows:

```
c:\pyramidtut> cd tutorial
c:\pyramidtut\tutorial> ..\Scripts\python setup.py develop
```

32.2.4 Running the Tests

After you've installed the project in development mode, you may run the tests for the project.

On UNIX:

```
$ ../bin/python setup.py test -q
```

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\python setup.py test -q

32.2.5 Starting the Application

Start the application.

On UNIX:

\$../bin/paster serve development.ini --reload

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\paster serve development.ini --reload

32.2.6 Exposing Test Coverage Information

You can run the nosetests command to see test coverage information. This runs the tests in the same way that setup.py test does but provides additional "coverage" information, exposing which lines of your project are "covered" (or not covered) by the tests.

To get this functionality working, we'll need to install a couple of other packages into our virtualenv: nose and coverage:

On UNIX:

\$../bin/easy_install nose coverage

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\easy_install nose coverage

Once nose and coverage are installed, we can actually run the coverage tests.

On UNIX:

\$../bin/nosetests --cover-package=tutorial --cover-erase --with-coverage

On Windows:

Looks like our package's models module doesn't quite have 100% test coverage.

32.2.7 Visit the Application in a Browser

In a browser, visit http://localhost:6543/. You will see the generated application's default page.

32.2.8 Decisions the pyramid_routesalchemy Scaffold Has Made For You

Creating a project using the pyramid_routesalchemy scaffold makes the following assumptions:

- you are willing to use SQLAlchemy as a database access tool
- you are willing to use *url dispatch* to map URLs to code.
- you want to configure your application imperatively (no declarative configuration such as ZCML).

Pyramid supports any persistent storage mechanism (e.g. object database or filesystem files, etc). It also supports an additional mechanism to map URLs to code (*traversal*). However, for the purposes of this tutorial, we'll only be using url dispatch and SQLAlchemy.

32.3 Basic Layout

The starter files generated by the pyramid_routesalchemy scaffold are basic, but they provide a good orientation for the high-level patterns common to most *url dispatch* -based Pyramid projects.

The source code for this tutorial stage can be browsed at http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki2/src/basiclayout/.

32.3.1 App Startup with __init__.py

A directory on disk can be turned into a Python *package* by containing an __init__.py file. Even if empty, this marks a directory as a Python package. We use __init__.py both as a package marker and to contain configuration code.

The generated development.ini file is read by paster which looks for the application module in the use variable of the app:tutorial section. The *entry point* is defined in the Setuptools configuration of this module, specifically in the setup.py file. For this tutorial, the *entry point* is defined as tutorial:main and points to a function named main.

First we need some imports to support later code:

```
1 from pyramid.config import Configurator
2 from sqlalchemy import engine_from_config
3
4 from tutorial.models import initialize_sql
```

Next we define the main function and create a SQLAlchemy database engine from the sqlalchemy. prefixed settings in the development.ini file's [app:tutorial] section. This will be a URI (something like sqlite://):

```
def main(global_config, **settings):
    """ This function returns a Pyramid WSGI application.
    """
    engine = engine_from_config(settings, 'sqlalchemy.')
```

We then initialize our SQL database using SQLAlchemy, passing it the engine:

initialize_sql(engine)

The next step is to construct a *Configurator*:

config = Configurator(settings=settings)

settings is passed to the Configurator as a keyword argument with the dictionary values passed by PasteDeploy as the **settings argument. This will be a dictionary of settings parsed from the .ini file, which contains deployment-related values such as reload_templates, db_string, etc.

We now can call pyramid.config.Configurator.add_static_view() with the arguments static (the name), and tutorial:static (the path):

config.add_static_view('static', 'tutorial:static')

This registers a static resource view which will match any URL that starts with /static/. This will serve up static resources for us from within the static directory of our tutorial package, in this case, via http://localhost:6543/static/ and below. With this declaration, we're saying that any URL that starts with /static should go to the static view; any remainder of its path (e.g. the /foo in /static/foo) will be used to compose a path to a static file resource, such as a CSS file.

Using the configurator we can also register a *route configuration* via the pyramid.config.Configurator.add_route() method that will be used when the URL is /:

config.add_route('home', '/')

Since this route has a pattern equalling / it is the route that will be matched when the URL / is visted, e.g. http://localhost:6543/.

Mapping the home route to code is done by registering a view. You will use pyramid.config.Configurator.add_view() in *URL dispatch* to register views for the routes, mapping your patterns to code:

The first positional add_view argument tutorial.views.my_view is the dotted name to a *function* we write (generated by the pyramid_routesalchemy scaffold) that is given a request object and which returns a response or a dictionary. This view also names a renderer, which is a template which lives in the templates subdirectory of the package. When the tutorial.views.my_view view returns a dictionary, a *renderer* will use this template to create a response.

Finally, we use the pyramid.config.Configurator.make_wsgi_app() method to return a *WSGI* application:

return config.make_wsgi_app()

Our final ______.py file will look like this:

```
1 from pyramid.config import Configurator
  from sqlalchemy import engine_from_config
2
3
  from tutorial.models import initialize_sql
4
5
  def main(global_config, **settings):
6
      """ This function returns a Pyramid WSGI application.
7
      .....
8
      engine = engine_from_config(settings, 'sqlalchemy.')
9
      initialize sql(engine)
10
      config = Configurator(settings=settings)
11
      config.add_static_view('static', 'tutorial:static')
12
      config.add_route('home', '/')
13
      config.add_view('tutorial.views.my_view', route_name='home',
14
                       renderer='templates/mytemplate.pt')
15
      return config.make_wsgi_app()
16
```

32.3.2 Content Models with models.py

In a SQLAlchemy-based application, a *model* object is an object composed by querying the SQL database which backs an application. SQLAlchemy is an "object relational mapper" (an ORM). The models.py file is where the pyramid_routesalchemy scaffold put the classes that implement our models.

Let's take a look. First, we need some imports to support later code.

```
import transaction
import transaction
from sqlalchemy import Column
from sqlalchemy import Integer
from sqlalchemy.exc import IntegrityError
from sqlalchemy.ext.declarative import declarative_base
from sqlalchemy.orm import scoped_session
from sqlalchemy.orm import sessionmaker
from sqlalchemy.orm import Sessionmaker
```

Next we set up a SQLAlchemy "DBSession" object:

We also need to create a declarative Base object to use as a base class for our model:

```
Base = declarative_base()
```

To give a simple example of a model class, we define one named MyModel:

```
class MyModel(Base):
1
       __tablename__ = 'models'
2
      id = Column(Integer, primary_key=True)
3
      name = Column(Unicode(255), unique=True)
4
      value = Column(Integer)
5
6
      def __init__(self, name, value):
7
          self.name = name
8
          self.value = value
```

Our sample model has an __init__ that takes a two arguments (name, and value). It stores these values as self.name and self.value within the __init__ function itself. The MyModel class also has a __tablename__ attribute. This informs SQLAlchemy which table to use to store the data representing instances of this class.

Next we define a function named populate which adds a single model instance into our SQL storage and commits a transaction:

```
1 def populate():
2    session = DBSession()
3    model = MyModel(name=u'root',value=55)
4    session.add(model)
5    session.flush()
6    transaction.commit()
```

The function doesn't do a lot in this case, but it's there to illustrate how an application requiring many objects to be set up could work.

Lastly we have a function named initialize_sql which receives a SQL database engine and binds it to our SQLAlchemy DBSession object. It also calls the populate function, to do initial database population. This is the initialization function that is called from __init__.py above.

```
1 def initialize_sql(engine):
2 DBSession.configure(bind=engine)
3 Base.metadata.bind = engine
4 Base.metadata.create_all(engine)
5 try:
6 populate()
7 except IntegrityError:
8 transaction.abort()
```

Here is the complete source for models.py:

```
import transaction
from sqlalchemy import Column
from sqlalchemy import Integer
from sqlalchemy import Unicode
from sqlalchemy.exc import IntegrityError
from sqlalchemy.ext.declarative import declarative_base
from sqlalchemy.orm import scoped_session
```

```
from sqlalchemy.orm import sessionmaker
11
12
  from zope.sqlalchemy import ZopeTransactionExtension
13
14
  DBSession = scoped_session(sessionmaker(
15
                                  extension=ZopeTransactionExtension()))
16
  Base = declarative_base()
17
18
  class MyModel(Base):
19
       __tablename__ = 'models'
20
       id = Column(Integer, primary_key=True)
21
       name = Column(Unicode(255), unique=True)
22
      value = Column(Integer)
23
24
       def init (self, name, value):
25
           self.name = name
26
           self.value = value
27
28
  def populate():
29
       session = DBSession()
30
      model = MyModel(name=u'root',value=55)
31
      session.add(model)
32
       session.flush()
33
      transaction.commit()
34
35
  def initialize_sql(engine):
36
       DBSession.configure(bind=engine)
37
      Base.metadata.bind = engine
38
       Base.metadata.create_all(engine)
39
      try:
40
           populate()
41
       except IntegrityError:
42
           transaction.abort()
43
```

32.4 Defining the Domain Model

The first change we'll make to our stock paster-generated application will be to define a *domain model* constructor representing a wiki page. We'll do this inside our models.py file.

The source code for this tutorial stage can be browsed at http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki2/src/models/.

32.4.1 Making Edits to models.py

• There is nothing automagically special about the filename models.py. A project may have many models throughout its codebase in arbitrarily-named files. Files implementing models often have model in their filenames (or they may live in a Python subpackage of your application package named models), but this is only by convention.

The first thing we want to do is remove the stock MyModel class from the generated models.py file. The MyModel class is only a sample and we're not going to use it.

Next, we'll remove the sqlalchemy.Unicode import and replace it with sqlalchemy.Text.

```
from sqlalchemy import Text
```

Then, we'll add a Page class. Because this is a SQLAlchemy application, this class should inherit from an instance of sqlalchemy.ext.declarative.declarative_base. Declarative SQLAlchemy models are easier to use than directly-mapped ones.

```
class Page (Base):
1
      """ The SQLAlchemy declarative model class for a Page object. """
2
      ___tablename___ = 'pages'
3
      id = Column(Integer, primary_key=True)
4
      name = Column(Text, unique=True)
5
      data = Column(Text)
6
7
      def __init__(self, name, data):
8
           self.name = name
9
           self.data = data
10
```

As you can see, our Page class has a class level attribute <u>tablename</u> which equals the string 'pages'. This means that SQLAlchemy will store our wiki data in a SQL table named pages. Our Page class will also have class-level attributes named id, name and data (all instances of sqlalchemy.Column). These will map to columns in the pages table. The id attribute will be the primary key in the table. The name attribute will be a text attribute, each value of which needs to be unique within the column. The data attribute is a text attribute that will hold the body of each page.

We'll also remove our populate function. We'll inline the populate step into initialize_sql, changing our initialize_sql function to add a FrontPage object to our database at startup time.

```
def initialize_sql(engine):
1
      DBSession.configure(bind=engine)
2
      Base.metadata.bind = engine
3
      Base.metadata.create_all(engine)
4
      try:
5
          transaction.begin()
6
          session = DBSession()
7
          page = Page('FrontPage', 'This is the front page')
8
          session.add(page)
9
          transaction.commit()
10
      except IntegrityError:
11
          # already created
12
          transaction.abort()
13
```

Here, we're using a slightly different binding syntax. It is otherwise largely the same as the initialize_sql in the paster-generated models.py.

Our DBSession assignment stays the same as the original generated models.py.

32.4.2 Looking at the Result of all Our Edits to models.py

The result of all of our edits to models.py will end up looking something like this:

```
import transaction
1
2
 from sqlalchemy import Column
3
4 from sqlalchemy import Integer
  from sqlalchemy import Text
5
6
  from sqlalchemy.exc import IntegrityError
7
  from sqlalchemy.ext.declarative import declarative_base
8
9
  from sqlalchemy.orm import scoped_session
10
  from sqlalchemy.orm import sessionmaker
11
12
  from zope.sqlalchemy import ZopeTransactionExtension
13
14
  DBSession = scoped_session(sessionmaker(
15
                                 extension=ZopeTransactionExtension()))
16
17
 Base = declarative_base()
18
  class Page(Base):
19
```

32. SQLALCHEMY + URL DISPATCH WIKI TUTORIAL

```
""" The SQLAlchemy declarative model class for a Page object. """
20
       __tablename__ = 'pages'
21
      id = Column(Integer, primary_key=True)
22
      name = Column(Text, unique=True)
23
      data = Column(Text)
24
25
      def __init__(self, name, data):
26
           self.name = name
27
           self.data = data
28
29
  def initialize_sql(engine):
30
      DBSession.configure(bind=engine)
31
      Base.metadata.bind = engine
32
      Base.metadata.create_all(engine)
33
      trv:
34
           transaction.begin()
35
           session = DBSession()
36
           page = Page('FrontPage', 'This is the front page')
37
           session.add(page)
38
           transaction.commit()
39
      except IntegrityError:
40
           # already created
41
           transaction.abort()
42
```

32.4.3 Viewing the Application in a Browser

We can't. At this point, our system is in a "non-runnable" state; we'll need to change view-related files in the next chapter to be able to start the application successfully. If you try to start the application, you'll wind up with a Python traceback on your console that ends with this exception:

ImportError: cannot import name MyModel

This will also happen if you attempt to run the tests.

32.5 Defining Views

A view callable in a *url dispatch* -based Pyramid application is typically a simple Python function that accepts a single parameter named *request*. A view callable is assumed to return a *response* object.

• A Pyramid view can also be defined as callable which accepts *two* arguments: a *context* and a *request*. You'll see this two-argument pattern used in other Pyramid tutorials and applications. Either calling convention will work in any Pyramid application; the calling conventions can be used interchangeably as necessary. In *url dispatch* based applications, however, the context object is rarely used in the view body itself, so within this tutorial we define views as callables that accept only a request to avoid the visual "noise". If you do need the context within a view function that only takes the request as a single argument, you can obtain it via request.

The request passed to every view that is called as the result of a route match has an attribute named matchdict that contains the elements placed into the URL by the pattern of a route statement. For instance, if a call to pyramid.config.Configurator.add_route() in __init__.py had the pattern {one}/{two}, and the URL at http://example.com/foo/bar was invoked, matching this pattern, the matchdict dictionary attached to the request passed to the view would have a 'one' key with the value 'foo' and a 'two' key with the value 'bar'.

The source code for this tutorial stage can be browsed at http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki2/src/views/.

32.5.1 Declaring Dependencies in Our setup.py File

The view code in our application will depend on a package which is not a dependency of the original "tutorial" application. The original "tutorial" application was generated by the paster create command; it doesn't know about our custom application requirements. We need to add a dependency on the docutils package to our tutorial package's setup.py file by assigning this dependency to the install_requires parameter in the setup function.

Our resulting setup.py should look like so:

```
import os
1
2
  import sys
3
  from setuptools import setup, find_packages
4
5
  here = os.path.abspath(os.path.dirname(___file___))
6
  README = open(os.path.join(here, 'README.txt')).read()
7
  CHANGES = open(os.path.join(here, 'CHANGES.txt')).read()
8
9
  requires = [
10
      'pyramid',
11
       'SQLAlchemy',
12
       'transaction',
13
```

```
'repoze.tm2>=1.0b1', # default_commit_veto
14
       'zope.sqlalchemy',
15
       'WebError',
16
       'docutils',
17
       1
18
19
  if sys.version_info[:3] < (2,5,0):
20
       requires.append('pysqlite')
21
22
  setup(name='tutorial',
23
         version='0.0',
24
         description='tutorial',
25
         long_description=README + '\n\n' + CHANGES,
26
         classifiers=[
27
           "Programming Language :: Python",
28
           "Framework :: Pylons",
29
           "Topic :: Internet :: WWW/HTTP",
30
           "Topic :: Internet :: WWW/HTTP :: WSGI :: Application",
31
           ],
32
         author='',
33
         author_email='',
34
         url='',
35
         keywords='web wsgi bfg pylons pyramid',
36
         packages=find_packages(),
37
         include_package_data=True,
38
         zip_safe=False,
39
         test_suite='tutorial',
40
         install_requires = requires,
41
         entry_points = """\
42
         [paste.app factory]
43
         main = tutorial:main
44
         .....
45
         paster_plugins=['pyramid'],
46
         )
47
```

• After these new dependencies are added, you will need to rerun python setup.py develop inside the root of the tutorial package to obtain and register the newly added dependency package.

32.5.2 Adding View Functions

We'll get rid of our my_view view function in our views.py file. It's only an example and isn't relevant to our application.

Then we're going to add four *view callable* functions to our views.py module. One view callable (named view_wiki) will display the wiki itself (it will answer on the root URL), another named view_page will display an individual page, another named add_page will allow a page to be added, and a final view callable named edit_page will allow a page to be edited. We'll describe each one briefly and show the resulting views.py file afterward.

There is nothing special about the filename views.py. A project may have many view callables throughout its codebase in arbitrarily-named files. Files implementing view callables often have view in their filenames (or may live in a Python subpackage of your application package named views), but this is only by convention.

The view_wiki view function

The view_wiki function is the *default view* that will be called when a request is made to the root URL of our wiki. It always redirects to a URL which represents the path to our "FrontPage".

The view_wiki function returns an instance of the pyramid.httpexceptions.HTTPFound class (instances of which implement the pyramid.interfaces.IResponse interface like pyramid.response.Response does), It will use the pyramid.url.route_url() API to construct a URL to the FrontPage page (e.g. http://localhost:6543/FrontPage), and will use it as the "location" of the HTTPFound response, forming an HTTP redirect.

The view_page view function

The view_page function will be used to show a single page of our wiki. It renders the *ReStructuredText* body of a page (stored as the data attribute of a Page object) as HTML. Then it substitutes an HTML anchor for each *WikiWord* reference in the rendered HTML using a compiled regular expression.

```
1 def view_page(request):
2 pagename = request.matchdict['pagename']
3 session = DBSession()
4 page = session.query(Page).filter_by(name=pagename).first()
5 if page is None:
6 return HTTPNotFound('No such page')
```

```
7
      def check (match):
8
          word = match.group(1)
9
          exists = session.query(Page).filter_by(name=word).all()
10
          if exists:
11
               view_url = route_url('view_page', request, pagename=word)
12
               return '<a href="%s">%s</a>' % (view_url, word)
13
          else:
14
               add_url = route_url('add_page', request, pagename=word)
15
               return '<a href="%s">%s</a>' % (add_url, word)
16
17
      content = publish_parts(page.data, writer_name='html')['html_body']
18
      content = wikiwords.sub(check, content)
19
      edit_url = route_url('edit_page', request, pagename=pagename)
20
      return dict (page=page, content=content, edit_url=edit_url)
21
```

The curried function named check is used as the first argument to wikiwords.sub, indicating that it should be called to provide a value for each WikiWord match found in the content. If the wiki already contains a page with the matched WikiWord name, the check function generates a view link to be used as the substitution value and returns it. If the wiki does not already contain a page with with the matched WikiWord name, the function generates an "add" link as the substitution value and returns it.

As a result, the content variable is now a fully formed bit of HTML containing various view and add links for WikiWords based on the content of our current page object.

We then generate an edit URL (because it's easier to do here than in the template), and we return a dictionary with a number of arguments. The fact that this view returns a dictionary (as opposed to a *response* object) is a cue to Pyramid that it should try to use a *renderer* associated with the view configuration to render a template. In our case, the template which will be rendered will be the templates/view.pt template, as per the configuration put into effect in __init__.py.

The add_page view function

The add_page function will be invoked when a user clicks on a *WikiWord* which isn't yet represented as a page in the system. The check function within the view_page view generates URLs to this view. It also acts as a handler for the form that is generated when we want to add a page object. The matchdict attribute of the request passed to the add_page view will have the values we need to construct URLs and find model objects.

```
def add_page(request):
1
      name = request.matchdict['pagename']
2
      if 'form.submitted' in request.params:
3
          session = DBSession()
4
          body = request.params['body']
5
          page = Page(name, body)
6
          session.add(page)
7
          return HTTPFound(location = route_url('view_page', request,
8
9
                                                   pagename=name))
      save_url = route_url('add_page', request, pagename=name)
10
      page = Page('', '')
11
      return dict(page=page, save_url=save_url)
12
```

The matchdict will have a 'pagename' key that matches the name of the page we'd like to add. If our add view is invoked via, e.g. http://localhost:6543/add_page/SomeName, the value for 'pagename' in the matchdict will be 'SomeName'.

If the view execution is *not* a result of a form submission (if the expression 'form.submitted' in request.params is False), the view callable renders a template. To do so, it generates a "save url" which the template uses as the form post URL during rendering. We're lazy here, so we're trying to use the same template (templates/edit.pt) for the add view as well as the page edit view, so we create a dummy Page object in order to satisfy the edit form's desire to have *some* page object exposed as page, and Pyramid will render the template associated with this view to a response.

If the view execution *is* a result of a form submission (if the expression 'form.submitted' in request.params is True), we scrape the page body from the form data, create a Page object with this page body and the name taken from matchdict ['pagename'], and save it into the database using session.add. We then redirect back to the view_page view for the newly created page.

The edit_page view function

The edit_page function will be invoked when a user clicks the "Edit this Page" button on the view form. It renders an edit form but it also acts as the handler for the form it renders. The matchdict attribute of the request passed to the edit_page view will have a 'pagename' key matching the name of the page the user wants to edit.

```
1 def edit_page(request):
2     name = request.matchdict['pagename']
3     session = DBSession()
4     page = session.query(Page).filter_by(name=name).one()
5     if 'form.submitted' in request.params:
```

```
page.data = request.params['body']
6
           session.add(page)
7
          return HTTPFound(location = route_url('view_page', request,
8
                                                    pagename=name))
9
      return dict (
10
11
           page=page,
           save_url = route_url('edit_page', request, pagename=name),
12
           )
13
```

If the view execution is *not* a result of a form submission (if the expression 'form.submitted' in request.params is False), the view simply renders the edit form, passing the page object and a save_url which will be used as the action of the generated form.

If the view execution is a result of a form submission (if the expression 'form.submitted' in request.params is True), the view grabs the body element of the request parameters and sets it as the data attribute of the page object. It then redirects to the view_page view of the wiki page.

32.5.3 Viewing the Result of all Our Edits to views.py

The result of all of our edits to views.py will leave it looking like this:

```
import re
2
  from docutils.core import publish_parts
3
4
  from pyramid.httpexceptions import HTTPFound, HTTPNotFound
5
  from pyramid.url import route_url
6
7
  from tutorial.models import DBSession
8
  from tutorial.models import Page
9
10
  # regular expression used to find WikiWords
11
  wikiwords = re.compile(r'' b([A-Z] w+[A-Z]+w+)'')
12
13
  def view_wiki(request):
14
      return HTTPFound(location = route_url('view_page', request,
15
                                               pagename='FrontPage'))
16
17
  def view_page(request):
18
      pagename = request.matchdict['pagename']
19
      session = DBSession()
20
      page = session.guery(Page).filter_by(name=pagename).first()
21
```

```
if page is None:
22
           return HTTPNotFound('No such page')
23
24
      def check(match):
25
           word = match.group(1)
26
           exists = session.query(Page).filter_by(name=word).all()
27
           if exists:
28
               view_url = route_url('view_page', request, pagename=word)
29
               return '<a href="%s">%s</a>' % (view url, word)
30
           else:
31
               add_url = route_url('add_page', request, pagename=word)
32
               return '<a href="%s">%s</a>' % (add url, word)
33
34
      content = publish_parts(page.data, writer_name='html')['html_body']
35
      content = wikiwords.sub(check, content)
36
      edit_url = route_url('edit_page', request, pagename=pagename)
37
      return dict(page=page, content=content, edit_url=edit_url)
38
39
  def add_page(request):
40
      name = request.matchdict['pagename']
41
      if 'form.submitted' in request.params:
42
           session = DBSession()
43
          body = request.params['body']
44
          page = Page(name, body)
45
           session.add(page)
46
           return HTTPFound(location = route_url('view_page', request,
47
                                                    pagename=name))
48
      save_url = route_url('add_page', request, pagename=name)
49
      page = Page('', '')
50
      return dict(page=page, save_url=save_url)
51
52
  def edit_page(request):
53
      name = request.matchdict['pagename']
54
      session = DBSession()
55
      page = session.query(Page).filter_by(name=name).one()
56
      if 'form.submitted' in request.params:
57
           page.data = request.params['body']
58
           session.add(page)
59
           return HTTPFound(location = route_url('view_page', request,
60
                                                    pagename=name))
61
      return dict(
62
          page=page,
63
           save_url = route_url('edit_page', request, pagename=name),
64
65
           )
```

32.5.4 Adding Templates

The views we've added all reference a *template*. Each template is a *Chameleon ZPT* template. These templates will live in the templates directory of our tutorial package.

The view.pt Template

The view.pt template is used for viewing a single wiki page. It is used by the view_page view function. It should have a div that is "structure replaced" with the content value provided by the view. It should also have a link on the rendered page that points at the "edit" URL (the URL which invokes the edit_page view for the page being viewed).

Once we're done with the view.pt template, it will look a lot like the below:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
     xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
 <title>${page.name} - Pyramid tutorial wiki (based on
   TurboGears 20-Minute Wiki) </title>
 <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
 <meta name="keywords" content="python web application" />
 <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <!--[if lte IE 6]>
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endif]-->
</head>
<body>
 <div id="wrap">
   <div id="top-small">
     <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
        src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
```

```
</div>
    </div>
    <div id="middle">
      <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
          Viewing <b><span tal:replace="page.name">Page Name
              Goes Here</span></b><br/>
          You can return to the
          <a href="${request.application_url}">FrontPage</a>.<br/>></pr>
        </div>
        <div id="right" class="app-welcome align-right"></div>
      </div>
    </div>
    <div id="bottom">
      <div class="bottom">
        <div tal:replace="structure content">
          Page text goes here.
        </div>
        <a tal:attributes="href edit_url" href="">
            Edit this page
          </a>
        </div>
    </div>
  </div>
  <div id="footer">
    <div class="footer"
         > & copy; Copyright 2008-2011, Agendaless Consulting. </div>
  </div>
</body>
</html>
```

U The names available for our use in a template are always those that are present in the dictionary returned by the view callable. But our templates make use of a request object that none of our tutorial views return in their dictionary. This value appears as if "by magic". However, request is one of several names that are available "by default" in a template when a template renderer is used. See *.*pt or* *.*txt: Chameleon Template Renderers* for more information about other names that are available by default in a template when a Chameleon template is used as a renderer.

The edit.pt Template

The edit.pt template is used for adding and editing a wiki page. It is used by the add_page and edit_page view functions. It should display a page containing a form that POSTs back to the "save_url" argument supplied by the view. The form should have a "body" textarea field (the page data), and a submit button that has the name "form.submitted". The textarea in the form should be filled with any existing page data when it is rendered.

Once we're done with the edit.pt template, it will look a lot like the below:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
     xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
 <title>${page.name} - Pyramid tutorial wiki (based on
   TurboGears 20-Minute Wiki) </title>
 <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
 <meta name="keywords" content="python web application" />
 <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
       type="text/css" media="screen" charset="utf-8" />
 <!--[if lte IE 6]>
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endifl-->
</head>
<body>
 <div id="wrap">
   <div id="top-small">
     <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
        src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
     </div>
   </div>
    <div id="middle">
     <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
         Editing <b><span tal:replace="page.name">Page Name Goes
            Here</span></b><br/>
```

```
You can return to the
          <a href="${request.application_url}">FrontPage</a>.<br/>></pr>
        </div>
        <div id="right" class="app-welcome align-right"></div>
      </div>
    </div>
    <div id="bottom">
      <div class="bottom">
        <form action="${save_url}" method="post">
          <textarea name="body" tal:content="page.data" rows="10"
                    cols="60"/><br/>
          <input type="submit" name="form.submitted" value="Save"/>
        </form>
      </div>
    </div>
  </div>
  <div id="footer">
    <div class="footer"
         >© Copyright 2008-2011, Agendaless Consulting.</div>
  </div>
</body>
</html>
```

Static Assets

Our templates name a single static asset named pylons.css. We don't need to create this file within our package's static directory because it was provided at the time we created the project. This file is a little too long to replicate within the body of this guide, however it is available online.

This CSS file will be accessed via e.g. http://localhost:6543/static/pylons.css by virtue of the call to add_static_view directive we've made in the __init__.py file. Any number and type of static assets can be placed in this directory (or subdirectories) and are just referred to by URL or by using the convenience method static_url e.g. request.static_url('{{package}}:static/foo.css') within templates.

32.5.5 Mapping Views to URLs in __init__.py

The __init__.py file contains pyramid.config.Configurator.add_view() calls which serve to map routes via *url dispatch* to views. First, we'll get rid of the existing route created by the template using the name ' home'. It's only an example and isn't relevant to our application.

We then need to add four calls to add_route. Note that the *ordering* of these declarations is very important. route declarations are matched in the order they're found in the __init__.py file.

- 1. Add a declaration which maps the pattern / (signifying the root URL) to the route named view_wiki.
- 2. Add a declaration which maps the pattern / {pagename} to the route named view_page. This is the regular view for a page.
- 3. Add a declaration which maps the pattern /add_page/{pagename} to the route named add_page. This is the add view for a new page.
- 4. Add a declaration which maps the pattern /{pagename}/edit_page to the route named edit_page. This is the edit view for a page.

After we've defined the routes for our application, we can register views to handle the processing and rendering that needs to happen when each route is requested.

- 1. Add a declaration which maps the view_wiki route to the view named view_wiki in our views.py file. This is the *default view* for the wiki.
- 2. Add a declaration which maps the view_page route to the view named view_page in our views.py file.
- 3. Add a declaration which maps the add_page route to the view named add_page in our views.py file.
- 4. Add a declaration which maps the edit_page route to the view named edit_page in our views.py file.

As a result of our edits, the __init__.py file should look something like so:

```
from pyramid.config import Configurator
  from sqlalchemy import engine_from_config
2
3
  from tutorial.models import initialize_sql
4
5
  def main(global_config, **settings):
6
      """ This function returns a WSGI application.
7
      .....
8
      engine = engine_from_config(settings, 'sqlalchemy.')
9
      initialize_sql(engine)
10
      config = Configurator(settings=settings)
11
      config.add_static_view('static', 'tutorial:static')
12
      config.add_route('view_wiki', '/')
13
      config.add_route('view_page', '/{pagename}')
14
      config.add_route('add_page', '/add_page/{pagename}')
15
      config.add_route('edit_page', '/{pagename}/edit_page')
16
```

```
config.add_view('tutorial.views.view_wiki', route_name='view_wiki')
17
      config.add_view('tutorial.views.view_page', route_name='view_page',
18
                       renderer='tutorial:templates/view.pt')
19
      config.add_view('tutorial.views.add_page', route_name='add_page',
20
                       renderer='tutorial:templates/edit.pt')
21
      config.add_view('tutorial.views.edit_page', route_name='edit_page',
22
                       renderer='tutorial:templates/edit.pt')
23
      return config.make_wsgi_app()
24
```

32.5.6 Viewing the Application in a Browser

We can finally examine our application in a browser. The views we'll try are as follows:

- Visiting http://localhost:6543 in a browser invokes the view_wiki view. This always redirects to the view_page view of the FrontPage page object.
- Visiting http://localhost:6543/FrontPage in a browser invokes the view_page view of the front page page object.
- Visiting http://localhost:6543/FrontPage/edit_page in a browser invokes the edit view for the front page object.
- Visiting http://localhost:6543/add_page/SomePageName in a browser invokes the add view for a page.

Try generating an error within the body of a view by adding code to the top of it that generates an exception (e.g. raise Exception ('Forced Exception')). Then visit the error-raising view in a browser. You should see an interactive exception handler in the browser which allows you to examine values in a post-mortem mode.

32.6 Adding Authorization

Our application currently allows anyone with access to the server to view, edit, and add pages to our wiki. For purposes of demonstration we'll change our application to allow only people whom possess a specific username (*editor*) to add and edit wiki pages but we'll continue allowing anyone with access to the server to view pages. Pyramid provides facilities for *authorization* and *authentication*. We'll make use of both features to provide security to our application.

We will add an *authentication policy* and an *authorization policy* to our *application registry*, add a security.py module, create a *root factory* with an *ACL*, and add *permission* declarations to the edit_page and add_page views.

Then we will add login and logout views, and modify the existing views to make them return a logged_in flag to the renderer.

Finally, we will add a login.pt template and change the existing view.pt and edit.pt to show a "Logout" link when not logged in.

The source code for this tutorial stage can be browsed at http://github.com/Pylons/pyramid/tree/master/docs/tutorials/wiki2/src/authorization/.

32.6.1 Changing __init__.py For Authorization

We're going to be making several changes to our <u>_____init___.py</u> file which will help us configure an authorization policy.

Adding A Root Factory

We're going to start to use a custom *root factory* within our __init__.py file. The objects generated by the root factory will be used as the *context* of each request to our application. We do this to allow Pyramid declarative security to work properly. The context object generated by the root factory during a request will be decorated with security declarations. When we begin to use a custom root factory to generate our contexts, we can begin to make use of the declarative security features of Pyramid.

We'll modify our <u>___init__</u>.py, passing in a *root factory* to our *Configurator* constructor. We'll point it at a new class we create inside our models.py file. Add the following statements to your models.py file:

The RootFactory class we've just added will be used by Pyramid to construct a context object. The context is attached to the request object passed to our view callables as the context attribute.

The context object generated by our root factory will possess an __acl__ attribute that allows pyramid.security.Everyone (a special principal) to view all pages, while allowing only a *principal* named group:editors to edit and add pages. The __acl__ attribute attached to a context is interpreted specially by Pyramid as an access control list during view callable execution. See *Assigning ACLs to your Resource Objects* for more information about what an *ACL* represents.

We'll pass the RootFactory we created in the step above in as the root_factory argument to a *Configurator*.

Configuring an Authorization Policy

For any Pyramid application to perform authorization, we need to add a security.py module (we'll do that shortly) and we'll need to change our _____init____.py file to add an *authentication policy* and an *authorization policy* which uses the security.py file for a *callback*.

We'll change our __init__.py file to enable an AuthTktAuthenticationPolicy and an ACLAuthorizationPolicy to enable declarative security checking. We need to import the new policies:

```
from pyramid.authentication import AuthTktAuthenticationPolicy
from pyramid.authorization import ACLAuthorizationPolicy
from tutorial.security import groupfinder
```

Then, we'll add those policies to the configuration:

Note that the pyramid.authentication.AuthTktAuthenticationPolicy constructor accepts two arguments: secret and callback. secret is a string representing an encryption key used by the "authentication ticket" machinery represented by this policy: it is required. The callback is a groupfinder function in the current directory's security.py file. We haven't added that module yet, but we're about to.

We'll also change __init__.py, adding a call to pyramid.config.Configurator.add_view() that points at our login *view callable*. This is also known as a *forbidden view*:

1

3

4

1

2

3

A forbidden view configures our newly created login view to show up when Pyramid detects that a view invocation can not be authorized.

A logout view callable will allow users to log out later:

```
1 config.add_route('logout', '/logout')
2 config.add_view('tutorial.login.logout', route_name='logout')
```

We'll also add permission arguments with the value edit to the edit_page and add_page views. This indicates that the view callables which these views reference cannot be invoked without the authenticated user possessing the edit permission with respect to the current context.

Adding these permission arguments causes Pyramid to make the assertion that only users who possess the effective edit permission at the time of the request may invoke those two views. We've granted the group:editors principal the edit permission at the root model via its ACL, so only the a user whom is a member of the group named group:editors will able to invoke the views associated with the add_page or edit_page routes.

Viewing Your Changes

When we're done configuring a root factory, adding an authorization policy, and adding views, your application's __init__.py will look like this:

```
1 from pyramid.config import Configurator
2 from pyramid.authentication import AuthTktAuthenticationPolicy
3 from pyramid.authorization import ACLAuthorizationPolicy
4 
5 from sqlalchemy import engine_from_config
6
```

```
from tutorial.models import initialize_sql
  from tutorial.security import groupfinder
  def main(global_config, **settings):
10
      """ This function returns a WSGI application.
11
      .....
12
      engine = engine_from_config(settings, 'sqlalchemy.')
13
      initialize_sql(engine)
14
      authn_policy = AuthTktAuthenticationPolicy(
15
          'sosecret', callback=groupfinder)
16
      authz_policy = ACLAuthorizationPolicy()
17
      config = Configurator(settings=settings,
18
                             root_factory='tutorial.models.RootFactory',
19
                             authentication_policy=authn_policy,
20
                             authorization policy=authz policy)
21
      config.add_static_view('static', 'tutorial:static')
22
23
      config.add_route('view_wiki', '/')
24
      config.add_route('login', '/login')
25
      config.add_route('logout', '/logout')
26
      config.add_route('view_page', '/{pagename}')
27
      config.add_route('add_page', '/add_page/{pagename}')
28
      config.add_route('edit_page', '/{pagename}/edit_page')
29
30
      config.add_view('tutorial.views.view_wiki', route_name='view_wiki')
31
      config.add_view('tutorial.login.login', route_name='login',
32
                       renderer='tutorial:templates/login.pt')
33
      config.add_view('tutorial.login.logout', route_name='logout')
34
      config.add_view('tutorial.views.view_page', route_name='view_page',
35
                       renderer='tutorial:templates/view.pt')
36
      config.add_view('tutorial.views.add_page', route_name='add_page',
37
                       renderer='tutorial:templates/edit.pt', permission='edit')
38
      config.add_view('tutorial.views.edit_page', route_name='edit_page',
39
                       renderer='tutorial:templates/edit.pt', permission='edit')
40
      config.add_view('tutorial.login.login',
41
                       context='pyramid.httpexceptions.HTTPForbidden',
42
                       renderer='tutorial:templates/login.pt')
43
      return config.make_wsgi_app()
44
```

32.6.2 Adding security.py

Add a security.py module within your package (in the same directory as __init__.py, views.py, etc.) with the following content:

```
1 USERS = {'editor':'editor',
2 'viewer':'viewer'}
3 GROUPS = {'editor':['group:editors']}
4 
5 def groupfinder(userid, request):
6 if userid in USERS:
7 return GROUPS.get(userid, [])
```

The groupfinder function defined here is an *authentication policy* "callback"; it is a callable that accepts a userid and a request. If the userid exists in the system, the callback will return a sequence of group identifiers (or an empty sequence if the user isn't a member of any groups). If the userid *does not* exist in the system, the callback will return None. In a production system, user and group data will most often come from a database, but here we use "dummy" data to represent user and groups sources. Note that the editor user is a member of the group:editors group in our dummy group data (the GROUPS data structure).

We've given the editor user membership to the group:editors by mapping him to this group in the GROUPS data structure (GROUPS = {'editor':['group:editors']}). Since the groupfinder function consults the GROUPS data structure, this will mean that, as a result of the ACL attached to the root returned by the root factory, and the permission associated with the add_page and edit_page views, the editor user should be able to add and edit pages.

32.6.3 Adding Login and Logout Views

We'll add a login view callable which renders a login form and processes the post from the login form, checking credentials.

We'll also add a logout view callable to our application and provide a link to it. This view will clear the credentials of the logged in user and redirect back to the front page.

We'll add a different file (for presentation convenience) to add login and the logout view callables. Add a file named login.py to your application (in the same directory as views.py) with the following content:

```
1 from pyramid.httpexceptions import HTTPFound
2 from pyramid.security import remember
3 from pyramid.security import forget
4 from pyramid.url import route_url
5
6 from tutorial.security import USERS
7
```

```
def login(request):
8
      login_url = route_url('login', request)
9
      referrer = request.url
10
      if referrer == login_url:
11
           referrer = '/' # never use the login form itself as came_from
12
      came_from = request.params.get('came_from', referrer)
13
      message = ''
14
      login = ''
15
      password = ''
16
      if 'form.submitted' in request.params:
17
           login = request.params['login']
18
           password = request.params['password']
19
           if USERS.get(login) == password:
20
               headers = remember(request, login)
21
               return HTTPFound(location = came from,
22
                                  headers = headers)
23
           message = 'Failed login'
24
25
      return dict (
26
           message = message,
27
           url = request.application_url + '/login',
28
           came_from = came_from,
29
           login = login,
30
           password = password,
31
           )
32
33
  def logout(request):
34
      headers = forget (request)
35
      return HTTPFound(location = route_url('view_wiki', request),
36
                         headers = headers)
37
```

32.6.4 Changing Existing Views

Then we need to change each of our view_page, edit_page and add_page views in views.py to pass a "logged in" parameter to its template. We'll add something like this to each view body:

```
1 from pyramid.security import authenticated_userid
2 logged_in = authenticated_userid(request)
```

We'll then change the return value of these views to pass the *resulting 'logged_in'* value to the template, e.g.:

```
1 return dict(page = page,
2 content = content,
3 logged_in = logged_in,
4 edit_url = edit_url)
```

32.6.5 Adding the login.pt Template

Add a login.pt template to your templates directory. It's referred to within the login view we just added to login.py.

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
     xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
 <title>Login - Pyramid tutorial wiki (based on TurboGears
   20-Minute Wiki) </title>
 <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
 <meta name="keywords" content="python web application" />
 <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
       type="text/css" media="screen" charset="utf-8" />
 <!--[if lte IE 6]>
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endif]-->
</head>
<body>
 <div id="wrap">
   <div id="top-small">
     <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
       src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
     </div>
   </div>
   <div id="middle">
      <div class="middle align-right">
```

```
<div id="left" class="app-welcome align-left">
          <b>Login</b><br/>
          <span tal:replace="message"/>
        </div>
        <div id="right" class="app-welcome align-right"></div>
      </div>
   </div>
    <div id="bottom">
      <div class="bottom">
        <form action="${url}" method="post">
          <input type="hidden" name="came_from" value="${came_from}"/>
          <input type="text" name="login" value="${login}"/><br/>
          <input type="password" name="password"
                 value="${password}"/><br/>
          <input type="submit" name="form.submitted" value="Log In"/>
        </form>
     </div>
   </div>
 </div>
 <div id="footer">
   <div class="footer"
         >© Copyright 2008-2011, Agendaless Consulting.</div>
 </div>
</bodv>
</html>
```

32.6.6 Change view.pt and edit.pt

We'll also need to change our edit.pt and view.pt templates to display a "Logout" link if someone is logged in. This link will invoke the logout view.

To do so we'll add this to both templates within the <div id="right" class="app-welcome align-right">div:

32.6.7 Seeing Our Changes To views.py and our Templates

Our views.py module will look something like this when we're done:

```
import re
1
2
  from docutils.core import publish_parts
3
4
  from pyramid. httpexceptions import HTTPFound, HTTPNotFound
5
  from pyramid.security import authenticated_userid
6
  from pyramid.url import route_url
9
  from tutorial.models import DBSession
10
  from tutorial.models import Page
11
  # regular expression used to find WikiWords
12
  wikiwords = re.compile (r'' b ([A-Z] w+[A-Z]+w+)'')
13
14
  def view_wiki(request):
15
      return HTTPFound(location = route_url('view_page', request,
16
                                               pagename='FrontPage'))
17
18
  def view_page(request):
19
      pagename = request.matchdict['pagename']
20
      session = DBSession()
21
      page = session.query(Page).filter_by(name=pagename).first()
22
23
      if page is None:
           return HTTPNotFound('No such page')
24
25
      def check (match):
26
           word = match.group(1)
27
           exists = session.query(Page).filter_by(name=word).all()
28
           if exists:
29
               view_url = route_url('view_page', request, pagename=word)
30
               return ' <a href="%s">%s</a>' % (view_url, word)
31
           else:
32
               add_url = route_url('add_page', request, pagename=word)
33
               return ' <a href="%s">%s</a>' % (add_url, word)
34
35
      content = publish_parts(page.data, writer_name='html')['html_body']
36
      content = wikiwords.sub(check, content)
37
      edit_url = route_url('edit_page', request, pagename=pagename)
38
      logged_in = authenticated_userid(request)
39
      return dict (page=page, content=content, edit_url=edit_url,
40
                   logged_in=logged_in)
41
42
  def add_page(request):
43
      name = request.matchdict['pagename']
44
      if 'form.submitted' in request.params:
45
           session = DBSession()
46
```

```
body = request.params['body']
47
           page = Page(name, body)
48
           session.add(page)
49
           return HTTPFound(location = route_url('view_page', request,
50
                                                    pagename=name))
51
      save_url = route_url('add_page', request, pagename=name)
52
      page = Page('', '')
53
      logged_in = authenticated_userid(request)
54
      return dict(page=page, save_url=save_url, logged_in=logged_in)
55
56
  def edit_page(request):
57
      name = request.matchdict['pagename']
58
      session = DBSession()
59
      page = session.guery(Page).filter_by(name=name).one()
60
      if 'form.submitted' in request.params:
           page.data = request.params['body']
62
           session.add(page)
63
           return HTTPFound(location = route_url('view_page', request,
64
                                                    pagename=name))
65
66
      logged_in = authenticated_userid(request)
67
      return dict(
68
           page=page,
69
           save_url = route_url('edit_page', request, pagename=name),
70
           logged_in = logged_in,
71
           )
72
```

Our edit.pt template will look something like this when we're done:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
     xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
 <title>${page.name} - Pyramid tutorial wiki (based on
   TurboGears 20-Minute Wiki) </title>
 <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
 <meta name="keywords" content="python web application" />
 <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static_url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
       type="text/css" media="screen" charset="utf-8" />
 <!--[if lte IE 6]>
  <link rel="stylesheet"
```

```
href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endif]-->
</head>
<body>
 <div id="wrap">
   <div id="top-small">
     <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
        src="${request.static_url('tutorial:static/pyramid-small.png')}" />
       </div>
     </div>
   </div>
    <div id="middle">
     <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
          Editing <b><span tal:replace="page.name">Page Name
           Goes Here</span></b><br/>
         You can return to the
          <a href="${request.application_url}">FrontPage</a>.<br/>
        </div>
        <div id="right" class="app-welcome align-right">
          <span tal:condition="logged_in">
              <a href="${request.application_url}/logout">Logout</a>
          </span>
        </div>
     </div>
   </div>
   <div id="bottom">
     <div class="bottom">
        <form action="${save_url}" method="post">
          <textarea name="body" tal:content="page.data" rows="10"
                    cols="60"/><br/>
          <input type="submit" name="form.submitted" value="Save"/>
       </form>
     </div>
   </div>
 </div>
 <div id="footer">
   <div class="footer"
        >© Copyright 2008-2011, Agendaless Consulting.</div>
 </div>
</body>
</html>
```

Our view.pt template will look something like this when we're done:

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
      xmlns:tal="http://xml.zope.org/namespaces/tal">
<head>
 <title>${page.name} - Pyramid tutorial wiki (based on
   TurboGears 20-Minute Wiki) </title>
 <meta http-equiv="Content-Type" content="text/html;charset=UTF-8"/>
 <meta name="keywords" content="python web application" />
 <meta name="description" content="pyramid web application" />
 <link rel="shortcut icon"
       href="${request.static url('tutorial:static/favicon.ico')}" />
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/pylons.css')}"
       type="text/css" media="screen" charset="utf-8" />
 <!--[if lte IE 6]>
 <link rel="stylesheet"
       href="${request.static_url('tutorial:static/ie6.css')}"
        type="text/css" media="screen" charset="utf-8" />
 <![endif]-->
</head>
<body>
 <div id="wrap">
   <div id="top-small">
      <div class="top-small align-center">
        <div>
          <img width="220" height="50" alt="pyramid"
        src="${request.static_url('tutorial:static/pyramid-small.png')}" />
        </div>
      </div>
    </div>
    <div id="middle">
      <div class="middle align-right">
        <div id="left" class="app-welcome align-left">
         Viewing <b><span tal:replace="page.name">Page Name
            Goes Here</span></b><br/>
         You can return to the
          <a href="${request.application_url}">FrontPage</a>.<br/>
        </div>
        <div id="right" class="app-welcome align-right">
          <span tal:condition="logged_in">
            <a href="${request.application_url}/logout">Logout</a>
          </span>
        </div>
      </div>
```

```
</div>
    <div id="bottom">
      <div class="bottom">
        <div tal:replace="structure content">
          Page text goes here.
        </div>
        <a tal:attributes="href edit_url" href="">
            Edit this page
          </a>
        </div>
    </div>
 </div>
  <div id="footer">
    <div class="footer"
         > & copy; Copyright 2008-2011, Agendaless Consulting. </div>
  </div>
</body>
</html>
```

32.6.8 Viewing the Application in a Browser

We can finally examine our application in a browser. The views we'll try are as follows:

- Visiting http://localhost:6543/ in a browser invokes the view_wiki view. This always redirects to the view_page view of the FrontPage page object. It is executable by any user.
- Visiting http://localhost:6543/FrontPage in a browser invokes the view_page view of the FrontPage page object.
- Visiting http://localhost:6543/FrontPage/edit_page in a browser invokes the edit view for the FrontPage object. It is executable by only the editor user. If a different user (or the anonymous user) invokes it, a login form will be displayed. Supplying the credentials with the username editor, password editor will display the edit page form.
- Visiting http://localhost:6543/add_page/SomePageName in a browser invokes the add view for a page. It is executable by only the editor user. If a different user (or the anonymous user) invokes it, a login form will be displayed. Supplying the credentials with the username editor, password editor will display the edit page form.
- After logging in (as a result of hitting an edit or add page and submitting the login form with the editor credentials), we'll see a Logout link in the upper right hand corner. When we click it, we're logged out, and redirected back to the front page.

32.7 Adding Tests

We will now add tests for the models and the views and a few functional tests in the tests.py. Tests ensure that an application works, and that it continues to work after some changes are made in the future.

32.7.1 Testing the Models

We write a test class for the model class Page and another test class for the initialize_sql function.

To do so, we'll retain the tutorial.tests.ViewTests class provided as a result of the pyramid_routesalchemy project generator. We'll add two test classes: one for the Page model named PageModelTests, one for the initialize_sql function named InitializeSqlTests.

32.7.2 Testing the Views

We'll modify our tests.py file, adding tests for each view function we added above. As a result, we'll *delete* the ViewTests test in the file, and add four other test classes: ViewWikiTests, ViewPageTests, AddPageTests, and EditPageTests. These test the view_wiki, view_page, add_page, and edit_page views respectively.

32.7.3 Functional tests

We test the whole application, covering security aspects that are not tested in the unit tests, like logging in, logging out, checking that the viewer user cannot add or edit pages, but the editor user can, and so on.

32.7.4 Viewing the results of all our edits to tests.py

Once we're done with the tests.py module, it will look a lot like the below:

```
import unittest
1
2
  from pyramid import testing
3
4
5
  def __initTestingDB():
6
      from tutorial.models import DBSession
7
       from tutorial.models import Base
8
       from sqlalchemy import create_engine
9
      engine = create_engine('sqlite:///:memory:')
10
      DBSession.configure(bind=engine)
11
      Base.metadata.bind = engine
12
      Base.metadata.create_all(engine)
13
      return DBSession
14
15
  def _registerRoutes(config):
16
      config.add_route('view_page', '{pagename}')
17
      config.add_route('edit_page', '{pagename}/edit_page')
18
       config.add_route('add_page', 'add_page/{pagename}')
19
20
21
  class PageModelTests(unittest.TestCase):
22
23
24
      def setUp(self):
           self.session = _initTestingDB()
25
26
      def tearDown(self):
27
           self.session.remove()
28
29
      def _getTargetClass(self):
30
           from tutorial.models import Page
31
           return Page
32
33
      def _makeOne(self, name='SomeName', data='some data'):
34
           return self._getTargetClass() (name, data)
35
36
      def test_constructor(self):
37
           instance = self._makeOne()
38
           self.assertEqual(instance.name, 'SomeName')
39
           self.assertEqual(instance.data, 'some data')
40
41
  class InitializeSqlTests(unittest.TestCase):
42
43
      def setUp(self):
44
           from tutorial.models import DBSession
45
           DBSession.remove()
46
```

```
47
       def tearDown(self):
48
           from tutorial.models import DBSession
49
           DBSession.remove()
50
51
       def _callFUT(self, engine):
52
           from tutorial.models import initialize_sql
53
           return initialize_sql(engine)
54
55
       def test it (self):
56
           from sqlalchemy import create_engine
57
           engine = create_engine('sqlite:///:memory:')
58
           self._callFUT(engine)
59
           from tutorial.models import DBSession, Page
60
           self.assertEqual(DBSession.query(Page).one().data,
61
               'This is the front page')
62
63
  class ViewWikiTests(unittest.TestCase):
64
       def setUp(self):
65
           self.config = testing.setUp()
66
67
       def tearDown(self):
68
           testing.tearDown()
69
70
       def _callFUT(self, request):
71
           from tutorial.views import view_wiki
72
           return view_wiki(request)
73
74
       def test_it(self):
75
           _registerRoutes(self.config)
76
           request = testing.DummyRequest()
77
           response = self._callFUT(request)
78
           self.assertEqual(response.location, 'http://example.com/FrontPage')
79
80
  class ViewPageTests(unittest.TestCase):
81
       def setUp(self):
82
           self.session = _initTestingDB()
83
           self.config = testing.setUp()
84
85
       def tearDown(self):
86
           self.session.remove()
87
           testing.tearDown()
88
89
       def __callFUT(self, request):
90
           from tutorial.views import view_page
91
           return view_page(request)
92
```

```
93
       def test it (self):
94
            from tutorial.models import Page
95
            request = testing.DummyRequest()
96
            request.matchdict['pagename'] = 'IDoExist'
97
           page = Page('IDoExist', 'Hello CruelWorld IDoExist')
98
            self.session.add(page)
00
           _registerRoutes(self.config)
100
           info = self._callFUT(request)
101
           self.assertEqual(info['page'], page)
102
            self.assertEqual(
103
                info['content'],
104
                '<div class="document">\n'
105
                'Hello <a href="http://example.com/add_page/CruelWorld">'
106
                'CruelWorld</a> '
107
                '<a href="http://example.com/IDoExist">'
108
                'IDoExist</a>'
109
                '\n</div>\n')
110
            self.assertEqual(info['edit_url'],
111
                'http://example.com/IDoExist/edit_page')
112
113
  class AddPageTests (unittest.TestCase):
114
       def setUp(self):
115
            self.session = _initTestingDB()
116
            self.config = testing.setUp()
117
            self.config.begin()
118
119
       def tearDown(self):
120
            self.session.remove()
121
           testing.tearDown()
122
123
       def _callFUT(self, request):
124
            from tutorial.views import add_page
125
            return add_page(request)
126
127
       def test_it_notsubmitted(self):
128
           _registerRoutes(self.config)
129
           request = testing.DummyRequest()
130
            request.matchdict = {'pagename':'AnotherPage'}
131
            info = self._callFUT(request)
132
            self.assertEqual(info['page'].data,'')
133
            self.assertEqual(info['save_url'],
134
                               'http://example.com/add_page/AnotherPage')
135
136
       def test_it_submitted(self):
137
            from tutorial.models import Page
138
```

```
_registerRoutes(self.config)
139
            request = testing.DummyRequest({'form.submitted':True,
140
                                               'body':'Hello yo!'})
141
           request.matchdict = {'pagename':'AnotherPage'}
142
            self._callFUT(request)
143
           page = self.session.guery(Page).filter_by(name='AnotherPage').one()
144
            self.assertEqual(page.data, 'Hello yo!')
145
146
   class EditPageTests(unittest.TestCase):
147
       def setUp(self):
148
            self.session = _initTestingDB()
149
            self.config = testing.setUp()
150
151
       def tearDown(self):
152
            self.session.remove()
153
           testing.tearDown()
154
155
       def __callFUT(self, request):
156
            from tutorial.views import edit_page
157
            return edit_page(request)
158
159
       def test it notsubmitted(self):
160
           from tutorial.models import Page
161
           _registerRoutes(self.config)
162
           request = testing.DummyRequest()
163
            request.matchdict = {'pagename':'abc'}
164
           page = Page('abc', 'hello')
165
            self.session.add(page)
166
           info = self._callFUT(request)
167
            self.assertEqual(info['page'], page)
168
            self.assertEqual(info['save_url'],
169
                'http://example.com/abc/edit_page')
170
171
       def test_it_submitted(self):
172
            from tutorial.models import Page
173
            _registerRoutes(self.config)
174
            request = testing.DummyRequest({'form.submitted':True,
175
                'body':'Hello vo!'})
176
            request.matchdict = { 'pagename': 'abc' }
177
           page = Page('abc', 'hello')
178
            self.session.add(page)
179
            response = self._callFUT(request)
180
            self.assertEqual(response.location, 'http://example.com/abc')
181
            self.assertEqual(page.data, 'Hello yo!')
182
183
  class FunctionalTests(unittest.TestCase):
184
```

```
185
       viewer_login = '/login?login=viewer&password=viewer' \
186
                       '&came_from=FrontPage&form.submitted=Login'
187
       viewer_wrong_login = '/login?login=viewer&password=incorrect' \
188
                        '&came_from=FrontPage&form.submitted=Login'
189
       editor_login = '/login?login=editor&password=editor' \
190
                       '&came_from=FrontPage&form.submitted=Login'
191
192
       def setUp(self):
193
            from tutorial import main
194
            settings = { 'sqlalchemy.url': 'sqlite:///:memory:'}
195
            app = main({}, **settings)
196
            from webtest import TestApp
197
            self.testapp = TestApp(app)
198
199
       def tearDown(self):
200
           del self.testapp
201
            from tutorial.models import DBSession
202
           DBSession.remove()
203
204
       def test_root(self):
205
            res = self.testapp.get('/', status=302)
206
            self.assertEqual(res.location, 'http://localhost/FrontPage')
207
208
       def test_FrontPage(self):
209
            res = self.testapp.get('/FrontPage', status=200)
210
            self.assertTrue('FrontPage' in res.body)
211
212
       def test_unexisting_page(self):
213
            self.testapp.get('/SomePage', status=404)
214
215
       def test_successful_log_in(self):
216
            res = self.testapp.get(self.viewer_login, status=302)
217
            self.assertEqual(res.location, 'http://localhost/FrontPage')
218
219
       def test_failed_log_in(self):
220
221
            res = self.testapp.get(self.viewer_wrong_login, status=200)
            self.assertTrue('login' in res.body)
222
223
       def test_logout_link_present_when_logged_in(self):
224
            self.testapp.get(self.viewer_login, status=302)
225
            res = self.testapp.get('/FrontPage', status=200)
226
            self.assertTrue('Logout' in res.body)
227
228
       def test_logout_link_not_present_after_logged_out(self):
229
            self.testapp.get(self.viewer_login, status=302)
230
```

```
self.testapp.get('/FrontPage', status=200)
231
           res = self.testapp.get('/logout', status=302)
232
           self.assertTrue('Logout' not in res.body)
233
234
       def test_anonymous_user_cannot_edit(self):
235
           res = self.testapp.get('/FrontPage/edit_page', status=200)
236
           self.assertTrue('Login' in res.body)
237
238
       def test_anonymous_user_cannot_add(self):
239
           res = self.testapp.get('/add_page/NewPage', status=200)
240
           self.assertTrue('Login' in res.body)
241
242
       def test_viewer_user_cannot_edit(self):
243
           self.testapp.get(self.viewer_login, status=302)
244
           res = self.testapp.get('/FrontPage/edit_page', status=200)
245
           self.assertTrue('Login' in res.body)
246
247
       def test_viewer_user_cannot_add(self):
248
           self.testapp.get(self.viewer_login, status=302)
249
           res = self.testapp.get('/add_page/NewPage', status=200)
250
           self.assertTrue('Login' in res.body)
251
252
       def test_editors_member_user_can_edit(self):
253
           self.testapp.get(self.editor_login, status=302)
254
           res = self.testapp.get('/FrontPage/edit_page', status=200)
255
           self.assertTrue('Editing' in res.body)
256
257
       def test_editors_member_user_can_add(self):
258
           self.testapp.get(self.editor_login, status=302)
259
           res = self.testapp.get('/add_page/NewPage', status=200)
260
           self.assertTrue('Editing' in res.body)
261
262
       def test_editors_member_user_can_view(self):
263
           self.testapp.get(self.editor_login, status=302)
264
           res = self.testapp.get('/FrontPage', status=200)
265
           self.assertTrue('FrontPage' in res.body)
266
```

32.7.5 Running the Tests

We can run these tests by using setup.py test in the same way we did in *Running the Tests*. However, first we must edit our setup.py to include a dependency on WebTest, which we've used in our tests.py. Change the requires list in setup.py to include WebTest.

1	requires = [
2	'pyramid',
3	'SQLAlchemy',
4	'transaction',
5	<pre>'repoze.tm2>=1.0b1',</pre>
6	'zope.sqlalchemy',
7	'WebError',
8	'docutils',
9	'WebTest', # add this
10]

After we've added a dependency on WebTest in setup.py, we need to rerun setup.py develop to get WebTest installed into our virtualenv. Assuming our shell's current working directory is the "tutorial" distribution directory:

On UNIX:

```
$ ../bin/python setup.py develop
```

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\python setup.py develop

Once that command has completed successfully, we can run the tests themselves:

On UNIX:

\$../bin/python setup.py test -q

On Windows:

c:\pyramidtut\tutorial> ..\Scripts\python setup.py test -q

The expected result looks something like:

```
.....Ran 22 tests in 2.700s
```

32.8 Distributing Your Application

Once your application works properly, you can create a "tarball" from it by using the setup.py sdist command. The following commands assume your current working directory is the tutorial package we've created and that the parent directory of the tutorial package is a virtualenv representing a Pyramid environment.

On UNIX:

\$../bin/python setup.py sdist

On Windows:

c:\pyramidtut> ..\Scripts\python setup.py sdist

The output of such a command will be something like:

```
running sdist
# ... more output ...
creating dist
tar -cf dist/tutorial-0.1.tar tutorial-0.1
gzip -f9 dist/tutorial-0.1.tar
removing 'tutorial-0.1' (and everything under it)
```

Note that this command creates a tarball in the "dist" subdirectory named tutorial-0.1.tar.gz. You can send this file to your friends to show them your cool new application. They should be able to install it by pointing the <code>easy_install</code> command directly at it. Or you can upload it to PyPI and share it with the rest of the world, where it can be downloaded via <code>easy_install</code> remotely like any other package people download from PyPI.

CHAPTER

THIRTYTHREE

CONVERTING A REPOZE . BFG APPLICATION TO PYRAMID

Prior iterations of Pyramid were released as a package named repoze.bfg. repoze.bfg users are encouraged to upgrade their deployments to Pyramid, as, after the first final release of Pyramid, further feature development on repoze.bfg will cease.

Most existing repoze.bfg applications can be converted to a Pyramid application in a completely automated fashion. However, if your application depends on packages which are not "core" parts of repoze.bfg but which nonetheless have repoze.bfg in their names (e.g. repoze.bfg.skins, repoze.bfg.traversalwrapper, repoze.bfg.jinja2), you will need to find an analogue for each. For example, by the time you read this, there will be a pyramid_jinja2 package, which can be used instead of repoze.bfg.jinja2. If an analogue does not seem to exist for a repoze.bfg add-on package that your application uses, please email the Pylons-devel maillist; we'll convert the package to a Pyramid analogue for you.

Here's how to convert a repoze.bfg application to a Pyramid application:

1. Ensure that your application works under repoze.bfg version 1.3 or better. See http://docs.repoze.org/bfg/1.3/narr/install.html for repoze.bfg 1.3 installation instructions. If your application has an automated test suite, run it while your application is using repoze.bfg 1.3+. Otherwise, test it manually. It is only safe to proceed to the next step once your application works under repoze.bfg 1.3+.

If your application has a proper set of dependencies, and a standard automated test suite, you might test your repoze.bfg application against repoze.bfg 1.3 like so:

33. CONVERTING A REPOZE.BFG APPLICATION TO PYRAMID

\$ bfgenv/bin/python setup.py test

bfgenv above will be the virtualenv into which you've installed repoze.bfg 1.3.

2. Install Pyramid into a *separate* virtualenv as per the instructions in *Installing Pyramid*. The Pyramid virtualenv should be separate from the one you've used to install repoze.bfg. A quick way to do this:

```
$ cd ~
$ virtualenv --no-site-packages pyramidenv
$ cd pyramidenv
$ bin/easy_install pyramid
```

3. Put a *copy* of your repoze.bfg application into a temporary location (perhaps by checking a fresh copy of the application out of a version control repository). For example:

```
$ cd /tmp
$ svn co http://my.server/my/bfg/application/trunk bfgapp
```

4. Use the bfg2pyramid script present in the bin directory of the Pyramid virtualenv to convert all repoze.bfg Python import statements into compatible Pyramid import statements. bfg2pyramid will also fix ZCML directive usages of common repoze.bfg directives. You invoke bfg2pyramid by passing it the *path* of the copy of your application. The path passed should contain a "setup.py" file, representing your repoze.bfg application's setup script. bfg2pyramid will change the copy of the application in place.

\$ ~/pyramidenv/bfg2pyramid /tmp/bfgapp

bfg2pyramid will convert the following repoze.bfg application aspects to Pyramid compatible analogues:

- Python import statements naming repoze.bfg APIs will be converted to Pyramid compatible import statements. Every Python file beneath the top-level path will be visited and converted recursively, except Python files which live in directories which start with a . (dot).
- Each ZCML file found (recursively) within the path will have the default xmlns attribute attached to the configure tag changed from http://namespaces.repoze.org/bfg to http://pylonshq.com/pyramid. Every ZCML file beneath the top-level path (files ending with .zcml) will be visited and converted recursively, except ZCML files which live in directories which start with a . (dot).

- ZCML files which contain directives that have attributes which name API API a repoze.bfg module or attribute of an module (e.g. context="repoze.bfg.exceptions.NotFound") will be converted to Pyramid compatible ZCML attributes (e.g. context="pyramid.exceptions.NotFound). Every ZCML file beneath the top-level path (files ending with .zcml) will be visited and converted recursively, except ZCML files which live in directories which start with a . (dot).
- 5. Edit the setup.py file of the application you've just converted (if you've been using the example paths, this will be /tmp/bfgapp/setup.py) to depend on the pyramid distribution instead the of repoze.bfg distribution in its install_requires list. If you used a scaffold to create the repoze.bfg application, you can do so by changing the requires line near the top of the setup.py file. The original may look like this:

requires = ['repoze.bfg', ... other dependencies ...]

Edit the setup.py so it has:

requires = ['pyramid', ... other dependencies ...]

All other install-requires and tests-requires dependencies save for the one on repoze.bfg can remain the same.

- 6. Convert any install_requires dependencies your application has on other add-on packages which have repoze.bfg in their names to Pyramid compatible analogues (e.g. repoze.bfg.jinja2 should be replaced with pyramid_jinja2). You may need to adjust configuration options and/or imports in your repoze.bfg application after replacing these add-ons. Read the documentation of the Pyramid add-on package for information.
- 7. Only if you use ZCML and add-ons which use ZCML: The default xmlns of the configure tag in ZCML has changed. The bfg2pyramid script effects the default namespace change (it changes the configure tag default xmlns from http://namespaces.repoze.org/bfg to http://pylonshq.com/pyramid).

This means that uses of add-ons which define ZCML directives in the http://namespaces.repoze.org/bfg namespace will begin to "fail" (they're actually not really failing, but your ZCML assumes that they will always be used within a configure tag which names the http://namespaces.repoze.org/bfg Symptom: when you attempt to start the applinamespace as its default xmlns). cation. an error such as ConfigurationError: ('Unknown directive', u'http://namespaces.repoze.org/bfg', u'workflow') printed is to the console and the application fails to start. In such a case, either add an xmlns="http://namespaces.repoze.org/bfg" attribute to each tag which causes a failure, or define a namespace alias in the configure tag and prefix each failing tag. For example, change this "failing" tag instance:

```
<configure xmlns="http://pylonshq.com/pyramid">
<failingtag attr="foo"/>
</configure>
```

To this, which will begin to succeed:

You will also need to add the pyramid_zcml package to your setup.py install_requires list. In Pyramid, ZCML configuration became an optional add-on supported by the pyramid_zcml package.

8. Retest your application using Pyramid. This might be as easy as:

```
$ cd /tmp/bfgapp
$ ~/pyramidenv/bin/python setup.py test
```

9. Fix any test failures.

10. Fix any code which generates deprecation warnings.

11. Start using the converted version of your application. Celebrate.

Two terminological changes have been made to Pyramid which make its documentation and newer APIs different than those of repoze.bfg. The concept that BFG called model is called resource in Pyramid and the concept that BFG called resource is called asset in Pyramid. Various APIs have changed as a result (although all have backwards compatible shims). Additionally, the environment variables that influenced server behavior which used to be prefixed with BFG_ (such as BFG_DEBUG_NOTFOUND) must now be prefixed with PYRAMID_.

CHAPTER

THIRTYFOUR

RUNNING PYRAMID ON GOOGLE'S APP ENGINE

It is possible to run a Pyramid application on Google's App Engine. Content from this tutorial was contributed by YoungKing, based on the "appengine-monkey" tutorial for Pylons. This tutorial is written in terms of using the command line on a UNIX system; it should be possible to perform similar actions on a Windows system.

- 1. Download Google's App Engine SDK and install it on your system.
- 2. Use Subversion to check out the source code for appengine-monkey.

3. Use appengine_homedir.py script in appengine-monkey to create a *virtualenv* for your application.

```
$ export GAE_PATH=/usr/local/google_appengine
$ python2.5 /path/to/appengine-monkey/appengine-homedir.py --gae \
$GAE_PATH pyramidapp
```

Note that \$GAE_PATH should be the path where you have unpacked the App Engine SDK. (On Mac OS X at least, /usr/local/google_appengine is indeed where the installer puts it).

This will set up an environment in pyramidapp/, with some tools installed in pyramidapp/bin. There will also be a directory pyramidapp/app/ which is the directory you will upload to appendine.

4. Install Pyramid into the virtualenv

34. RUNNING PYRAMID ON GOOGLE'S APP ENGINE

```
$ cd pyramidapp/
$ bin/easy_install pyramid
```

This will install Pyramid in the environment.

5. Create your application

We'll use the standard way to create a Pyramid application, but we'll have to move some files around when we are done. The below commands assume your current working directory is the pyramidapp virtualenv directory you created in the third step above:

```
$ cd app
$ rm -rf pyramidapp
$ bin/paster create -t pyramid_starter pyramidapp
$ mv pyramidapp aside
$ mv aside/pyramidapp .
$ rm -rf aside
```

6. Edit config.py

Edit the APP_NAME and APP_ARGS settings within config.py. The APP_NAME must be pyramidapp:main, and the APP_ARGS must be ({},). Any other settings in config.py should remain the same.

```
APP_NAME = 'pyramidapp:main'
APP_ARGS = ({},)
```

7. Edit runner.py

To prevent errors for import site, add this code stanza before import site in app/runner.py:

```
import sys
sys.path = [path for path in sys.path if 'site-packages' not in path]
import site
```

You will also need to comment out the line that starts with assert sys.path in the file.

```
# comment the sys.path assertion out
# assert sys.path[:len(cur_sys_path)] == cur_sys_path, (
# "addsitedir() caused entries to be prepended to sys.path")
```

For GAE development environment 1.3.0 or better, you will also need the following somewhere near the top of the runner.py file to fix a compatibility issue with appengine-monkey:

```
import os
os.mkdir = None
```

8. Run the application. dev_appserver.py is typically installed by the SDK in the global path but you need to be sure to run it with Python 2.5 (or whatever version of Python your GAE SDK expects).

```
1 $ cd ../..
2 $ python2.5 /usr/local/bin/dev_appserver.py pyramidapp/app/
```

Startup success looks something like this:

You may need to run "Make Symlinks" from the Google App Engine Launcher GUI application if your system doesn't already have the dev_appserver.py script sitting around somewhere.

9. Hack on your pyramid application, using a normal run, debug, restart process. For tips on how to use the pdb module within Google App Engine, see this blog post. In particular, you can create a function like so and call it to drop your console into a pdb trace:

```
1 def set_trace():
2     import pdb, sys
3     debugger = pdb.Pdb(stdin=sys.__stdin__,
4         stdout=sys.__stdout__)
5     debugger.set_trace(sys._getframe().f_back)
```

- 10. Sign up for a GAE account and create an application. You'll need a mobile phone to accept an SMS in order to receive authorization.
- 11. Edit the application's ID in app.yaml to match the application name you created during GAE account setup.

34. RUNNING PYRAMID ON GOOGLE'S APP ENGINE

application: mycoolpyramidapp

12. Upload the application

\$ python2.5 /usr/local/bin/appcfg.py update pyramidapp/app

You almost certainly won't hit the 3000-file GAE file number limit when invoking this command. If you do, however, it will look like so:

```
HTTPError: HTTP Error 400: Bad Request
Rolling back the update.
Error 400: --- begin server output ---
Max number of files and blobs is 3000.
--- end server output ---
```

If you do experience this error, you will be able to get around this by zipping libraries. You can use pip to create zipfiles from packages. See *Zipping Files Via Pip* for more information about this.

A successful upload looks like so:

13. Visit http://<yourapp>.appspot.com in a browser.

34.1 Zipping Files Via Pip

If you hit the Google App Engine 3000-file limit, you may need to create zipfile archives out of some distributions installed in your application's virtualenv.

First, see which packages are available for zipping:

\$ bin/pip zip -l

This shows your zipped packages (by default, none) and your unzipped packages. You can zip a package like so:

```
$ bin/pip zip pytz-2009g-py2.5.egg
```

Note that it requires the whole egg file name. For a Pyramid app, the following packages are good candidates to be zipped.

- Chameleon
- zope.i18n

Once the zipping procedure is finished you can try uploading again.

34. RUNNING PYRAMID ON GOOGLE'S APP ENGINE

CHAPTER

THIRTYFIVE

RUNNING A PYRAMID APPLICATION UNDER MOD_WSGI

mod_wsgi is an Apache module developed by Graham Dumpleton. It allows *WSGI* programs to be served using the Apache web server.

This guide will outline broad steps that can be used to get a Pyramid application running under Apache via mod_wsgi. This particular tutorial was developed under Apple's Mac OS X platform (Snow Leopard, on a 32-bit Mac), but the instructions should be largely the same for all systems, delta specific path information for commands and files.

Unfortunately these instructions almost certainly won't work for deploying a Pyramid application on a Windows system using mod_wsgi. If you have experience with Pyramid and mod_wsgi on Windows systems, please help us document this experience by submitting documentation to the Pylons-devel maillist.

- 1. The tutorial assumes you have Apache already installed on your system. If you do not, install Apache 2.X for your platform in whatever manner makes sense.
- 2. Once you have Apache installed, install mod_wsgi. Use the (excellent) installation instructions for your platform into your system's Apache installation.
- 3. Install *virtualenv* into the Python which mod_wsgi will run using the <code>easy_install</code> program.

\$ sudo /usr/bin/easy_install-2.6 virtualenv

This command may need to be performed as the root user.

4. Create a *virtualenv* which we'll use to install our application.

```
$ cd ~
$ mkdir modwsgi
$ cd modwsgi
$ /usr/local/bin/virtualenv --no-site-packages env
```

5. Install Pyramid into the newly created virtualenv:

```
$ cd ~/modwsgi/env
$ bin/easy_install pyramid
```

6. Create and install your Pyramid application. For the purposes of this tutorial, we'll just be using the pyramid_starter application as a baseline application. Substitute your existing Pyramid application as necessary if you already have one.

```
$ cd ~/modwsgi/env
$ bin/paster create -t pyramid_starter myapp
$ cd myapp
$ ../bin/python setup.py install
```

7. Within the virtualenv directory (~/modwsgi/env), create a script named pyramid.wsgi. Give it these contents:

```
from pyramid.paster import get_app
application = get_app(
    '/Users/chrism/modwsgi/env/myapp/production.ini', 'main')
```

The first argument to get_app is the project Paste configuration file name. It's best to use the production.ini file provided by your scaffold, as it contains settings appropriate for production. The second is the name of the section within the .ini file that should be loaded by mod_wsgi. The assignment to the name application is important: mod_wsgi requires finding such an assignment when it opens the file.

8. Make the pyramid.wsgi script executable.

```
$ cd ~/modwsgi/env
$ chmod 755 pyramid.wsgi
```

9. Edit your Apache configuration and add some stuff. I happened to create a file named /etc/apache2/other/modwsgi.conf on my own system while installing Apache, so this stuff went in there.

```
# Use only 1 Python sub-interpreter. Multiple sub-interpreters
# play badly with C extensions.
WSGIApplicationGroup %{GLOBAL}
WSGIPassAuthorization On
WSGIDaemonProcess pyramid user=chrism group=staff threads=4 \
    python-path=/Users/chrism/modwsgi/env/lib/python2.6/site-packages
WSGIScriptAlias /myapp /Users/chrism/modwsgi/env/pyramid.wsgi
<Directory /Users/chrism/modwsgi/env>
WSGIProcessGroup pyramid
Order allow,deny
Allow from all
</Directory>
```

10. Restart Apache

```
$ sudo /usr/sbin/apachectl restart
```

11. Visit http://localhost/myapp in a browser. You should see the sample application rendered in your browser.

mod_wsgi has many knobs and a great variety of deployment modes. This is just one representation of how you might use it to serve up a Pyramid application. See the mod_wsgi configuration documentation for more in-depth configuration information.

Part III

API Reference

CHAPTER

THIRTYSIX

PYRAMID.AUTHORIZATION

class ACLAuthorizationPolicy

An *authorization policy* which consults an *ACL* object attached to a *context* to determine authorization information about a *principal* or multiple principals. If the context is part of a *lineage*, the context's parents are consulted for ACL information too. The following is true about this security policy.

•When checking whether the 'current' user is permitted (via the permits method), the security policy consults the context for an ACL first. If no ACL exists on the context, or one does exist but the ACL does not explicitly allow or deny access for any of the effective principals, consult the context's parent ACL, and so on, until the lineage is exhausted or we determine that the policy permits or denies.

During this processing, if any pyramid.security.Deny ACE is found matching any principal in principals, stop processing by returning an pyramid.security.ACLDenied instance (equals False) immediately. If any pyramid.security.Allow ACE is found matching any principal, stop processing by returning an pyramid.security.ACLAllowed instance (equals True) immediately. If we exhaust the context's *lineage*, and no ACE has explicitly permitted or denied access, return an instance of pyramid.security.ACLDenied (equals False).

•When computing principals allowed permission via the by а pyramid.security.principals_allowed_by_permission() method. we compute the set of principals that are explicitly granted the permission in the provided context. We do this by walking 'up' the object graph from the root to the context. During this walking process, if we find an explicit pyramid.security.Allow ACE for a principal that matches the permission, the principal is included in the allow list. However, if later in the walking process that principal is mentioned in any pyramid.security.Deny ACE for the permission, the principal is removed from the allow list. If a pyramid.security.Deny to the principal pyramid.security.Everyone is encountered during the walking process that matches the permission, the allow list is cleared for all principals encountered in previous ACLs. The walking process ends after we've processed the any ACL directly attached to context; a set of principals is returned.

Objects of this class implement the pyramid.interfaces.IAuthorizationPolicy interface.

CHAPTER

THIRTYSEVEN

PYRAMID.AUTHENTICATION

37.1 Authentication Policies

Constructor Arguments

secret

The secret (a string) used for auth_tkt cookie signing. Required.

callback

Default: None. A callback passed the userid and the request, expected to return None if the userid doesn't exist or a sequence of principal identifiers (possibly empty) if the user does exist. If callback is None, the userid will be assumed to exist with no principals. Optional.

cookie_name

Default: auth_tkt. The cookie name used (string). Optional.

secure

Default: False. Only send the cookie back over a secure conn. Optional.

include_ip

Default: False. Make the requesting IP address part of the authentication data in the cookie. Optional.

timeout

Default: None. Maximum number of seconds which a newly issued ticket will be considered valid. After this amount of time, the ticket will expire (effectively logging the user out). If this value is None, the ticket never expires. Optional.

reissue_time

Default: None. If this parameter is set, it represents the number of seconds that must pass before an authentication token cookie is automatically reissued as the result of a request which requires authentication. The duration is measured as the number of seconds since the last auth_tkt cookie was issued and 'now'. If this value is 0, a new ticket cookie will be reissued on every request which requires authentication.

A good rule of thumb: if you want auto-expired cookies based on inactivity: set the timeout value to 1200 (20 mins) and set the reissue_time value to perhaps a tenth of the timeout value (120 or 2 mins). It's nonsensical to set the timeout value lower than the reissue_time value, as the ticket will never be reissued if so. However, such a configuration is not explicitly prevented.

Optional.

```
max_age
```

Default: None. The max age of the auth_tkt cookie, in seconds. This differs from timeout inasmuch as timeout represents the lifetime of the ticket contained in the cookie, while this value represents the lifetime of the cookie itself. When this value is set, the cookie's Max-Age and Expires settings will be set, allowing the auth_tkt cookie to last between browser sessions. It is typically nonsensical to set this to a value that is lower than timeout or reissue_time, although it is not explicitly prevented. Optional.

path

Default: /. The path for which the auth_tkt cookie is valid. May be desirable if the application only serves part of a domain. Optional.

http_only

Default: False. Hide cookie from JavaScript by setting the HttpOnly flag. Not honored by all browsers. Optional.

wild_domain

Default: True. An auth_tkt cookie will be generated for the wildcard domain. Optional.

Objects of this class implement the interface described by pyramid.interfaces.IAuthenticationPolicy.

class RepozeWholAuthenticationPolicy (identifier_name='auth_tkt', callback=None)
A Pyramid authentication policy which obtains data from the repoze.who 1.X WSGI 'API' (the
repoze.who.identity key in the WSGI environment).

Constructor Arguments

identifier_name

Default: auth_tkt. The repoze.who plugin name that performs remember/forget. Optional.

callback

Default: None. A callback passed the repoze.who identity and the *request*, expected to return None if the user represented by the identity doesn't exist or a sequence of principal identifiers (possibly empty) representing groups if the user does exist. If callback is None, the userid will be assumed to exist with no group principals.

Objects of this class implement the interface described by pyramid.interfaces.IAuthenticationPolicy.

class RemoteUserAuthenticationPolicy (environ_key='REMOTE_USER', call-

back=None)

A Pyramid *authentication policy* which obtains data from the REMOTE_USER WSGI environment variable.

Constructor Arguments

environ_key

Default: REMOTE_USER. The key in the WSGI environ which provides the userid.

callback

Default: None. A callback passed the userid and the request, expected to return None if the userid doesn't exist or a sequence of principal identifiers (possibly empty) representing groups if the user does exist. If callback is None, the userid will be assumed to exist with no group principals.

Objects of this class implement the interface described by pyramid.interfaces.IAuthenticationPolicy.

class SessionAuthenticationPolicy (prefix='auth.', callback=None)

A Pyramid authentication policy which gets its data from the configured *session*. For this authentication policy to work, you will have to follow the instructions in the *Sessions* to configure a *session factory*.

Constructor Arguments

prefix

A prefix used when storing the authentication parameters in the session. Defaults to 'auth.'. Optional.

callback

Default: None. A callback passed the userid and the request, expected to return None if the userid doesn't exist or a sequence of principal identifiers (possibly empty) if the user does exist. If callback is None, the userid will be assumed to exist with no principals. Optional.

37.2 Helper Classes

class AuthTktCookieHelper (secret,			cookie_name='auth_tkt', se		
	6	cure=False,	include_ip	=False,	time-
	6	out=None, r	eissue_time=Nor	ne, max <u></u>	_age=None,
	http_only=False, path='/', wild_domain=True)				
A helper class for	use in	third-party	authentication	policy	implementatio

A helper class for use in third-party authentication policy implementations. See pyramid.authentication.AuthTktAuthenticationPolicy for the meanings of the constructor arguments.

forget (request)

Return a set of expires Set-Cookie headers, which will destroy any existing auth_tkt cookie when attached to a response

identify(request)

Return a dictionary with authentication information, or None if no valid auth_tkt is attached to request

remember (request, userid, max_age=None, tokens=())

Return a set of Set-Cookie headers; when set into a response, these headers will represent a valid authentication ticket.

- max_age The max age of the auth_tkt cookie, in seconds. When this value is set, the cookie's Max-Age and Expires settings will be set, allowing the auth_tkt cookie to last between browser sessions. If this value is None, the max_age value provided to the helper itself will be used as the max_age value. Default: None.
- **tokens** A sequence of strings that will be placed into the auth_tkt tokens field. Each string in the sequence must be of the Python str type and must match the regex ^ [A-Za-z] [A-Za-z0-9+_-] *\$. Tokens are available in the returned identity when an auth_tkt is found in the request and unpacked. Default: ().

CHAPTER

THIRTYEIGHT

PYRAMID.CHAMELEON_TEXT

get_template (path)

Return the underyling object representing a *Chameleon* text template using the template implied by the path argument. The path argument may be a package-relative path, an absolute path, or a *asset specification*.

This API is deprecated in Pyramid 1.0. Use the implementation() method of a template renderer retrieved via pyramid.renderers.get_renderer() instead.

render_template (path, **kw)

Render a *Chameleon* text template using the template implied by the path argument. The path argument may be a package-relative path, an absolute path, or a *asset specification*. The arguments in $\star kw$ are passed as top-level names to the template, and so may be used within the template itself. Returns a string.

This API is deprecated in Pyramid 1.0. Use pyramid.renderers.render() instead.

render_template_to_response (path, **kw)

Render a *Chameleon* text template using the template implied by the path argument. The path argument may be a package-relative path, an absolute path, or a *asset specification*. The arguments in $\star kw$ are passed as top-level names to the template, and so may be used within the template itself. Returns a *Response* object with the body as the template result.

This API is deprecated in Pyramid 1.0. Use pyramid.renderers.render_to_response() instead.

These APIs will will work against template files which contain simple \${Genshi} - style replacement markers.

The API of pyramid.chameleon_text is identical to that of pyramid.chameleon_zpt; only its import location is different. If you need to import an API functions from this module as well as the pyramid.chameleon_zpt module within the same view file, use the as feature of the Python import statement, e.g.:

```
1 from pyramid.chameleon_zpt import render_template as zpt_render
2 from pyramid.chameleon_text import render_template as text_render
```

CHAPTER

THIRTYNINE

PYRAMID.CHAMELEON_ZPT

get_template(path)

Return the underyling object representing a *Chameleon* ZPT template using the template implied by the path argument. The path argument may be a package-relative path, an absolute path, or a *asset specification*.

This API is deprecated in Pyramid 1.0. Use the implementation() method of a template renderer retrieved via pyramid.renderers.get_renderer() instead.

render_template(path, **kw)

Render a *Chameleon* ZPT template using the template implied by the path argument. The path argument may be a package-relative path, an absolute path, or a *asset specification*. The arguments in $\star kw$ are passed as top-level names to the template, and so may be used within the template itself. Returns a string.

This API is deprecated in Pyramid 1.0. Use pyramid.renderers.render() instead.

render_template_to_response (path, **kw)

Render a *Chameleon* ZPT template using the template implied by the path argument. The path argument may be a package-relative path, an absolute path, or a *asset specification*. The arguments in $\star kw$ are passed as top-level names to the template, and so may be used within the template itself. Returns a *Response* object with the body as the template result.

This API is deprecated in Pyramid 1.0. Use pyramid.renderers.render_to_response() instead.

39. PYRAMID.CHAMELEON_ZPT

These APIs will work against files which supply template text which matches the ZPT specification.

The API of pyramid.chameleon_zpt is identical to that of pyramid.chameleon_text; only its import location is different. If you need to import an API functions from this module as well as the pyramid.chameleon_text module within the same view file, use the as feature of the Python import statement, e.g.:

1 from pyramid.chameleon_zpt import render_template as zpt_render
2 from pyramid.chameleon_text import render_template as text_render

CHAPTER

FORTY

PYRAMID.CONFIG

class Configurator (registry=None, package=None, settings=None, root_factory=None, authentication_policy=None, authorization_policy=None, renderers=DEFAULT_RENDERERS, debug_logger=None, locale_negotiator=None, request_factory=None, renderer_globals_factory=None, default_permission=None, session_factory=None, autocommit=False) A Configurator is used to configure a Pyramid application registry.

The Configurator accepts a number of arguments: registry, package, settings, root_factory, authentication_policy, authorization_policy, renderers debug_logger, locale_negotiator, request_factory, renderer_globals_factory, default_permission, session_factory, default_view_mapper, autocommit, and exceptionresponse_view.

If the registry argument is passed as a non-None value, it must be an instance of the pyramid.registry.Registry class representing the registry to configure. If registry is None, the configurator will create a pyramid.registry.Registry instance itself; it will also perform some default configuration that would not otherwise be done. After construction, the configurator may be used to add configuration to the registry. The overall state of a registry is called the 'configuration state'.

If a registry is passed to the Configurator constructor, all other constructor arguments except package are ignored.

If the package argument is passed, it must be a reference to a Python *package* (e.g. sys.modules['thepackage']) or a *dotted Python name* to same. This value is used as a

basis to convert relative paths passed to various configuration methods, such as methods which accept a renderer argument, into absolute paths. If None is passed (the default), the package is assumed to be the Python package in which the *caller* of the Configurator constructor lives.

If the settings argument is passed, it should be a Python dictionary representing the deployment settings for this application. These are later retrievable using the pyramid.registry.Registry.settings attribute (aka request.registry.settings).

If the root_factory argument is passed, it should be an object representing the default *root factory* for your application or a *dotted Python name* to same. If it is None, a default root factory will be used.

If authentication_policy is passed, it should be an instance of an *authentication policy* or a *dotted Python name* to same.

If authorization_policy is passed, it should be an instance of an *authorization policy* or a *dotted Python name* to same.

• A ConfigurationError will be raised when an authorization policy is supplied without also supplying an authentication policy (authorization requires authentication).

If renderers is passed, it should be a list of tuples representing a set of *renderer* factories which should be configured into this application (each tuple representing a set of positional values that should be passed to pyramid.config.Configurator.add_renderer()). If it is not passed, a default set of renderer factories is used.

If debug_logger is not passed, a default debug logger that logs to stderr will be used. If it is passed, it should be an instance of the logging.Logger (PEP 282) standard library class or a *dotted Python name* to same. The debug logger is used by Pyramid itself to log warnings and authorization debugging information.

If locale_negotiator is passed, it should be a *locale negotiator* implementation or a *dotted Python name* to same. See *Using a Custom Locale Negotiator*.

If request_factory is passed, it should be a *request factory* implementation or a *dotted Python name* to same. See *Changing the Request Factory*. By default it is None, which means use the default request factory.

If renderer_globals_factory is passed, it should be a *renderer globals* factory implementation or a *dotted Python name* to same. See *Adding Renderer Globals (Deprecated)*. By default, it is None, which means use no renderer globals factory. as of Pyramid 1.1, renderer_globals_factory is deprecated. Instead, use a BeforeRender event subscriber as per *Using The Before Render Event*.

If default_permission is passed, it should be a *permission* string to be used as the default permission for all view configuration registrations performed against this Configurator. An example of a permission string: 'view'. Adding a default permission makes it unnecessary to protect each view configuration with an explicit permission, unless your application policy requires some exception for a particular view. By default, default_permission is None, meaning that view configurations which do not explicitly declare a permission will always be executable by entirely anonymous users (any authorization policy in effect is ignored). See also *Setting a Default Permission*.

If session_factory is passed, it should be an object which implements the *session factory* interface. If a nondefault value is passed, the session_factory will be used to create a session object when request.session is accessed. Note that the same outcome can be achieved by calling pyramid.config.Configurator.set_session_factory(). By default, this argument is None, indicating that no session factory will be configured (and thus accessing request.session will throw an error) unless set_session_factory is called later during configuration.

If autocommit is True, every method called on the configurator will cause an immediate action, and no configuration conflict detection will be used. If autocommit is False, most methods of the configurator will defer their action until pyramid.config.Configurator.commit() is called. When pyramid.config.Configurator.commit() is called, the actions implied by the called methods will be checked for configuration conflicts unless autocommit is True. If a conflict is detected a Configurator.make_wsgi_app() always implies a final commit.

If default_view_mapper is passed, it will be used as the default view mapper factory for view configurations that don't otherwise specify one (see pyramid.interfaces.IViewMapperFactory). If a default_view_mapper is not passed, a superdefault view mapper will be used.

If exceptionresponse_view is passed, it must be a view callable or None. If it is a view callable, it will be used as an exception view callable when an *exception response* is raised. If exceptionresponse_view is None, no exception response view will be registered, and all raised exception responses will be bubbled up to Pyramid's caller. By default, the pyramid.httpexceptions.default_exceptionresponse_view function is used as the exceptionresponse_view. This argument is new in Pyramid 1.1.

registry

The application registry which holds the configuration associated with this configurator.

begin (request=None)

Indicate that application or test configuration has begun. This pushes a dictionary containing the *application registry* implied by registry attribute of this configurator and the *request* implied by the request argument on to the *thread local* stack consulted by various pyramid.threadlocal API functions.

end()

Indicate that application or test configuration has ended. This pops the last value pushed on to the *thread local* stack (usually by the begin method) and returns that value.

hook_zca()

Call zope.component.getSiteManager.sethook() with the argument pyramid.threadlocal.get_current_registry, causing the Zope Component Architecture 'global' APIs such as zope.component.getSiteManager(), zope.component.getAdapter() and others to use the Pyramid application registry rather than the Zope 'global' registry. If zope.component cannot be imported, this method will raise an ImportError.

$unhook_zca()$

Call zope.component.getSiteManager.reset() to undo the action of pyramid.config.Configurator.hook_zca(). If zope.component cannot be imported, this method will raise an ImportError.

get_settings()

Return a *deployment settings* object for the current application. A deployment settings object is a dictionary-like object that contains key/value pairs based on the dictionary passed as the settings argument to the pyramid.config.Configurator constructor or the pyramid.router.make_app() API.

• For backwards compatibility, dictionary keys can also be looked up as attributes of the settings object.

the pyramid.registry.Registry.settings API performs the same duty.

commit()

Commit any pending configuration actions. If a configuration conflict is detected in the pending configuration actins, this method will raise a ConfigurationConflictError; within the traceback of this error will be information about the source of the conflict, usually including file names and line numbers of the cause of the configuration conflicts.

action (discriminator, callable=None, args=(), kw=None, order=0)

Register an action which will be executed when pyramid.config.Configuration.commit() is called (or executed immediately if autocommit is True).

This method is typically only used by Pyramid framework extension authors, not by Pyramid application developers.

The discriminator uniquely identifies the action. It must be given, but it can be None, to indicate that the action never conflicts. It must be a hashable value.

The callable is a callable object which performs the action. It is optional. args and kw are tuple and dict objects respectively, which are passed to callable when this action is executed.

order is a crude order control mechanism, only rarely used (has no effect when autocommit is True).

include (*callables)

Include one or more configuration callables, to support imperative application extensibility.

A configuration callable should be a callable that accepts a single argument named config, which will be an instance of a *Configurator* (be warned that it will not be the same configurator instance on which you call this method, however). The code which runs as the result of calling the callable should invoke methods on the configurator passed to it which add configuration state. The return value of a callable will be ignored.

Values allowed to be presented via the *callables argument to this method: any callable Python object or any *dotted Python name* which resolves to a callable Python object. It may also be a Python *module*, in which case, the module will be searched for a callable named includeme, which will be treated as the configuration callable.

For example, if the includeme function below lives in a module named myapp.myconfig:

```
1 # myapp.myconfig module
2
3 def my_view(request):
4 from pyramid.response import Response
5 return Response('OK')
6
7 def includeme(config):
8 config.add_view(my_view)
```

You might cause it be included within your Pyramid application like so:

```
from pyramid.config import Configurator
def main(global_config, **settings):
    config = Configurator()
    config.include('myapp.myconfig.includeme')
```

Because the function is named includeme, the function name can also be omitted from the dotted name reference:

```
from pyramid.config import Configurator
def main(global_config, **settings):
    config = Configurator()
    config.include('myapp.myconfig')
```

Included configuration statements will be overridden by local configuration statements if an included callable causes a configuration conflict by registering something with the same configuration parameters.

add_directive (*name*, *directive*, *action_wrap=True*) Add a directive method to the configurator.

This method is typically only used by Pyramid framework extension authors, not by Pyramid application developers.

Framework extenders can add directive methods to a configurator by instructing their users to call config.add_directive('somename', 'some.callable'). This will make some.callable accessible as config.somename.some.callable should be a function which accepts config as a first argument, and arbitrary positional and keyword arguments following. It should use config.action as necessary to perform actions. Directive methods can then be invoked like 'built-in' directives such as add_view, add_route, etc.

The action_wrap argument should be True for directives which perform config.action with potentially conflicting discriminators. action_wrap will cause the directive to be wrapped in a decorator which provides more accurate conflict cause information.

add_directive does not participate in conflict detection, and later calls to add_directive will override earlier calls.

with_package (package)

Return a new Configurator instance with the same registry as this configurator using the package supplied as the package argument to the new configurator. package may be an actual Python package object or a Python dotted name representing a package.

maybe_dotted(dotted)

Resolve the *dotted Python name* dotted to a global Python object. If dotted is not a string, return it without attempting to do any name resolution. If dotted is a relative dotted name (e.g. .foo.bar, consider it relative to the package argument supplied to this Configurator's constructor.

absolute_asset_spec(relative_spec)

Resolve the potentially relative *asset specification* string passed as relative_spec into an absolute asset specification string and return the string. Use the package of this configurator as the package to which the asset specification will be considered relative when generating an absolute asset specification. If the provided relative_spec argument is already absolute, or if the relative_spec is not a string, it is simply returned.

When you pass a non-None registry argument to the *Configurator* constructor, no initial 'setup' is performed against the registry. This is because the registry you pass in may have already been initialized for use under Pyramid via a different configurator. However, in some circumstances (such as when you want to use the Zope 'global' registry instead of a registry created as a result of the Configurator constructor), or when you want to reset the initial setup of a registry, you *do* want to explicitly initialize the registry associated with a Configurator for use under Pyramid. Use setup_registry to do this initialization.

setup_registry configures settings, a root factory, security policies, renderers, a debug logger, a locale negotiator, and various other settings using the configurator's current registry, as per the descriptions in the Configurator constructor.

add_renderer (name, factory)

Add a Pyramid *renderer* factory to the current configuration state.

The name argument is the renderer name. Use None to represent the default renderer (a renderer which will be used for all views unless they name another renderer specifically).

The factory argument is Python reference to an implementation of a *renderer* factory or a *dotted Python name* to same.

Note that this function must be called *before* any add_view invocation that names the renderer name as an argument. As a result, it's usually a better idea to pass globally used renderers into the Configurator constructor in the sequence of renderers passed as renderer than it is to use this method.

add_response_adapter (adapter, type_or_iface)

When an object of type (or interface) type_or_iface is returned from a view callable, Pyramid will use the adapter adapter to convert it into an object which implements the pyramid.interfaces.IResponse interface. If adapter is None, an object returned of type (or interface) type_or_iface will itself be used as a response object.

adapter and type_or_interface may be Python objects or strings representing dotted names to importable Python global objects.

See Changing How Pyramid Treats View Responses for more information.

add_route (name, pattern=None, view=None, view_for=None, permission=None, factory=None, for_=None, header=None, xhr=False, accept=None, path_info=None, request_method=None, request_param=None, traverse=None, custom_predicates=(), view_permission=None, renderer=None, view_renderer=None, view_context=None, view_attr=None, use global views=False, path=None, pregenerator=None, static=False)

Add a *route configuration* to the current configuration state, as well as possibly a *view configuration* to be used to specify a *view callable* that will be invoked when this route matches. The arguments to this method are divided into *predicate*, *non-predicate*, and *view-related* types. *Route predicate* arguments narrow the circumstances in which a route will be match a request; non-predicate arguments are informational.

Non-Predicate Arguments

name

The name of the route, e.g. myroute. This attribute is required. It must be unique among all defined routes in a given application.

factory

A Python object (often a function or a class) or a *dotted Python name* which refers to the same object that will generate a Pyramid root resource object when this route matches. For example, mypackage.resources.MyFactory. If this argument is not specified, a default root factory will be used.

traverse

If you would like to cause the *context* to be something other than the *root* object when this route matches, you can spell a traversal pattern as the traverse argument. This traversal pattern will be used as the traversal path: traversal will begin at the root object implied by this route (either the global root, or the object returned by the factory associated with this route).

The syntax of the traverse argument is the same as it is for pattern. For example, if the pattern provided to add_route is articles/{article}/edit, and the traverse argument provided to add_route is /{article}, when a request comes in that causes the route to match in such a way that the article match value is '1' (when the request URI is /articles/1/edit), the traversal path will be generated as /1. This means that the root object's __getitem__ will be called with the name 1 during the traversal phase. If the 1 object exists, it will become the *context* of the request. *Traversal* has more information about traversal.

If the traversal path contains segment marker names which are not present in the pattern argument, a runtime error will occur. The traverse pattern should not contain segment markers that do not exist in the pattern argument.

A similar combining of routing and traversal is available when a route is matched which contains a *traverse remainder marker in its pattern (see *Using *traverse In a Route Pattern*). The traverse argument to add_route allows you to associate route patterns with an arbitrary traversal path without using a a *traverse remainder marker; instead you can use other match information.

Note that the traverse argument to add_route is ignored when attached to a route that has a *traverse remainder marker in its pattern.

pregenerator

This option should be а callable object that implements the pyramid.interfaces.IRoutePregenerator interface. A pregenerator is a callable called by the pyramid.url.route url function to augment or replace the arguments it is passed when generating a URL for the route. This is a feature not often used directly by applications, it is meant to be hooked by frameworks that use Pyramid as a base.

use_global_views

When a request matches this route, and view lookup cannot find a view which has a route_name predicate argument that matches the route, try to fall back to using a view that otherwise matches the context, request, and view name (but which does not match the route_name predicate).

static

If static is True, this route will never match an incoming request; it will only be useful for URL generation. By default, static is False. See *Static Routes*.

New in Pyramid 1.1.

Predicate Arguments

pattern

The pattern of the route e.g. ideas/{idea}. This argument is required. See *Route Pattern Syntax* for information about the syntax of route patterns. If the pattern doesn't match the current URL, route matching continues.

■ For backwards compatibility purposes (as of Pyramid 1.0), a path keyword argument passed to this function will be used to represent the pattern value if the pattern argument is None. If both path and pattern are passed, pattern wins.

xhr

This value should be either True or False. If this value is specified and is True, the *request* must possess an HTTP_X_REQUESTED_WITH (aka X-Requested-With) header for this route to match. This is useful for detecting AJAX requests issued from jQuery, Prototype and other Javascript libraries. If this predicate returns False, route matching continues.

request_method

A string representing an HTTP method name, e.g. GET, POST, HEAD, DELETE, PUT. If this argument is not specified, this route will match if the request has *any* request method. If this predicate returns False, route matching continues.

path_info

This value represents a regular expression pattern that will be tested against the PATH_INFO WSGI environment variable. If the regex matches, this predicate will return True. If this predicate returns False, route matching continues.

request_param

This value can be any string. A view declaration with this argument ensures that the associated route will only match when the request has a key in the request .params dictionary (an HTTP GET or POST variable) that has a name which matches the supplied value. If the value supplied as the argument has a = sign in it, e.g. request_param="foo=123", then the key (foo) must both exist in the request .params dictionary, and the value must match the right hand side of the expression (123) for the route to "match" the current request. If this predicate returns False, route matching continues.

header

This argument represents an HTTP header name or a header name/value pair. If the argument contains a : (colon), it will be considered a name/value pair (e.g. User-Agent:Mozilla/.* or Host:localhost). If the value contains a colon, the value portion should be a regular expression. If the value does not contain a colon, the entire value will be considered to be the header name (e.g. If-Modified-Since). If the value evaluates to a header name only without a value, the header specified by the name must be present in the request for this predicate to be true. If the value evaluates to a header name/value pair, the header specified by the name must be present in the regular expression specified as the value must match the header value. Whether or not the value represents a header name or a header name/value pair, the case of the header name is not significant. If this predicate returns False, route matching continues.

accept

This value represents a match query for one or more mimetypes in the Accept HTTP request header. If this value is specified, it must be in one of the following forms: a mimetype match token in the form text/plain, a wildcard mimetype match token in the form text/* or a match-all wildcard mimetype match token in the form */*. If any of the forms matches the Accept header of the request, this predicate will be true. If this predicate returns False, route matching continues.

custom_predicates

This value should be a sequence of references to custom predicate callables. Use custom predicates when no set of predefined predicates does what you need. Custom predicates can be combined with predefined predicates as necessary. Each custom predicate callable should accept two arguments: info and request and should return either True or False after doing arbitrary evaluation of the info and/or the request. If all custom and non-custom predicate callables return True the associated route will be considered viable for a given request. If any predicate callable returns False, route matching continues. Note that the value info passed to a custom route predicate is a dictionary containing matching information; see *Custom Route Predicates* for more information about info.

View-Related Arguments

The arguments described below have been deprecated as of Pyramid 1.1. Do not use these for new development; they should only be used to support older code bases which depend upon them. Use a separate call to pyramid.config.Configurator.add_view() to associate a view with a route using the route_name argument.

view

Deprecated as of Pyramid 1.1.

A Python object or *dotted Python name* to the same object that will be used as a view callable when this route matches. e.g. mypackage.views.my_view.

view_context



A class or an *interface* or *dotted Python name* to the same object which the *context* of the view should match for the view named by the route to be used. This argument is only useful if the view attribute is used. If this attribute is not specified, the default (None) will be used.

If the view argument is not provided, this argument has no effect.

This attribute can also be spelled as for_or view_for.

view_permission

Deprecated as of Pyramid 1.1.

The permission name required to invoke the view associated with this route. e.g. edit. (see *Using Pyramid Security With URL Dispatch* for more information about permissions).

If the view attribute is not provided, this argument has no effect.

This argument can also be spelled as permission.

view_renderer

Deprecated as of Pyramid 1.1.

This is either a single string term (e.g. json) or a string implying a path or *asset specification* (e.g. templates/views.pt). If the renderer value is a single term (does not contain a dot .), the specified term will be used to look up a renderer implementation, and that renderer implementation will be used to construct a response from the view return value. If the renderer term contains a dot (.), the specified term will be used to look up the renderer implementation, which will be passed the full path. The renderer implementation will be used to construct a response from the view return value. See *Writing View Callables Which Use a Renderer* for more information.

If the view argument is not provided, this argument has no effect.

This argument can also be spelled as renderer.

view_attr

Deprecated as of Pyramid 1.1.

The view machinery defaults to using the ___call___ method of the view callable (or the function itself, if the view callable is a function) to obtain a response dictionary. The attr value allows you to vary the method attribute used to obtain the response. For example, if your view was a class, and the class has a method named index and you wanted to use this method instead of the class' ___call___ method to return the response, you'd say attr="index" in the view configuration for the view. This is most useful when the view definition is a class.

If the view argument is not provided, this argument has no effect.

add_static_view (name, path, **kw)

Add a view used to render static assets such as images and CSS files.

The name argument is a string representing an application-relative local URL prefix. It may alternately be a full URL.

The path argument is the path on disk where the static files reside. This can be an absolute path, a package-relative path, or a *asset specification*.

The cache_max_age keyword argument is input to set the Expires and Cache-Control headers for static assets served. Note that this argument has no effect when the name is a *url prefix*. By default, this argument is None, meaning that no particular Expires or Cache-Control headers are set in the response.

The permission keyword argument is used to specify the *permission* required by a user to execute the static view. By default, it is the string __no_permission_required__. The __no_permission_required__ string is a special sentinel which indicates that, even if a *default permission* exists for the current application, the static view should be renderered to completely anonymous users. This default value is permissive because, in most web apps, static assets seldom need protection from viewing. If permission is specified, the security checking will be performed against the default root factory ACL.

Any other keyword arguments sent to add_static_view are passed on to pyramid.config.Configuration.add_route() (e.g. factory, perhaps to define a custom factory with a custom ACL for this static view).

Usage

The add_static_view function is typically used in conjunction with the pyramid.url.static_url() function.add_static_view adds a view which renders a static asset when some URL is visited; pyramid.url.static_url() generates a URL to that asset.

The name argument to add_static_view is usually a *view name*. When this is the case, the pyramid.url.static_url() API will generate a URL which points to a Pyramid view, which will serve up a set of assets that live in the package itself. For example:

add_static_view('images', 'mypackage:images/')

Code that registers such a view can generate URLs to the view via pyramid.url.static_url():

static_url('mypackage:images/logo.png', request)

When add_static_view is called with a name argument that represents a URL prefix, as it is above, subsequent calls to pyramid.url.static_url() with paths that start with the path argument passed to add_static_view will generate a URL something like http://<Pyramid app URL>/images/logo.png, which will cause the logo.png file in the images subdirectory of the mypackage package to be served.

add_static_view can alternately be used with a name argument which is a *URL*, causing static assets to be served from an external webserver. This happens when the name argument is a fully qualified URL (e.g. starts with http:// or similar). In this mode, the name is used as the prefix of the full URL when generating a URL using pyramid.url.static_url(). For example, if add_static_view is called like so:

add_static_view('http://example.com/images', 'mypackage:images/')

Subsequently, the URLs generated by pyramid.url.static_url() for that static view will be prefixed with http://example.com/images:

```
static_url('mypackage:images/logo.png', request)
```

When add static view is called with that а argument name is the http://example.com/images. URL subsequent calls to pyramid.url.static_url() with paths that start with the path argument passed to add_static_view will generate a URL something like http://example.com/logo.png. The external webserver listening on example.com must be itself configured to respond properly to such a request.

See Serving Static Assets for more information.

add_settings (settings=None, **kw)

Augment the settings argument passed in to the Configurator constructor with one or more 'setting' key/value pairs. A setting is a single key/value pair in the dictionaryish object returned from the API pyramid.registry.Registry.settings and pyramid.config.Configurator.get_settings().

You may pass a dictionary:

config.add_settings({'external_uri':'http://example.com'})

Or a set of key/value pairs:

config.add_settings(external_uri='http://example.com')

This function is useful when you need test code that acto pyramid.registry.Registry.settings API cesses the (or the pyramid.config.Configurator.get_settings() API) and which uses values from that APL.

add_subscriber(subscriber, iface=None)

Add an event *subscriber* for the event stream implied by the supplied iface interface. The subscriber argument represents a callable object (or a *dotted Python name* which identifies a callable); it will be called with a single object event whenever Pyramid emits an *event* associated with the iface, which may be an *interface* or a class or a *dotted Python name* to a global object representing an interface or a class. Using the default iface value, None will cause the subscriber to be registered for all event types. See *Using Events* for more information about events and subscribers.

add_translation_dirs(*specs)

Add one or more *translation directory* paths to the current configuration state. The specs argument is a sequence that may contain absolute directory paths (e.g. /usr/share/locale) or *asset specification* names naming a directory path (e.g. some.package:locale) or a combination of the two.

Example:

Later calls to add_translation_dir insert directories into the beginning of the list of translation directories created by earlier calls. This means that the same translation found in a directory added later in the configuration process will be found before one added earlier in the configuration process. However, if multiple specs are provided in a single call to add_translation_dirs, the directories will be inserted into the beginning of the directory list in the order they're provided in the *specs list argument (items earlier in the list trump ones later in the list).

add_view (view=None, name='', for_=None, permission=None, request_type=None, route_name=None, request_method=None, request_param=None, containment=None, attr=None, renderer=None, wrapper=None, xhr=False, accept=None, header=None, path_info=None, custom_predicates=(), context=None, decorator=None, mapper=None, http cache=None)

Add a view configuration to the current configuration state. Arguments to add_view are broken down below into *predicate* arguments and *non-predicate* arguments. Predicate arguments narrow the circumstances in which the view callable will be invoked when a request is presented to Pyramid; non-predicate arguments are informational.

Non-Predicate Arguments

view

A view callable or a dotted Python name which refers to a view callable. This argument is required unless a renderer argument also exists. If a renderer argument is passed, and a view argument is not provided, the view callable defaults to a callable that returns an empty dictionary (see *Writing View Callables Which Use a Renderer*).

permission

The name of a permission that the user must possess in order to invoke the *view callable*. See Configuring View Security for more information about view security and permissions. If permission is omitted, a *default* permission may be used for this view registration if one was named as the pyramid.config.Configurator constructor's default permission argument, or if pyramid.config.Configurator.set_default_permission() prior to this view registration. Pass used the was string __no_permission_required___ as the permission argument to explicitly indicate that the view should always be executable by entirely anonymous users, regardless of the default permission, bypassing any *authorization policy* that may be in effect.

attr

The view machinery defaults to using the __call__ method of the *view callable* (or the function itself, if the view callable is a function) to obtain a response. The attr value allows you to vary the method attribute used to obtain the response. For example, if your view was a class, and the class has a method named index and you wanted to use this method instead of the class' __call__ method to return the response, you'd say attr="index" in the view configuration for the view. This is most useful when the view definition is a class.

renderer

This is either a single string term (e.g. json) or a string implying a path or *asset specification* (e.g. templates/views.pt) naming a *renderer* implementation. If the renderer value does not contain a dot ., the specified string will be used to look up a renderer implementation, and that renderer implementation will be used to construct a response from the view return value. If the renderer value contains a dot (.), the specified term will be treated as a path, and the filename extension of the last element in the path will be used to look up the renderer implementation, which will be passed the full path. The renderer implementation will be used to construct a *response* from the view return value.

Note that if the view itself returns a *response* (see *View Callable Responses*), the specified renderer implementation is never called.

When the renderer is a path, although a path is usually just a simple relative pathname (e.g. templates/foo.pt, implying that a template named "foo.pt" is in the "templates" directory relative to the directory of the current *package* of the Configurator), a path can be absolute, starting with a slash on UNIX or a drive letter prefix on Windows. The path can alternately be a *asset specification* in the form some.dotted.package_name:relative/path, making it possible to address template assets which live in a separate package.

The renderer attribute is optional. If it is not defined, the "null" renderer is assumed (no rendering is performed and the value is passed back to the upstream Pyramid machinery unmodified).

http_cache

This feature is new as of Pyramid 1.1.

When you supply an http_cache value to a view configuration, the Expires and Cache-Control headers of a response generated by the associated view callable are modified. The value for http_cache may be one of the following:

- •A nonzero integer. If it's a nonzero integer, it's treated as a number of seconds. This number of seconds will be used to compute the Expires header and the Cache-Control: max-age parameter of responses to requests which call this view. For example: http_cache=3600 instructs the requesting browser to 'cache this response for an hour, please'.
- •A datetime.timedelta instance. If it's a datetime.timedelta instance, it will be converted into a number of seconds, and that number of seconds will be used to compute the Expires header and the Cache-Control: max-age parameter of responses to requests which call this view. For example: http_cache=datetime.timedelta(days=1) instructs the requesting browser to 'cache this response for a day, please'.
- •Zero (0). If the value is zero, the Cache-Control and Expires headers present in all responses from this view will be composed such that client browser cache (and any intermediate caches) are instructed to never cache the response.
- •A two-tuple. If it's a two tuple (e.g. http_cache=(1, {'public':True})), the first value in the tuple may be a nonzero integer or a datetime.timedelta instance; in either case this value will be used as the number of seconds to cache the response. The second value in the tuple must be a dictionary. The values present in the dictionary will be used as input to the Cache-Control response header. For example: http_cache=(3600, {'public':True}) means 'cache for an hour, and add public to the Cache-Control header of the response'. All keys and values supported by the webob.cachecontrol.CacheControl interface may be added to the dictionary. Supplying {'public':True} is equivalent to calling response.cache_control.public = True.

Providing a non-tuple value as http_cache is equivalent to calling response.cache_expires(value) within your view's body.

Providing a two-tuple value as http_cache is equivalent to calling
response.cache_expires(value[0], **value[1]) within your
view's body.

If you wish to avoid influencing, the Expires header, and instead wish to only influence Cache-Control headers, pass a tuple as http_cache with the first element of None, e.g.: (None, {'public':True}).

If you wish to prevent a view that uses http_cache in its configuration from having its caching response headers changed by this machinery, set response.cache_control.prevent_auto = True before returning the response from the view. This effectively disables any HTTP caching done by http_cache for that response.

wrapper

The view name of a different view configuration which will receive the response body of this view as the request.wrapped_body attribute of its own request, and the response returned by this view as the request.wrapped_response attribute of its own request. Using a wrapper makes it possible to "chain" views together to form a composite response. The response of the outermost wrapper view will be returned to the user. The wrapper view will be found as any view is found: see View Configuration. The "best" wrapper view will be found based on the lookup ordering: "under the hood" this wrapper view is looked up via pyramid.view.render_view_to_response (context, request, 'wrapper_viewname'). The context and request of a wrapper view is the same context and request of the inner view. If this attribute is unspecified, no view wrapping is done.

decorator

A *dotted Python name* to function (or the function itself) which will be used to decorate the registered *view callable*. The decorator function will be called with the view callable as a single argument. The view callable it is passed will accept (context, request). The decorator must return a replacement view callable which also accepts (context, request).

mapper

A Python object or *dotted Python name* which refers to a *view mapper*, or None. By default it is None, which indicates that the view should use the default view mapper. This plug-point is useful for Pyramid extension developers, but it's not very useful for 'civilians' who are just developing stock Pyramid applications. Pay no attention to the man behind the curtain.

Predicate Arguments

name

The view name. Read Traversal to understand the concept of a view name.

context

An object or a *dotted Python name* referring to an interface or class object that the *context* must be an instance of, *or* the *interface* that the *context* must provide in order for this view to be found and called. This predicate is true when the *context* is an instance of the represented class or if the *context* provides the represented interface; it is otherwise false. This argument may also be provided to add_view as for_ (an older, still-supported spelling).

route_name

This value must match the name of a *route configuration* declaration (see *URL Dispatch*) that must match before this view will be called.

request_type

This value should be an *interface* that the *request* must provide in order for this view to be found and called. This value exists only for backwards compatibility purposes.

request_method

This value can be one of the strings GET, POST, PUT, DELETE, or HEAD representing an HTTP REQUEST_METHOD. A view declaration with this argument ensures that the view will only be called when the request's method attribute (aka the REQUEST_METHOD of the WSGI environment) string matches the supplied value.

request_param

This value can be any string. A view declaration with this argument ensures that the view will only be called when the *request* has a key in the request.params dictionary (an HTTP GET or POST variable) that has a name which matches the supplied value. If the value supplied has a = sign in it, e.g. request_param="foo=123", then the key (foo) must both exist in the request.params dictionary, *and* the value must match the right hand side of the expression (123) for the view to "match" the current request.

containment

This value should be a Python class or *interface* (or a *dotted Python name*) that an object in the *lineage* of the context must provide in order for this view to be found and called. The nodes in your object graph must be "location-aware" to use this feature. See *Location-Aware Resources* for more information about locationawareness.

xhr

This value should be either True or False. If this value is specified and is True, the *request* must possess an HTTP_X_REQUESTED_WITH (aka X-Requested-With) header that has the value XMLHttpRequest for this view to be found and called. This is useful for detecting AJAX requests issued from jQuery, Prototype and other Javascript libraries.

accept

The value of this argument represents a match query for one or more mimetypes in the Accept HTTP request header. If this value is specified, it must be in one of the following forms: a mimetype match token in the form text/plain, a wild-card mimetype match token in the form text/* or a match-all wildcard mimetype match token in the form \star/\star . If any of the forms matches the Accept header of the request, this predicate will be true.

header

This value represents an HTTP header name or a header name/value pair. If the value contains a : (colon), it will be considered a name/value pair (e.g. User-Agent:Mozilla/.* or Host:localhost). The value portion should be a regular expression. If the value does not contain a colon, the entire value will be considered to be the header name (e.g. If-Modified-Since). If the value evaluates to a header name only without a value, the header specified by the name must be present in the request for this predicate to be true. If the value evaluates to a header name/value pair, the header specified by the name must be present in the request *and* the regular expression specified as the value must match the header value. Whether or not the value represents a header name or a header name/value pair, the case of the header name is not significant.

path_info

This value represents a regular expression pattern that will be tested against the PATH_INFO WSGI environment variable. If the regex matches, this predicate will be True.

custom_predicates

This value should be a sequence of references to custom predicate callables. Use custom predicates when no set of predefined predicates do what you need. Custom predicates can be combined with predefined predicates as necessary. Each custom predicate callable should accept two arguments: context and request and should return either True or False after doing arbitrary evaluation of the context and/or the request. If all callables return True, the associated view callable will be considered viable for a given request.

derive_view (view, attr=None, renderer=None)

Create a *view callable* using the function, instance, or class (or *dotted Python name* referring to the same) provided as view object.

This method is typically only used by Pyramid framework extension authors, not by Pyramid application developers.

This is API is useful to framework extenders who create pluggable systems which need to register 'proxy' view callables for functions, instances, or classes which meet the requirements of being a Pyramid view callable. For example, a some_other_framework function in another framework may want to allow a user to supply a view callable, but he may want to wrap the view callable in his own before registering the wrapper as a Pyramid view callable. Because a Pyramid view callable can be any of a number of valid objects, the framework extender will not know how to call the user-supplied object. Running it through derive_view normalizes it to a callable which accepts two arguments: context and request.

For example:

```
def some_other_framework(user_supplied_view):
    config = Configurator(reg)
    proxy_view = config.derive_view(user_supplied_view)
    def my_wrapper(context, request):
        do_something_that_mutates(request)
        return proxy_view(context, request)
        config.add_view(my_wrapper)
```

The view object provided should be one of the following:

•A function or another non-class callable object that accepts a *request* as a single positional argument and which returns a *response* object.

- •A function or other non-class callable object that accepts two positional arguments, context, request and which returns a *response* object.
- •A class which accepts a single positional argument in its constructor named request, and which has a ______ method that accepts no arguments that returns a *response* object.
- •A class which accepts two positional arguments named context, request, and which has a __call__ method that accepts no arguments that returns a *response* object.
- •A dotted Python name which refers to any of the kinds of objects above.

This API returns a callable which accepts the arguments context, request and which returns the result of calling the provided view object.

The attr keyword argument is most useful when the view object is a class. It names the method that should be used as the callable. If attr is not provided, the attribute effectively defaults to ______. See *Defining a View Callable as a Class* for more information.

The renderer keyword argument should be a renderer name. If supplied, it will cause the returned callable to use a *renderer* to convert the user-supplied view result to a *response* object. If a renderer argument is not supplied, the user-supplied view must itself return a *response* object.

make_wsgi_app()

Commits any pending configuration statements, sends a pyramid.events.ApplicationCreated event to all listeners, adds this configuration's registry to pyramid.config.global_registries, and returns a Pyramid WSGI application representing the committed configuration state.

override_asset (to_override, override_with, _override=None)

Add a Pyramid asset override to the current configuration state.

to_override is a *asset specification* to the asset being overridden.

override_with is a *asset specification* to the asset that is performing the override.

See Static Assets for more information about asset overrides.

scan (package=None, categories=None, **kw)

Scan a Python package and any of its subpackages for objects marked with *configuration decoration* such as pyramid.view.view_config. Any decorated object found will influence the current configuration state.

The package argument should be a Python *package* or module object (or a *dotted Python name* which refers to such a package or module). If package is None, the package of the *caller* is used.

The categories argument, if provided, should be the *Venusian* 'scan categories' to use during scanning. Providing this argument is not often necessary; specifying scan categories is an extremely advanced usage. By default, categories is None which will execute *all* Venusian decorator callbacks including Pyramid-related decorators such as pyramid.view.view_config. See the *Venusian* documentation for more information about limiting a scan by using an explicit set of categories.

To perform a scan, Pyramid creates a Venusian Scanner object. The kw argument represents a set of keyword arguments to pass to the Venusian Scanner object's constructor. See the *venusian* documentation (its Scanner class) for more information about the constructor. By default, the only keyword arguments passed to the Scanner constructor are {'config':self} where self is this configurator object. This services the requirement of all built-in Pyramid decorators, but extension systems may require additional arguments. Providing this argument is not often necessary; it's an advanced usage.

the **kw argument is new in Pyramid 1.1

set_forbidden_view (*view=None*, *attr=None*, *renderer=None*, *wrapper=None*) Add a default forbidden view to the current configuration state.

This method has been deprecated in Pyramid 1.0. *Do not use it for new development; it should only be used to support older code bases which depend upon it.* See *Changing the Forbidden View* to see how a forbidden view should be registered in new projects.

The view argument should be a *view callable* or a *dotted Python name* which refers to a view callable.

The attr argument should be the attribute of the view callable used to retrieve the response (see the add_view method's attr argument for a description).

The renderer argument should be the name of (or path to) a *renderer* used to generate a response for this view (see the pyramid.config.Configurator.add_view() method's renderer argument for information about how a configurator relates to a renderer).

The wrapper argument should be the name of another view which will wrap this view when rendered (see the add_view method's wrapper argument for a description).

set_notfound_view (view=None, attr=None, renderer=None, wrapper=None)
Add a default not found view to the current configuration state.

This method has been deprecated in Pyramid 1.0. *Do not use it for new development; it should only be used to support older code bases which depend upon it.* See *Changing the Not Found View* to see how a not found view should be registered in new projects.

The view argument should be a *view callable* or a *dotted Python name* which refers to a view callable.

The attr argument should be the attribute of the view callable used to retrieve the response (see the add_view method's attr argument for a description).

The renderer argument should be the name of (or path to) a *renderer* used to generate a response for this view (see the pyramid.config.Configurator.add_view() method's renderer argument for information about how a configurator relates to a renderer).

The wrapper argument should be the name of another view which will wrap this view when rendered (see the add_view method's wrapper argument for a description).

set_locale_negotiator (negotiator)

Set the *locale negotiator* for this application. The *locale negotiator* is a callable which accepts a *request* object and which returns a *locale name*. The negotiator argument should be the locale negotiator implementation or a *dotted Python name* which refers to such an implementation.

Later calls to this method override earlier calls; there can be only one locale negotiator active at a time within an application. See *Activating Translation* for more information.

Using the locale_negotiator argument to the pyramid.config.Configurator constructor can be used to achieve the same purpose.

set_default_permission(permission)

Set the default permission to be used by all subsequent *view configuration* registrations. permission should be a *permission* string to be used as the default permission. An example of a permission string: 'view'. Adding a default permission makes it unnecessary to protect each view configuration with an explicit permission, unless your application policy requires some exception for a particular view.

If a default permission is *not* set, views represented by view configuration registrations which do not explicitly declare a permission will be executable by entirely anonymous users (any authorization policy is ignored).

Later calls to this method override will conflict with earlier calls; there can be only one default permission active at a time within an application.

If a default permission is in effect, view configurations meant to create a truly anonymously accessible view (even *exception view* views) *must* use the explicit permission string __no_permission_required__ as the permission. When this string is used as the permission for a view configuration, the default permission is ignored, and the view is registered, making it available to all callers regardless of their credentials.

See also Setting a Default Permission.

Using the default_permission argument to the pyramid.config.Configurator constructor can be used to achieve the same purpose.

set_session_factory(session_factory)

Configure the application with a *session factory*. If this method is called, the session_factory argument must be a session factory callable.

Using the session_factory argument to the pyramid.config.Configurator constructor can be used to achieve the same purpose.

set_request_factory(factory)

The object passed as factory should be an object (or a *dotted Python name* which refers to an object) which will be used by the Pyramid router to create all request objects. This factory

object must have the same methods and attributes as the pyramid.request.Request class (particularly __call__, and blank).

Using the request_factory argument to the pyramid.config.Configurator constructor can be used to achieve the same purpose.

set_renderer_globals_factory(factory, warn=True)

The object passed as factory should be an callable (or a *dotted Python name* which refers to an callable) that will be used by the Pyramid rendering machinery as a renderers global factory (see *Adding Renderer Globals (Deprecated)*).

The factory callable must accept a single argument named system (which will be a dictionary) and it must return a dictionary. When an application uses a renderer, the factory's return dictionary will be merged into the system dictionary, and therefore will be made available to the code which uses the renderer.

This method is deprecated as of Pyramid 1.1.

Using the renderer_globals_factory argument to the pyramid.config.Configurator constructor can be used to achieve the same purpose.

set_view_mapper(mapper)

Setting a *view mapper* makes it possible to make use of *view callable* objects which implement different call signatures than the ones supported by Pyramid as described in its narrative documentation.

The mapper should argument be an object implementing pyramid.interfaces.IViewMapperFactory or a *dotted Python name* to such an object.

The provided mapper will become the default view mapper to be used by all subsequent view *configuration* registrations, as if you had passed a default_view_mapper argument to the pyramid.config.Configurator constructor.

See also Using a View Mapper.

testing_securitypolicy (userid=None, groupids=(), permissive=True)

Unit/integration testing helper: Registers a pair of faux Pyramid security policies: a *authentication policy* and a *authorization policy*.

The behavior of the registered *authorization policy* depends on the permissive argument. If permissive is true, a permissive *authorization policy* is registered; this policy allows all access. If permissive is false, a nonpermissive *authorization policy* is registered; this policy denies all access.

The behavior of the registered *authentication policy* depends on the values provided for the userid and groupids argument. The authentication policy will return the userid identifier implied by the userid argument and the group ids implied by the groupids argument when the pyramid.security.authenticated_userid() or pyramid.security.effective_principals() APIs are used.

This function is useful when most testing code that uses the APIs pyramid.security.has permission(), named pyramid.security.authenticated_userid(),pyramid.security.effective_princip and pyramid.security.principals allowed by permission().

testing_resources (resources)

Unit/integration testing helper: registers a dictionary of *resource* objects that can be resolved via the pyramid.traversal.find_resource() API.

The pyramid.traversal.find_resource() API is called with a path as one of its arguments. If the dictionary you register when calling this method contains that path as a string key (e.g. /foo/bar or foo/bar), the corresponding value will be returned to find_resource (and thus to your code) when pyramid.traversal.find_resource() is called with an equivalent path string or tuple.

testing_add_subscriber(event_iface=None)

Unit/integration testing helper: Registers a *subscriber* which listens for events of the type event_iface. This method returns a list object which is appended to by the subscriber whenever an event is captured.

When an event is dispatched that matches the value implied by the event_iface argument, that event will be appended to the list. You can then compare the values in the list to expected event notifications. This method is useful when testing code that wants to call pyramid.registry.Registry.notify(), or zope.component.event.dispatch().

The default value of event_iface (None) implies a subscriber registered for *any* kind of event.

testing_add_renderer (path, renderer=None)

Unit/integration testing helper: register a renderer at path (usually a relative filename ala templates/foo.pt or an asset specification) and return the renderer object. If the renderer argument is None, a 'dummy' renderer will be used. This function is useful when testing code that calls the pyramid.renderers.render() function or pyramid.renderers.render_to_response() function or any other render_* or get_* API of the pyramid.renderers module.

Note that calling this method for with a path argument representing a renderer factory type (e.g. for foo.pt usually implies the chameleon_zpt renderer factory) clobbers any existing renderer factory registered for that type.

U This method is also available under the alias testing_add_template (an older name for it).

global_registries

The set of registries that have been created for Pyramid applications, one per each call to pyramid.config.Configurator.make_wsgi_app() in the current process. The object itself supports iteration and has a last property containing the last registry loaded.

The registries contained in this object are stored as weakrefs, thus they will only exist for the lifetime of the actual applications for which they are being used.

CHAPTER

FORTYONE

PYRAMID.EVENTS

41.1 Functions

subscriber(*ifaces)

Decorator activated via a *scan* which treats the function being decorated as an event subscriber for the set of interfaces passed as **ifaces* to the decorator constructor.

For example:

```
from pyramid.events import NewRequest
from pyramid.events import subscriber
@subscriber(NewRequest)
def mysubscriber(event):
    event.request.foo = 1
```

More than one event type can be passed as a construtor argument. The decorated subscriber will be called for each event type.

```
from pyramid.events import NewRequest, NewResponse
from pyramid.events import subscriber
@subscriber(NewRequest, NewResponse)
def mysubscriber(event):
    print event
```

When the subscriber decorator is used without passing an arguments, the function it decorates is called for every event sent:

```
from pyramid.events import subscriber
@subscriber()
def mysubscriber(event):
    print event
```

This method will have no effect until a *scan* is performed against the package or module which contains it, ala:

```
from pyramid.config import Configurator
config = Configurator()
config.scan('somepackage_containing_subscribers')
```

41.2 Event Types

class ApplicationCreated (app)

class is emitted when the An instance of this as an event pyramid.config.Configurator.make wsgi app() is called. The instance has an attribute, app, which is an instance of the *router* that will handle WSGI requests. This class implements the pyramid.interfaces.IApplicationCreated interface.

() For backwards compatibility purposes, this class can also be imported as pyramid.events.WSGIApplicationCreatedEvent. This was the name of the event class before Pyramid 1.0.

class NewRequest (request)

An instance of this class is emitted as an *event* whenever Pyramid begins to process a new request. The even instance has an attribute, request, which is a *request* object. This event class implements the pyramid.interfaces.INewRequest interface.

class ContextFound (request)

An instance of this class is emitted as an *event* after the Pyramid *router* finds a *context* object (after it performs traversal) but before any view code is executed. The instance has an attribute, request, which is the request object generated by Pyramid.

Notably, the request object will have an attribute named context, which is the context that will be provided to the view which will eventually be called, as well as other attributes attached by context-finding code.

This class implements the pyramid.interfaces.IContextFound interface.

• As of Pyramid 1.0, for backwards compatibility purposes, this event may also be imported as pyramid.events.AfterTraversal.

class NewResponse (request, response)

An instance of this class is emitted as an *event* whenever any Pyramid *view* or *exception view* returns a *response*.

The instance has two attributes:request, which is the request which caused the response, and response, which is the response object returned by a view or renderer.

If the response was generated by an *exception view*, the request will have an attribute named exception, which is the exception object which caused the exception view to be executed. If the response was generated by a 'normal' view, the request will not have this attribute.

This event will not be generated if a response cannot be created due to an exception that is not caught by an exception view (no response is created under this circumstace).

This class implements the pyramid.interfaces.INewResponse interface.

• Postprocessing a response is usually better handled in a WSGI *middleware* component than in subscriber code that is called by a pyramid.interfaces.INewResponse event. The pyramid.interfaces.INewResponse event exists almost purely for symmetry with the pyramid.interfaces.INewRequest event.

class BeforeRender (system)

get (k, default=None)

Return the value for key k from the renderer globals dictionary, or the default if no such value exists.

setdefault (name, default=None)

Return the existing value for name in the renderers globals dictionary. If no value with name exists in the dictionary, set the default value into the renderer globals dictionary under the name passed. If a value already existed in the dictionary, return it. If a value did not exist in the dictionary, return the default

update(d)

Update the renderer globals dictionary with another dictionary d.

See Using Events for more information about how to register code which subscribes to these events.

CHAPTER

FORTYTWO

PYRAMID.EXCEPTIONS

Forbidden

alias of HTTPForbidden

NotFound

alias of HTTPNotFound

class ConfigurationError

Raised when inappropriate input values are supplied to an API method of a Configurator

class URLDecodeError

This exception is raised when Pyramid cannot successfully decode a URL or a URL path segment. This exception it behaves just like the Python builtin UnicodeDecodeError. It is a subclass of the builtin UnicodeDecodeError exception only for identity purposes, mostly so an exception view can be registered when a URL cannot be decoded.

42. PYRAMID. EXCEPTIONS

CHAPTER

FORTYTHREE

PYRAMID.HTTPEXCEPTIONS

43.1 HTTP Exceptions

This module contains Pyramid HTTP exception classes. Each class relates to a single HTTP status code. Each class is a subclass of the HTTPException. Each exception class is also a *response* object.

Each exception class has a status code according to RFC 2068: codes with 100-300 are not really errors; 400s are client errors, and 500s are server errors.

Exception

HTTPException

HTTPOk

- 200 HTTPOk
- 201 HTTPCreated
- 202 HTTPAccepted
- 203 HTTPNonAuthoritativeInformation
- 204 HTTPNoContent
- 205 HTTPResetContent

• 206 - HTTPPartialContent

HTTPRedirection

- 300 HTTPMultipleChoices
- 301 HTTPMovedPermanently
- 302 HTTPFound
- 303 HTTPSeeOther
- 304 HTTPNotModified
- 305 HTTPUseProxy
- 306 Unused (not implemented, obviously)
- 307 HTTPTemporaryRedirect

HTTPError

HTTPClientError

- 400 HTTPBadRequest
- 401 HTTPUnauthorized
- 402 HTTPPaymentRequired
- 403 HTTPForbidden
- 404 HTTPNotFound
- 405 HTTPMethodNotAllowed
- 406 HTTPNotAcceptable
- 407 HTTPProxyAuthenticationRequired
- 408 HTTPRequestTimeout
- 409 HTTPConflict

- 410 HTTPGone
- 411 HTTPLengthRequired
- 412 HTTPPreconditionFailed
- 413 HTTPRequestEntityTooLarge
- 414 HTTPRequestURITooLong
- 415 HTTPUnsupportedMediaType
- 416 HTTPRequestRangeNotSatisfiable
- 417 HTTPExpectationFailed

HTTPServerError

- 500 HTTPInternalServerError
- 501 HTTPNotImplemented
- 502 HTTPBadGateway
- 503 HTTPServiceUnavailable
- 504 HTTPGatewayTimeout
- 505 HTTPVersionNotSupported

Each HTTP exception has the following attributes:

code the HTTP status code for the exception

- title remainder of the status line (stuff after the code)
- **explanation** a plain-text explanation of the error message that is not subject to environment or header substitutions; it is accessible in the template via \${explanation}
- **detail** a plain-text message customization that is not subject to environment or header substitutions; accessible in the template via \${detail}

body_template a String.template-format content fragment used for environment and header substitution; the default template includes both the explanation and further detail provided in the message.

Each HTTP exception accepts the following parameters:

detail a plain-text override of the default detail

headers a list of (k,v) header pairs

comment a plain-text additional information which is usually stripped/hidden for end-users

body_template a string.Template object containing a content fragment in HTML that frames the explanation and further detail

Substitution of response headers into template values is always performed. Substitution of WSGI environment values is performed if a request is passed to the exception's constructor.

The subclasses of _HTTPMove (HTTPMultipleChoices, HTTPMovedPermanently, HTTPFound, HTTPSeeOther, HTTPUseProxy and HTTPTemporaryRedirect) are redirections that require a Location field. Reflecting this, these subclasses have one additional keyword argument: location, which indicates the location to which to redirect.

status_map

A mapping of integer status code to exception class (eg. the integer "401" maps to pyramid.httpexceptions.HTTPUnauthorized).

exception_response (status_code, **kw)

Creates an HTTP exception based on a status code. Example:

raise responsecode(404) # raises an HTTPNotFound exception.

The values passed as kw are provided to the exception's constructor.

class HTTPException

Base class for all exception response objects.

```
class HTTPOk (detail=None, headers=None, comment=None, body_template=None, **kw)
Base class for exceptions with status codes in the 200s (successful responses)
```

code: 200, title: OK

class HTTPRedirection (detail=None, headers=None, comment=None,

body_template=None, ***kw*)

base class for exceptions with status codes in the 300s (redirections)

This is an abstract base class for 3xx redirection. It indicates that further action needs to be taken by the user agent in order to fulfill the request. It does not necessarly signal an error condition.

class HTTPError (*detail=None*, *headers=None*, *comment=None*, *body_template=None*, **kw) base class for exceptions with status codes in the 400s and 500s

This is an exception which indicates that an error has occurred, and that any work in progress should not be committed.

 class HTTPClientError (detail=None, body_template=None, **kw)
 body_template=None, **kw)
 comment=None,

 base class for the 400s, where the client is in error
 comment=None,
 comment=None,

This is an error condition in which the client is presumed to be in-error. This is an expected problem, and thus is not considered a bug. A server-side traceback is not warranted. Unless specialized, this is a '400 Bad Request'

class HTTPServerError (detail=None, headers=None, comment=None, body_template=None, **kw) base class for the 500s, where the server is in-error

This is an error condition in which the server is presumed to be in-error. Unless specialized, this is a '500 Internal Server Error'.

This indicates that request has been fulfilled and resulted in a new resource being created.

code: 201, title: Created

class HTTPAccepted (detail=None, headers=None, comment=None, body_template=None, **kw) subclass of HTTPOk

This indicates that the request has been accepted for processing, but the processing has not been completed.

code: 202, title: Accepted

```
class HTTPNonAuthoritativeInformation (detail=None, headers=None, com-
ment=None, body_template=None, **kw)
```

subclass of HTTPOk

This indicates that the returned metainformation in the entity-header is not the definitive set as available from the origin server, but is gathered from a local or a third-party copy.

code: 203, title: Non-Authoritative Information

```
class HTTPNoContent (detail=None, headers=None, comment=None, body_template=None,
**kw)
```

subclass of HTTPOk

This indicates that the server has fulfilled the request but does not need to return an entity-body, and might want to return updated metainformation.

code: 204, title: No Content

```
class HTTPResetContent (detail=None, headers=None, comment=None,
body_template=None, **kw)
subclass of HTTPOk
```

This indicates that the server has fulfilled the request and the user agent SHOULD reset the document view which caused the request to be sent.

code: 205, title: Reset Content

```
class HTTPPartialContent (detail=None, headers=None, comment=None,
body_template=None, **kw)
subclass of HTTPOk
```

This indicates that the server has fulfilled the partial GET request for the resource.

code: 206, title: Partial Content

```
class HTTPMultipleChoices (location='', detail=None, headers=None, comment=None, body_template=None, **kw)
```

subclass of _HTTPMove

This indicates that the requested resource corresponds to any one of a set of representations, each with its own specific location, and agent-driven negotiation information is being provided so that the user can select a preferred representation and redirect its request to that location.

code: 300, title: Multiple Choices

subclass of _HTTPMove

This indicates that the requested resource has been assigned a new permanent URI and any future references to this resource SHOULD use one of the returned URIs.

code: 301, title: Moved Permanently

```
class HTTPFound (location='', detail=None, headers=None, comment=None,
body_template=None, **kw)
subclass of _HTTPMove
```

This indicates that the requested resource resides temporarily under a different URI.

code: 302, title: Found

This indicates that the response to the request can be found under a different URI and SHOULD be retrieved using a GET method on that resource.

code: 303, title: See Other

This indicates that if the client has performed a conditional GET request and access is allowed, but the document has not been modified, the server SHOULD respond with this status code.

code: 304, title: Not Modified

This indicates that the requested resource MUST be accessed through the proxy given by the Location field.

code: 305, title: Use Proxy

class HTTPTemporaryRedirect (*location=''*, *detail=None*, *headers=None*, *comment=None*, *body template=None*, ***kw*) subclass of HTTPMove This indicates that the requested resource resides temporarily under a different URI. code: 307, title: Temporary Redirect **class HTTPBadRequest** (*detail=None*, *headers=None*, *comment=None*, *body_template=None*, **kwclass HTTPUnauthorized (detail=None. headers=None. comment=None. *body template=None*, ***kw*) subclass of HTTPClientError This indicates that the request requires user authentication. code: 401, title: Unauthorized class HTTPPaymentRequired (detail=None, headers=None. comment=None. *body template=None*, ***kw*) subclass of HTTPClientError code: 402, title: Payment Required **class** HTTPForbidden (detail=None, headers=None, comment=None, body_template=None, result=None. **kw) subclass of HTTPClientError This indicates that the server understood the request, but is refusing to fulfill it. code: 403, title: Forbidden Raise this exception within view code to immediately return the *forbidden view* to the invoking user. Usually this is a basic 403 page, but the forbidden view can be customized as necessary. See Changing the Forbidden View. A Forbidden exception will be the context of a Forbidden View.

This exception's constructor treats two arguments specially. The first argument, detail, should be a string. The value of this string will be used as the message attribute of the exception object. The second special keyword argument, result is usually an instance of pyramid.security.Denied or pyramid.security.ACLDenied each of which indicates a reason for the forbidden error. However, result is also permitted to be just a plain boolean False object or None. The result value will be used as the result attribute of the exception object. It defaults to None.

The *Forbidden View* can use the attributes of a Forbidden exception as necessary to provide extended information in an error report shown to a user.

This indicates that the server did not find anything matching the Request-URI.

code: 404, title: Not Found

Raise this exception within *view* code to immediately return the *Not Found view* to the invoking user. Usually this is a basic 404 page, but the Not Found view can be customized as necessary. See *Changing the Not Found View*.

This exception's constructor accepts a detail argument (the first argument), which should be a string. The value of this string will be available as the message attribute of this exception, for availability to the *Not Found View*.

This indicates that the method specified in the Request-Line is not allowed for the resource identified by the Request-URI.

code: 405, title: Method Not Allowed

This indicates the resource identified by the request is only capable of generating response entities which have content characteristics not acceptable according to the accept headers sent in the request.

code: 406, title: Not Acceptable

```
class HTTPProxyAuthenticationRequired (detail=None, headers=None, com-
ment=None, body_template=None, **kw)
```

subclass of HTTPClientError

This is similar to 401, but indicates that the client must first authenticate itself with the proxy.

code: 407, title: Proxy Authentication Required

This indicates that the client did not produce a request within the time that the server was prepared to wait.

code: 408, title: Request Timeout

This indicates that the request could not be completed due to a conflict with the current state of the resource.

code: 409, title: Conflict

class HTTPGone (detail=None, headers=None, comment=None, body_template=None, **kw)
 subclass of HTTPClientError

This indicates that the requested resource is no longer available at the server and no forwarding address is known.

code: 410, title: Gone

This indicates that the the server refuses to accept the request without a defined Content-Length.

code: 411, title: Length Required

This indicates that the precondition given in one or more of the request-header fields evaluated to false when it was tested on the server.

code: 412, title: Precondition Failed

```
subclass of HTTPClientError
```

This indicates that the server is refusing to process a request because the request entity is larger than the server is willing or able to process.

code: 413, title: Request Entity Too Large

This indicates that the server is refusing to service the request because the Request-URI is longer than the server is willing to interpret.

code: 414, title: Request-URI Too Long

This indicates that the server is refusing to service the request because the entity of the request is in a format not supported by the requested resource for the requested method.

code: 415, title: Unsupported Media Type

subclass of HTTPClientError

The server SHOULD return a response with this status code if a request included a Range requestheader field, and none of the range-specifier values in this field overlap the current extent of the selected resource, and the request did not include an If-Range request-header field.

code: 416, title: Request Range Not Satisfiable

This indidcates that the expectation given in an Expect request-header field could not be met by this server.

code: 417, title: Expectation Failed

class HTTPInternalServerError (detail=None,	headers=None,	comment=None,	
<i>body_template=None</i> , ** <i>kw</i>)			
class HTTPNotImplemented (detail=None,	headers=None,	comment=None,	
body_template=None, **kw)			
subclass of HTTPServerError			

This indicates that the server does not support the functionality required to fulfill the request.

code: 501, title: Not Implemented

This indicates that the server, while acting as a gateway or proxy, received an invalid response from the upstream server it accessed in attempting to fulfill the request.

code: 502, title: Bad Gateway

This indicates that the server is currently unable to handle the request due to a temporary overloading or maintenance of the server.

code: 503, title: Service Unavailable

class HTTPGatewayTimeout (detail=None,	headers=None,	comment=None,
body_template=None,	** <i>kw</i>)	
subclass of HTTPServerError		

This indicates that the server, while acting as a gateway or proxy, did not receive a timely response from the upstream server specified by the URI (e.g. HTTP, FTP, LDAP) or some other auxiliary server (e.g. DNS) it needed to access in attempting to complete the request.

code: 504, title: Gateway Timeout

This indicates that the server does not support, or refuses to support, the HTTP protocol version that was used in the request message.

code: 505, title: HTTP Version Not Supported

CHAPTER

FORTYFOUR

PYRAMID. I18N

class TranslationString

The constructor for a *translation string*. A translation string is a Unicode-like object that has some extra metadata.

This constructor accepts one required argument named msgid. msgid must be the *message identifier* for the translation string. It must be a unicode object or a str object encoded in the default system encoding.

Optional keyword arguments to this object's constructor include domain, default, and mapping.

domain represents the *translation domain*. By default, the translation domain is None, indicating that this translation string is associated with the default translation domain (usually messages).

default represents an explicit *default text* for this translation string. Default text appears when the translation string cannot be translated. Usually, the msgid of a translation string serves double duty as as its default text. However, using this option you can provide a different default text for this translation string. This feature is useful when the default of a translation string is too complicated or too long to be used as a message identifier. If default is provided, it must be a unicode object or a str object encoded in the default system encoding (usually means ASCII). If default is None (its default value), the msgid value used by this translation string will be assumed to be the value of default.

mapping, if supplied, must be a dictionary-like object which represents the replacement values for any *translation string replacement marker* instances found within the msgid (or default) value of this translation string.

After a translation string is constructed, it behaves like most other unicode objects; its msgid value will be displayed when it is treated like a unicode object. Only when its ugettext method is called will it be translated.

Its default value is available as the default attribute of the object, its *translation domain* is available as the domain attribute, and the mapping is available as the mapping attribute. The object otherwise behaves much like a Unicode string.

class TranslationStringFactory

Create a factory which will generate translation strings without requiring that each call to the factory be passed a domain value. A single argument is passed to this class' constructor: domain. This value will be used as the domain values of translationstring.TranslationString objects generated by the __call__ of this class. The msgid, mapping, and default values provided to the __call__ method of an instance of this class have the meaning as described by the constructor of the translationstring.TranslationString

class Localizer (*locale_name*, *translations*)

An object providing translation and pluralizations related to the current request's locale name. A pyramid.i18n.Localizer object is created using the pyramid.i18n.get_localizer() function.

locale_name

The locale name for this localizer (e.g. en or en_US).

pluralize (*singular*, *plural*, *n*, *domain=None*, *mapping=None*)

Return a Unicode string translation by using two *message identifier* objects as a singular/plural pair and an n value representing the number that appears in the message using gettext plural forms support. The singular and plural objects passed may be translation strings or unicode strings. n represents the number of elements. domain is the translation domain to use to do the pluralization, and mapping is the interpolation mapping that should be used on the result. Note that if the objects passed are translation strings, their domains and mappings are ignored. The domain and mapping arguments must be used instead. If the domain is not supplied, a default domain is used (usually messages).

Example:

translate(tstring, domain=None, mapping=None)

Translate a *translation string* to the current language and interpolate any *replacement markers* in the result. The translate method accepts three arguments: tstring (required), domain (optional) and mapping (optional). When called, it will translate the tstring translation string to a unicode object using the current locale. If the current locale could not be determined, the result of interpolation of the default value is returned. The optional domain argument can be used to specify or override the domain of the tstring (useful when tstring is a normal string rather than a translation string). The optional mapping argument can specify or override the tstring interpolation mapping, useful when the tstring argument is a simple string instead of a translation string.

Example:

Example:

get_localizer(request)

Retrieve a pyramid.i18n.Localizer object corresponding to the current request's locale name.

negotiate_locale_name(request)

Negotiate and return the *locale name* associated with the current request (never cached).

get_locale_name (request)

Return the *locale name* associated with the current request (possibly cached).

default_locale_negotiator(request)

The default *locale negotiator*. Returns a locale name or None.

•First, the negotiator looks for the _LOCALE_ attribute of the request object (possibly set by a view or a listener for an *event*).

•Then it looks for the request .params ['_LOCALE_'] value.

•Then it looks for the request.cookies['_LOCALE_'] value.

•Finally, the negotiator returns None if the locale could not be determined via any of the previous checks (when a locale negotiator returns None, it signifies that the *default locale name* should be used.)

make_localizer (current_locale_name, translation_directories)

Create a pyramid.i18n.Localizer object corresponding to the provided locale name from the translations found in the list of translation directories.

See *Internationalization and Localization* for more information about using Pyramid internationalization and localization services within an application.

CHAPTER

FORTYFIVE

PYRAMID.INTERFACES

45.1 Event-Related Interfaces

interface IApplicationCreated

Event issued when the pyramid.config.Configurator.make_wsgi_app() method is called. See the documentation attached to pyramid.events.ApplicationCreated for more information.

0 For backwards compatibility with Pyramid versions before 1.0, this interface can also be imported as pyramid.interfaces.IWSGIApplicationCreatedEvent.

app

Created application

interface INewRequest

An event type that is emitted whenever Pyramid begins to process a new request. See the documentation attached to pyramid.events.NewRequest for more information.

request

The request object

interface IContextFound

An event type that is emitted after Pyramid finds a *context* object but before it calls any view code. See the documentation attached to pyramid.events.ContextFound for more information.

• For backwards compatibility with versions of Pyramid before 1.0, this event interface can also be imported as pyramid.interfaces.IAfterTraversal.

request

The request object

interface INewResponse

An event type that is emitted whenever any Pyramid view returns a response. See the documentation attached to pyramid.events.NewResponse for more information.

request

The request object

response

The response object

interface IBeforeRender

Subscribers to this event may introspect the and modify the set of *renderer globals* before they are passed to a *renderer*. This event object iself has a dictionary-like interface that can be used for this purpose. For example:

```
from repoze.events import subscriber
from pyramid.interfaces import IBeforeRender
@subscriber(IBeforeRender)
def add_global(event):
    event['mykey'] = 'foo'
```

See also Using The Before Render Event.

setdefault (name, default=None)

Return the existing value for name in the renderers globals dictionary. If no value with name exists in the dictionary, set the default value into the renderer globals dictionary under the name passed. If a value already existed in the dictionary, return it. If a value did not exist in the dictionary, return the default

```
___getitem___(k)
```

Return the value for key k from the renderer globals dictionary.

___contains___(k)

Return True if k exists in the renderer globals dictionary.

get (k, default=None)

Return the value for key k from the renderer globals dictionary, or the default if no such value exists.

update(d)

Update the renderer globals dictionary with another dictionary d.

__setitem__(name, value)

Set a name/value pair into the dictionary which is passed to a renderer as the renderer globals dictionary.

45.2 Other Interfaces

interface IAuthenticationPolicy

An object representing a Pyramid authentication policy.

remember (*request*, *principal*, **kw)

Return a set of headers suitable for 'remembering' the principal named principal when set in a response. An individual authentication policy and its consumers can decide on the composition and meaning of **kw.

authenticated_userid(request)

Return the authenticated userid or None if no authenticated userid can be found. This method of the policy should ensure that a record exists in whatever persistent store is used related to the user (the user should not have been deleted); if a record associated with the current id does not exist in a persistent store, it should return None.

unauthenticated_userid(request)

Return the *unauthenticated* userid. This method performs the same duty as authenticated_userid but is permitted to return the userid based only on data present in the request; it needn't (and shouldn't) check any persistent store to ensure that the user record related to the request userid exists.

effective_principals(request)

Return a sequence representing the effective principals including the userid and any groups belonged to by the current user, including 'system' groups such as Everyone and Authenticated.

forget (request)

Return a set of headers suitable for 'forgetting' the current user on subsequent requests.

interface IAuthorizationPolicy

An object representing a Pyramid authorization policy.

principals_allowed_by_permission(context, permission)

Return a set of principal identifiers allowed by the permission in context. This behavior is optional; if you choose to not implement it you should define this method as something which raises a NotImplementedError. This method will only be called when the pyramid.security.principals allowed by permission API is used.

permits (context, principals, permission)

Return True if any of the principals is allowed the permission in the current context, else return False

interface IExceptionResponse

Extends:

pyramid.interfaces.IException, pyramid.interfaces.IResponse

An interface representing a WSGI response which is also an exception object. Register an exception view using this interface as a context to apply the registered view for all exception types raised by Pyramid internally (any exception that inherits from pyramid.response.Response, including pyramid.httpexceptions.HTTPNotFound and pyramid.httpexceptions.HTTPForbidden).

interface IRoute

Interface representing the type of object returned from IRoutesMapper.get_route

name

The route name

pattern

The route pattern

factory

The root factory used by the Pyramid router when this route matches (or None)

generate(kw)

Generate a URL based on filling in the dynamic segment markers in the pattern using the kw dictionary provided.

pregenerator

This attribute should either be None or a callable object implementing the IRoutePregenerator interface

predicates

A sequence of *route predicate* objects used to determine if a request matches this route or not or not after basic pattern matching has been completed.

match(path)

If the path passed to this function can be matched by the pattern of this route, return a dictionary (the 'matchdict'), which will contain keys representing the dynamic segment markers in the pattern mapped to values extracted from the provided path.

If the path passed to this function cannot be matched by the pattern of this route, return None.

interface IRoutePregenerator

____call___ (request, elements, kw)

A pregenerator is a function associated by a developer with a *route*. The pregenerator for a route is called by pyramid.url.route_url() in order to adjust the set of arguments passed to it by the user for special purposes, such as Pylons 'subdomain' support. It will influence the URL returned by route_url.

A pregenerator should return a two-tuple of (elements, kw) after examining the originals passed to this function, which are the arguments (request, elements, kw). The simplest pregenerator is:

```
def pregenerator(request, elements, kw):
    return elements, kw
```

You can employ a pregenerator by passing a pregenerator argument to the pyramid.config.Configurator.add_route() function.

interface ISession

An interface representing a session (a web session object, usually accessed via request.session.

Keys and values of a session must be pickleable.

invalidate()

Invalidate the session. The action caused by invalidate is implementationdependent, but it should have the effect of completely dissociating any data stored in the session with the current request. It might set response values (such as one which clears a cookie), or it might not.

new_csrf_token()

Create and set into the session a new, random cross-site request forgery protection token. Return the token. It will be a string.

pop (*k*, **args*)

remove specified key and return the corresponding value *args may contain a single default value, or may not be supplied. If key is not found, default is returned if given, otherwise KeyError is raised

get_csrf_token()

Return a random cross-site request forgery protection token. It will be a string. If a token was previously added to the session via new_csrf_token, that token will be returned. If no CSRF token was previously set into the session, new_csrf_token will be called, which will create and set a token, and this token will be returned.

__contains__(key)

Return true if a key exists in the mapping.

flash (msg, queue='', allow_duplicate=True)

Push a flash message onto the end of the flash queue represented by queue. An alternate flash message queue can used by passing an optional queue, which must be a string. If allow_duplicate is false, if the msg already exists in the queue, it will not be readded.

peek_flash(queue='')

Peek at a queue in the flash storage. The queue remains in flash storage after this message is called. The queue is returned; it is a list of flash messages added by pyramid.interfaces.ISesssion.flash()

itervalues()

iterate over values

new

Boolean attribute. If True, the session is new.

__len__() Return the number of items in the session.

___getitem___(*key*) Get a value for a key

A KeyError is raised if there is no value for the key.

get (key, default=None) Get a value for a key

The default is returned if there is no value for the key.

keys()

Return the keys of the mapping object.

update(d)

Update D from E: for k in E.keys(): D[k] = E[k]

__setitem__(key, value) Set a new item in the mapping.

iteritems()

iterate over items

popitem()

remove and return some (key, value) pair as a 2-tuple; but raise KeyError if mapping is empty

iterkeys()

iterate over keys; equivalent to __iter__

pop_flash(queue='')

Pop a queue from the flash storage. The queue is removed from flash storage after this message is called. The queue is returned; it is a list of flash messages added by pyramid.interfaces.ISesssion.flash()

__delitem__ (key)

Delete a value from the mapping using the key.

A KeyError is raised if there is no value for the key.

setdefault (key, default=None)

D.setdefault(k[,d]) -> D.get(k,d), also set D[k]=d if k not in D

created

Integer representing Epoch time when created.

items()

Return the items of the mapping object.

clear()

delete all items

changed()

Mark the session as changed. A user of a session should call this method after he or she mutates a mutable object that is *a value of the session* (it should not be required after mutating the session itself). For example, if the user has stored a dictionary in the session under the key foo, and he or she does session['foo'] ={}, changed() needn't be called. However, if subsequently he or she does session['foo']['a'] = 1, changed() must be called for the sessioning machinery to notice the mutation of the internal dictionary.

iter()

Return an iterator for the keys of the mapping object.

values()

Return the values of the mapping object.

interface ISessionFactory

An interface representing a factory which accepts a request object and returns an ISession object

___call___(request) Return an ISession object

interface IRendererInfo

An object implementing this interface is passed to every *renderer factory* constructor as its only argument (conventionally named info)

name

The value passed by the user as the renderer name

package

The "current package" when the renderer configuration statement was found

settings

The deployment settings dictionary related to the current application

registry

The "current" application registry when the renderer was created

type

The renderer type name

interface ITemplateRenderer

Extends: pyramid.interfaces.IRenderer

implementation()

Return the object that the underlying templating system uses to render the template; it is typically a callable that accepts arbitrary keyword arguments and returns a string or unicode object

interface IViewMapperFactory

__call__(*self*, **kw)

Return an object which implements pyramid.interfaces.IViewMapper. kw will be a dictionary containing view-specific arguments, predicates. such as permission, attr, renderer. and other items. An **IViewMapperFactory** is used bv pyramid.config.Configurator.add view() to provide a plugpoint to extension developers who want to modify potential view callable invocation signatures and response values.

interface IViewMapper

____call__(*self*, *object*)

Provided with an arbitrary object (a function, class, or instance), returns a callable with the call signature (context, request). The callable returned should itself return a Response object. An IViewMapper is returned by pyramid.interfaces.IViewMapperFactory.

interface IMultiDict

An ordered dictionary that can have multiple values for each key. A multidict adds the methods getall, getone, mixed, extend add, and dict_of_lists to the normal dictionary interface. A multidict data structure is used as request.POST, request.GET, and request.params within an Pyramid application.

extend(other=None, **kwargs)

Add a set of keys and values, not overwriting any previous values. The other structure may be a list of two-tuples or a dictionary. If **kwargs is passed, its value *will* overwrite existing values.

getall(key)

Return a list of all values matching the key (may be an empty list)

add (key, value)

Add the key and value, not overwriting any previous value.

getone (key)

Get one value matching the key, raising a KeyError if multiple values were found.

dict_of_lists()

Returns a dictionary where each key is associated with a list of values.

mixed()

Returns a dictionary where the values are either single values, or a list of values when a key/value appears more than once in this dictionary. This is similar to the kind of dictionary often used to represent the variables in a web request.

interface IResponse

Represents a WSGI response using the WebOb response interface. Some attribute and method documentation of this interface references RFC 2616.

This interface is most famously implemented by pyramid.response.Response and the HTTP exception classes in pyramid.httpexceptions.

content_length

Gets and sets and deletes the Content-Length header. For more information on Content-Length see RFC 2616 section 14.17. Converts using int.

status

The status string.

encode_content (encoding='gzip', lazy=False)

Encode the content with the given encoding (only gzip and identity are supported).

cache_expires

Get/set the Cache-Control and Expires headers. This sets the response to expire in the number of seconds passed when set.

set_cookie (key, value='', max_age=None, path='/', domain=None, secure=False, httponly=False, comment=None, expires=None, overwrite=False) Set (add) a cookie for the response

vary

Gets and sets and deletes the Vary header. For more information on Vary see section 14.44. Converts using list.

retry_after

Gets and sets and deletes the Retry-After header. For more information on Retry-After see RFC 2616 section 14.37. Converts using HTTP date or delta seconds.

www_authenticate

Gets and sets and deletes the WWW-Authenticate header. For more information on WWW-Authenticate see RFC 2616 section 14.47. Converts using 'parse_auth' and 'serialize_auth'.

content_language

Gets and sets and deletes the Content-Language header. Converts using list. For more information about Content-Language see RFC 2616 section 14.12.

etag

Gets and sets and deletes the ETag header. For more information on ETag see RFC 2616 section 14.19. Converts using Entity tag.

content_location

Gets and sets and deletes the Content-Location header. For more information on Content-Location see RFC 2616 section 14.14.

server

Gets and sets and deletes the Server header. For more information on Server see RFC216 section 14.38.

unset_cookie (key, strict=True)

Unset a cookie with the given name (remove it from the response).

pragma

Gets and sets and deletes the Pragma header. For more information on Pragma see RFC 2616 section 14.32.

app_iter

Returns the app_iter of the response.

If body was set, this will create an app_iter from that body (a single-item list)

headers

The headers in a dictionary-like object

charset

Get/set the charset (in the Content-Type)

unicode_body

Get/set the unicode value of the body (using the charset of the Content-Type)

status_int

The status as an integer

conditional_response_app (environ, start_response)

Like the normal __call__ interface, but checks conditional headers: •If-Modified-Since (304 Not Modified; only on GET, HEAD) •If-None-Match (304 Not Modified; only on GET, HEAD) •Range (406 Partial Content; only on GET, HEAD)

delete_cookie(key, path='/', domain=None)

Delete a cookie from the client. Note that path and domain must match how the cookie was originally set. This sets the cookie to the empty string, and max_age=0 so that it should expire immediately.

content_range

Gets and sets and deletes the Content-Range header. For more information on Content-Range see section 14.16. Converts using ContentRange object.

content_encoding

Gets and sets and deletes the Content-Encoding header. For more information about Content-Encoding see RFC 2616 section 14.11.

____call___(environ, start_response)

WSGI call interface, should call the start_response callback and should return an iterable

content_md5

Gets and sets and deletes the Content-MD5 header. For more information on Content-MD5 see RFC 2616 section 14.14.

content_disposition

Gets and sets and deletes the Content-Disposition header. For more information on Content-Disposition see RFC 2616 section 19.5.1.

cache_control

Get/set/modify the Cache-Control header (RFC 2616 section 14.9)

location

Gets and sets and deletes the Location header. For more information on Location see RFC 2616 section 14.30.

body

The body of the response, as a str. This will read in the entire app_iter if necessary.

expires

Gets and sets and deletes the Expires header. For more information on Expires see RFC 2616 section 14.21. Converts using HTTP date.

content_type_params

A dictionary of all the parameters in the content type. This is not a view, set to change, modifications of the dict would not be applied otherwise.

md5_etag(body=None, set_content_md5=False)

Generate an etag for the response object using an MD5 hash of the body (the body parameter, or self.body if not given). Sets self.etag. If set_content_md5 is True sets self.content_md5 as well

app_iter_range (start, stop)

Return a new app_iter built from the response app_iter that serves up only the given start:stop range.

last_modified

Gets and sets and deletes the Last-Modified header. For more information on Last-Modified see RFC 2616 section 14.29. Converts using HTTP date.

RequestClass

Alias for pyramid.request.Request

content_type

Get/set the Content-Type header (or None), without the charset or any parameters. If you include parameters (or ; at all) when setting the content_type, any existing parameters will be deleted; otherwise they will be preserved.

date

Gets and sets and deletes the Date header. For more information on Date see RFC 2616 section 14.18. Converts using HTTP date.

copy()

Makes a copy of the response and returns the copy.

accept_ranges

Gets and sets and deletes the Accept-Ranges header. For more information on Accept-Ranges see RFC 2616, section 14.5

age

Gets and sets and deletes the Age header. Converts using int. For more information on Age see RFC 2616, section 14.6.

request

Return the request associated with this response if any.

merge_cookies(resp)

Merge the cookies that were set on this response with the given resp object (which can be any WSGI application). If the resp is a webob.Response object, then the other object will be modified in-place.

headerlist

The list of response headers.

environ

Get/set the request environ associated with this response, if any.

allow

Gets and sets and deletes the Allow header. Converts using list. For more information on Allow see RFC 2616, Section 14.7.

body_file

A file-like object that can be used to write to the body. If you passed in a list app_iter, that app_iter will be modified by writes.

CHAPTER

FORTYSIX

PYRAMID.LOCATION

lineage(*resource*)

Return a generator representing the *lineage* of the *resource* object implied by the resource argument. The generator first returns resource unconditionally. Then, if resource supplies a _____parent___ attribute, return the resource represented by resource.____parent___. If *that* resource has a ____parent___ attribute, return that resource's parent, and so on, until the resource being inspected either has no ____parent___ attribute or which has a ___parent___ attribute of None. For example, if the resource tree is:

thing1 = Thing()
thing2 = Thing()
thing2.__parent__ = thing1

Calling lineage (thing2) will return a generator. When we turn it into a list, we will get:

```
list(lineage(thing2))
[ <Thing object at thing2>, <Thing object at thing1> ]
```

inside (resource1, resource2)

Is resource1 'inside' resource2? Return True if so, else False.

resource1 is 'inside' resource2 if resource2 is a *lineage* ancestor of resource1. It is a lineage ancestor if its parent (or one of its parent's parents, etc.) is an ancestor.

CHAPTER

FORTYSEVEN

PYRAMID.PASTER

get_app (config_uri, name=None)

Return the WSGI application named name in the PasteDeploy config file specified by config_uri.

If the name is None, this will attempt to parse the name from the config_uri string expecting the format inifile#name. If no name is found, the name will default to "main".

bootstrap (config_uri, request=None)

Load a WSGI application from the PasteDeploy config file specified by config_uri. The environment will be configured as if it is currently serving request, leaving a natural environment in place to write scripts that can generate URLs and utilize renderers.

This function returns a dictionary with app, root, closer, request, and registry keys. app is the WSGI app loaded (based on the config_uri), root is the traversal root resource of the Pyramid application, and closer is a parameterless callback that may be called when your script is complete (it pops a threadlocal stack).

• Most operations within Pyramid expect to be invoked within the context of a WSGI request, thus it's important when loading your application to anchor it when executing scripts and other code that is not normally invoked during active WSGI requests.

• For a complex config file containing multiple Pyramid applications, this function will setup the environment under the context of the last-loaded Pyramid application. You may load a specific application yourself by using the lower-level functions pyramid.paster.get_app() and pyramid.scripting.prepare() in conjunction with pyramid.config.global_registries. config_uri – specifies the PasteDeploy config file to use for the interactive shell. The format is inifile#name. If the name is left off, main will be assumed.

request – specified to anchor the script to a given set of WSGI parameters. For example, most people would want to specify the host, scheme and port such that their script will generate URLs in relation to those parameters. A request with default parameters is constructed for you if none is provided. You can mutate the request's environ later to setup a specific host/port/scheme/etc.

See Writing a Script for more information about how to use this function.

CHAPTER

FORTYEIGHT

PYRAMID.REGISTRY

class Registry (name='', bases=())

A registry object is an *application registry*. The existence of a registry implementation detail of pyramid. It is used by the framework itself to perform mappings of URLs to view callables, as well as servicing other various duties. Despite being an implementation detail of the framework, it has a number of attributes that may be useful within application code.

For information about the purpose and usage of the application registry, see *Using the Zope Component Architecture in Pyramid*.

The application registry is usually accessed as request.registry in application code.

settings

The dictionary-like *deployment settings* object. See *Deployment Settings* for information. This object is often accessed as request.registry.settings or config.registry.settings in a typical Pyramid application.

CHAPTER

FORTYNINE

PYRAMID. RENDERERS

get_renderer (renderer_name, package=None)

Return the renderer object for the renderer named as renderer_name.

You may supply a relative asset spec as renderer_name. If the package argument is supplied, a relative renderer name will be converted to an absolute asset specification by combining the package supplied as package with the relative asset specification supplied as renderer_name. If you do not supply a package (or package is None) the package name of the *caller* of this function will be used as the package.

render (renderer_name, value, request=None, package=None)

Using the renderer specified as renderer_name (a template or a static renderer) render the value (or set of values) present in value. Return the result of the renderer's __call__ method (usually a string or Unicode).

If the renderer name refers to a file on disk (such as when the renderer is a template), it's usually best to supply the name as a *asset specification* (e.g. packagename:path/to/template.pt).

You may supply a relative asset spec as renderer_name. If the package argument is supplied, a relative renderer path will be converted to an absolute asset specification by combining the package supplied as package with the relative asset specification supplied as renderer_name. If you do not supply a package (or package is None) the package name of the *caller* of this function will be used as the package.

The value provided will be supplied as the input to the renderer. Usually, for template renderings, this should be a dictionary. For other renderers, this will need to be whatever sort of value the renderer expects.

The 'system' values supplied to the renderer will include a basic set of top-level system names, such as request, context, and renderer_name. If *renderer globals* have been specified, these will also be used to agument the value.

Supply a request parameter in order to provide the renderer with the most correct 'system' values (request and context in particular).

render_to_response (renderer_name, value, request=None, package=None)

Using the renderer specified as renderer_name (a template or a static renderer) render the value (or set of values) using the result of the renderer's __call__ method (usually a string or Unicode) as the response body.

If the renderer name refers to a file on disk (such as when the renderer is a template), it's usually best to supply the name as a *asset specification*.

You may supply a relative asset spec as renderer_name. If the package argument is supplied, a relative renderer name will be converted to an absolute asset specification by combining the package supplied as package with the relative asset specification supplied as renderer_name. If you do not supply a package (or package is None) the package name of the *caller* of this function will be used as the package.

The value provided will be supplied as the input to the renderer. Usually, for template renderings, this should be a dictionary. For other renderers, this will need to be whatever sort of value the renderer expects.

The 'system' values supplied to the renderer will include a basic set of top-level system names, such as request, context, and renderer_name. If *renderer globals* have been specified, these will also be used to agument the value.

Supply a request parameter in order to provide the renderer with the most correct 'system' values (request and context in particular).

class JSONP (*param_name='callback'*)

JSONP renderer factory helper which implements a hybrid json/jsonp renderer. JSONP is useful for making cross-domain AJAX requests.

Configure a JSONP renderer using the pyramid.config.Configurator.add_renderer() API at application startup time:

```
from pyramid.config import Configurator
config = Configurator()
config.add_renderer('jsonp', JSONP(param_name='callback'))
```

Once this renderer registered add renderer() is via as above, you can use jsonp as the renderer= parameter to @view config or pyramid.config.Configurator.add_view`():

```
from pyramid.view import view_config
@view_config(renderer='jsonp')
def myview(request):
    return {'greeting':'Hello world'}
```

When a view is called that uses the JSONP renderer:

•If there is a parameter in the request's HTTP query string that matches the param_name of the registered JSONP renderer (by default, callback), the renderer will return a JSONP response.

•If there is no callback parameter in the request's query string, the renderer will return a 'plain' JSON response.

This feature is new in Pyramid 1.1.

See also: JSONP Renderer.

null_renderer

An object that can be used in advanced integration cases as input to the view configuration renderer= argument. When the null renderer is used as a view renderer argument, Pyramid avoids converting the view callable result into a Response object. This is useful if you want to reuse the view configuration and lookup machinery outside the context of its use by the Pyramid router (e.g. the package named pyramid_rpc does this).

CHAPTER

FIFTY

PYRAMID. REQUEST

class Request (environ, charset=(No Default), unicode_errors=(No Default), decode_param_names=(No Default), **kw)

A subclass of the *WebOb* Request class. An instance of this class is created by the *router* and is provided to a view callable (and to other subsystems) as the request argument.

The documentation below (save for the add_response_callback and add_finished_callback methods, which are defined in this subclass itself, and the attributes context, registry, root, subpath, traversed, view_name, virtual_root, and virtual_root_path, each of which is added to the request by the *router* at request ingress time) are autogenerated from the WebOb source code used when this documentation was generated.

Due to technical constraints, we can't yet display the WebOb version number from which this documentation is autogenerated, but it will be the 'prevailing WebOb version' at the time of the release of this Pyramid version. See http://pythonpaste.org/webob/ for further information.

context

The *context* will be available as the context attribute of the *request* object. It will be the context object implied by the current request. See *Traversal* for information about context objects.

registry

The *application registry* will be available as the registry attribute of the *request* object. See *Using the Zope Component Architecture in Pyramid* for more information about the application registry.

root

The *root* object will be available as the root attribute of the *request* object. It will be the resource object at which traversal started (the root). See *Traversal* for information about root objects.

subpath

The traversal *subpath* will be available as the subpath attribute of the *request* object. It will be a sequence containing zero or more elements (which will be Unicode objects). See *Traversal* for information about the subpath.

traversed

The "traversal path" will be available as the traversed attribute of the *request* object. It will be a sequence representing the ordered set of names that were used to traverse to the *context*, not including the view name or subpath. If there is a virtual root associated with the request, the virtual root path is included within the traversal path. See *Traversal* for more information.

view_name

The *view name* will be available as the view_name attribute of the *request* object. It will be a single string (possibly the empty string if we're rendering a default view). See *Traversal* for information about view names.

virtual_root

The *virtual root* will be available as the virtual_root attribute of the *request* object. It will be the virtual root object implied by the current request. See *Virtual Hosting* for more information about virtual roots.

virtual_root_path

The *virtual root path* will be available as the virtual_root_path attribute of the *request* object. It will be a sequence representing the ordered set of names that were used to traverse to the virtual root object. See *Virtual Hosting* for more information about virtual roots.

exception

If an exception was raised by a *root factory* or a *view callable*, or at various other points where Pyramid executes user-defined code during the processing of a request, the exception object which was caught will be available as the exception attribute of the request within a *exception view*, a *response callback* or a *finished callback*. If no exception occurred, the value of request.exception will be None within response and finished callbacks.

response

This attribute is actually a "reified" property which returns an instance of the pyramid.response.Response class. The response object returned does not exist until this attribute is accessed. Once it is accessed, subsequent accesses to this request object will return the same Response object.

The request.response API can is used by renderers. A render obtains the response object it will return from a view that uses that renderer by accessing request.response. Therefore, it's possible to use the request.response API to set up a response object with "the right" attributes (e.g. by calling request.response.set_cookie(...) or request.response.content_type = 'text/plain', etc) within a view that uses a renderer.

```
response = request.response
response.set_cookie('mycookie', 'mine, all mine!')
return {'text':'Value that will be used by the renderer'}
```

Mutations to this response object will be preserved in the response sent to the client after rendering. For more information about using request.response in conjunction with a renderer, see *Varying Attributes of Rendered Responses*.

Non-renderer code can also make use of request.response instead of creating a response "by hand". For example, in view code:

```
response = request.response
response.body = 'Hello!'
response.content_type = 'text/plain'
return response
```

Note that the response in this circumstance is not "global"; it still must be returned from the view code if a renderer is not used.

session

If a *session factory* has been configured, this attribute will represent the current user's *session* object. If a session factory *has not* been configured, requesting the request.session attribute will cause a pyramid.exceptions.ConfigurationError to be raised.

tmpl_context

The template context for Pylons-style applications.

matchdict

If a *route* has matched during this request, this attribute will be a dictionary containing the values matched by the URL pattern associated with the route. If a route has not matched during this request, the value of this attribute will be None. See *The Matchdict*.

matched_route

If a *route* has matched during this request, this attribute will be an obect representing the route matched by the URL pattern associated with the route. If a route has not matched during this request, the value of this attribute will be None. See *The Matched Route*.

add_response_callback(callback)

Add a callback to the set of callbacks to be called by the *router* at a point after a *response* object is successfully created. Pyramid does not have a global response object: this functionality allows an application to register an action to be performed against the response once one is created.

A 'callback' is a callable which accepts two positional parameters: request and response. For example:

2

```
1 def cache_callback(request, response):
```

```
'Set the cache_control max_age for the response'
```

```
3 response.cache_control.max_age = 360
```

4 request.add_response_callback(cache_callback)

Response callbacks are called in the order they're added (first-to-most-recently-added). No response callback is called if an exception happens in application code, or if the response object returned by *view* code is invalid.

All response callbacks are called *after* the pyramid.events.NewResponse event is sent.

Errors raised by callbacks are not handled specially. They will be propagated to the caller of the Pyramid router application.

See also: Using Response Callbacks.

add_finished_callback(callback)

Add a callback to the set of callbacks to be called unconditionally by the *router* at the very end of request processing.

callback is a callable which accepts a single positional parameter: request. For example:

```
import transaction
1
2
 def commit_callback(request):
3
      '''commit or abort the transaction associated with request'''
4
      if request.exception is not None:
5
          transaction.abort()
6
7
      else:
          transaction.commit()
8
 request.add_finished_callback(commit_callback)
9
```

Finished callbacks are called in the order they're added (first- to most-recently- added). Finished callbacks (unlike response callbacks) are *always* called, even if an exception happens in application code that prevents a response from being generated.

The set of finished callbacks associated with a request are called *very late* in the processing of that request; they are essentially the last thing called by the *router*. They are called after response processing has already occurred in a top-level finally: block within the router

request processing code. As a result, mutations performed to the request provided to a finished callback will have no meaningful effect, because response processing will have already occurred, and the request's scope will expire almost immediately after all finished callbacks have been processed.

Errors raised by finished callbacks are not handled specially. They will be propagated to the caller of the Pyramid router application.

See also: Using Finished Callbacks.

route_url(route_name, *elements, **kw)

Return the URL for the route named route_name, using *elements and **kw as modifiers.

This convenience calling is а method. The result of pyramid.request.Request.route url() is the calling same as pyramid.url.route url() with an explicit request parameter.

The pyramid.request.Request.route_url() method calls the pyramid.url.route_url() function using the Request object as the request argument. The route_name, *elements and *kw arguments passed to pyramid.request.Request.route_url() are passed through to pyramid.url.route_url() unchanged and its result is returned.

This call to pyramid.request.Request.route_url():

request.route_url('route_name')

Is completely equivalent to calling pyramid.url.route_url() like this:

```
from pyramid.url import route_url
route_url('route_name', request)
```

route_path (route_name, *elements, **kw)

Generates a path (aka a 'relative URL', a URL minus the host, scheme, and port) for a named Pyramid *route configuration*.

This is convenience method. The calling а result of pyramid.request.Request.route path() is the same calling as pyramid.url.route_path() with an explicit request parameter.

This method accepts the same arguments as pyramid.request.Request.route_url() and performs the same duty. It just omits the host, port, and scheme information in the

return value; only the script name, path, query parameters, and anchor data are present in the returned string.

calls the The pyramid.request.Request.route path() method pyramid.url.route path() function using the Request object as the request argument. The *elements and *kw arguments passed to pyramid.request.Request.route path() through are passed to pyramid.url.route path() unchanged and its result is returned.

This call to pyramid.request.Request.route_path():

request.route_path('foobar')

Is completely equivalent to calling pyramid.url.route_path() like this:

```
from pyramid.url import route_path
route_path('foobar', request)
```

See pyramid.url.route_path() for more information

resource_url (*resource*, **elements*, ***kw*)

Return the URL for the *resource* object named resource, using *elements and **kw as modifiers.

This is a convenience method. The result of calling pyramid.request.Request.resource_url() is the same as calling pyramid.url.resource_url() with an explicit request parameter.

The pyramid.request.Request.resource_url() method calls the pyramid.url.resource_url() function using the Request object as the request argument. The resource, *elements and *kw arguments passed to pyramid.request.Request.resource_url() are passed through to pyramid.url.resource_url() unchanged and its result is returned.

This call to pyramid.request.Request.resource_url():

request.resource_url(myresource)

Is completely equivalent to calling pyramid.url.resource_url() like this:

```
from pyramid.url import resource_url
resource_url(resource, request)
```

U For backwards compatibility purposes, this method can also be called as pyramid.request.Request.model_url().

static_url(path, **kw)

Generates a fully qualified URL for a static *asset*. The asset must live within a location defined via the pyramid.config.Configurator.add_static_view() *configuration declaration directive* (see *Serving Static Assets*).

This The is convenience method. calling а result of pyramid.request.Request.static_url() is the calling same as pyramid.url.static_url() with an explicit request parameter.

The pyramid.request.Request.static_url() method calls the pyramid.url.static_url() function using the Request object as the request argument. The *kw arguments passed to pyramid.request.Request.static_url() are passed through to pyramid.url.static_url() unchanged and its result is returned.

This call to pyramid.request.Request.static_url():

request.static_url('mypackage:static/foo.css')

Is completely equivalent to calling pyramid.url.static_url() like this:

```
from pyramid.url import static_url
static_url('mypackage:static/foo.css', request)
```

See pyramid.url.static_url() for more information

response_*

In Pyramid 1.0, you could set attributes on a pyramid.request.Request which influenced the behavor of *rendered* responses (views which use a *renderer* and which don't directly return a response). These attributes began with response_, such as response_headerlist. If you needed to influence response values from a view that uses a renderer (such as the status code, a header, the content type, etc) you would set these attributes. See *Deprecated Mechanism to Vary Attributes of Rendered Responses* for further

discussion. As of Pyramid 1.1, assignment to response_* attrs are deprecated. Assigning to one is still supported but will cause a deprecation warning to be emitted, and eventually the feature will be removed. For new code, instead of assigning response_* attributes to the request, use API of the the pyramid.request.Request.response object (exposed to view code as request.response) to influence rendered response behavior.

json_body

This property will return the JSON-decoded variant of the request body. If the request body is not well-formed JSON, or there is no body associated with this request, this property will raise an exception. See also *Dealing With A JSON-Encoded Request Body*.

GET

Like .str_GET, but decodes values and keys

POST

Like .str_POST, but decodes values and keys

accept

Gets and sets the Accept header (HTTP spec section 14.1).

accept_charset

Gets and sets the Accept-Charset header (HTTP spec section 14.2).

accept_encoding

Gets and sets the Accept-Encoding header (HTTP spec section 14.3).

accept_language

Gets and sets the Accept-Language header (HTTP spec section 14.4).

add_finished_callback(callback)

Add a callback to the set of callbacks to be called unconditionally by the *router* at the very end of request processing.

callback is a callable which accepts a single positional parameter: request. For example:

```
import transaction
1
2
 def commit callback(request):
3
      '''commit or abort the transaction associated with request'''
4
      if request.exception is not None:
5
          transaction.abort()
6
      else:
7
          transaction.commit()
8
 request.add_finished_callback(commit_callback)
9
```

Finished callbacks are called in the order they're added (first- to most-recently- added). Finished callbacks (unlike response callbacks) are *always* called, even if an exception happens in application code that prevents a response from being generated.

The set of finished callbacks associated with a request are called *very late* in the processing of that request; they are essentially the last thing called by the *router*. They are called after response processing has already occurred in a top-level finally: block within the router request processing code. As a result, mutations performed to the request provided to a finished callback will have no meaningful effect, because response processing will have already occurred, and the request's scope will expire almost immediately after all finished callbacks have been processed.

Errors raised by finished callbacks are not handled specially. They will be propagated to the caller of the Pyramid router application.

See also: Using Finished Callbacks.

add_response_callback(callback)

Add a callback to the set of callbacks to be called by the *router* at a point after a *response* object is successfully created. Pyramid does not have a global response object: this functionality allows an application to register an action to be performed against the response once one is created.

A 'callback' is a callable which accepts two positional parameters: request and response. For example:

Response callbacks are called in the order they're added (first-to-most-recently-added). No response callback is called if an exception happens in application code, or if the response object returned by *view* code is invalid.

All response callbacks are called *after* the pyramid.events.NewResponse event is sent.

Errors raised by callbacks are not handled specially. They will be propagated to the caller of the Pyramid router application.

See also: Using Response Callbacks.

application_url

The URL including SCRIPT_NAME (no PATH_INFO or query string)

as_string(skip_body=False)

Return HTTP string representing this request. If skip_body is True, exclude the body. If skip_body is an integer larger than one, skip body only if its length is bigger than that number.

authorization

Gets and sets the Authorization header (HTTP spec section 14.8). Converts it using parse_auth and serialize_auth.

```
classmethod blank (path, environ=None, base_url=None, headers=None, POST=None,
```

**kw)

Create a blank request environ (and Request wrapper) with the given path (path should be urlencoded), and any keys from environ.

The path will become path_info, with any query string split off and used.

All necessary keys will be added to the environ, but the values you pass in will take precedence. If you pass in base_url then wsgi.url_scheme, HTTP_HOST, and SCRIPT_NAME will be filled in from that value.

Any extra keyword will be passed to __init__ (e.g., decode_param_names).

body

Return the content of the request body.

body_file

Input stream of the request (wsgi.input). Setting this property resets the content_length and seekable flag (unlike setting req.body_file_raw).

body_file_raw

Gets and sets the wsgi.input key in the environment.

body_file_seekable

Get the body of the request (wsgi.input) as a seekable file-like object. Middleware and routing applications should use this attribute over .body_file.

If you access this value, CONTENT_LENGTH will also be updated.

cache_control

Get/set/modify the Cache-Control header (HTTP spec section 14.9)

call_application (*application*, *catch_exc_info=False*)

Call the given WSGI application, returning (status_string, headerlist, app_iter)

Be sure to call app_iter.close() if it's there.

If catch_exc_info is true, then returns (status_string, headerlist, app_iter, exc_info), where the fourth item may be None, but won't be if there was an exception. If you don't do this and there was an exception, the exception will be raised directly.

charset

Get the charset of the request.

If the request was sent with a charset parameter on the Content-Type, that will be used. Otherwise if there is a default charset (set during construction, or as a class attribute) that will be returned. Otherwise None.

Setting this property after request instantiation will always update Content-Type. Deleting the property updates the Content-Type to remove any charset parameter (if none exists, then deleting the property will do nothing, and there will be no error).

content_length

Gets and sets the Content-Length header (HTTP spec section 14.13). Converts it using int.

content_type

Return the content type, but leaving off any parameters (like charset, but also things like the type in application/atom+xml; type=entry)

If you set this property, you can include parameters, or if you don't include any parameters in the value then existing parameters will be preserved.

cookies

Like .str_cookies, but decodes values and keys

copy()

Copy the request and environment object.

This only does a shallow copy, except of wsgi.input

copy_body()

Copies the body, in cases where it might be shared with another request object and that is not desired.

This copies the body in-place, either into a StringIO object or a temporary file.

copy_get()

Copies the request and environment object, but turning this request into a GET along the way. If this was a POST request (or any other verb) then it becomes GET, and the request body is thrown away.

date

Gets and sets the Date header (HTTP spec section 14.8). Converts it using HTTP date.

classmethod from_file (*fp*)

Read a request from a file-like object (it must implement .read(size) and .readline()).

It will read up to the end of the request, not the end of the file (unless the request is a POST or PUT and has no Content-Length, in that case, the entire file is read).

This reads the request as represented by str(req); it may not read every valid HTTP request properly.

classmethod from_string(s)

Create a request from HTTP string. If the string contains extra data after the request, raise a ValueError.

get_response (application, catch_exc_info=False)

Like .call_application(application), except returns a response object with .status, .headers, and .body attributes.

This will use self.ResponseClass to figure out the class of the response object to return.

headers

All the request headers as a case-insensitive dictionary-like object.

host

Host name provided in HTTP_HOST, with fall-back to SERVER_NAME

host_url

The URL through the host (no path)

http_version

Gets and sets the SERVER_PROTOCOL key in the environment.

if_match

Gets and sets the If-Match header (HTTP spec section 14.24). Converts it as a Etag.

if_modified_since

Gets and sets the If-Modified-Since header (HTTP spec section 14.25). Converts it using HTTP date.

if_none_match

Gets and sets the If-None-Match header (HTTP spec section 14.26). Converts it as a Etag.

if_range

Gets and sets the If-Range header (HTTP spec section 14.27). Converts it using IfRange object.

if_unmodified_since

Gets and sets the If-Unmodified-Since header (HTTP spec section 14.28). Converts it using HTTP date.

is_body_readable

webob.is_body_readable is a flag that tells us that we can read the input stream even though CONTENT_LENGTH is missing. This allows FakeCGIBody to work and can be used by servers to support chunked encoding in requests. For background see https://bitbucket.org/ianb/webob/issue/6

is_body_seekable

Gets and sets the webob.is_body_seekable key in the environment.

is_response(*ob*)

Return True if the object passed as ob is a valid response object, False otherwise.

is_xhr

Is X-Requested-With header present and equal to XMLHttpRequest?

Note: this isn't set by every XMLHttpRequest request, it is only set if you are using a Javascript library that sets it (or you set the header yourself manually). Currently Prototype and jQuery are known to set this header.

make_body_seekable()

This forces environ ['wsgi.input'] to be seekable. That means that, the content is copied into a StringIO or temporary file and flagged as seekable, so that it will not be unnecessarily copied again.

After calling this method the .body_file is always seeked to the start of file and .content_length is not None.

The choice to copy to StringIO is made from self.request_body_tempfile_limit

make_tempfile()

Create a tempfile to store big request body. This API is not stable yet. A 'size' argument might be added.

max_forwards

Gets and sets the Max-Forwards header (HTTP spec section 14.31). Converts it using int.

method

Gets and sets the REQUEST_METHOD key in the environment.

model_url (resource, *elements, **kw)

Return the URL for the *resource* object named resource, using *elements and **kw as modifiers.

This is a convenience method. The result of calling pyramid.request.Request.resource_url() is the same as calling pyramid.url.resource_url() with an explicit request parameter.

The pyramid.request.Request.resource_url() method calls the pyramid.url.resource_url() function using the Request object as the request argument. The resource, *elements and *kw arguments passed to pyramid.request.Request.resource_url() are passed through to pyramid.url.resource_url() unchanged and its result is returned.

This call to pyramid.request.Request.resource_url():

request.resource_url(myresource)

Is completely equivalent to calling pyramid.url.resource_url() like this:

```
from pyramid.url import resource_url
resource_url(resource, request)
```

● For backwards compatibility purposes, this method can also be called as pyramid.request.Request.model_url().

params

Like .str_params, but decodes values and keys

path

The path of the request, without host or query string

path_info

Gets and sets the PATH_INFO key in the environment.

path_info_peek()

Returns the next segment on PATH_INFO, or None if there is no next segment. Doesn't modify the environment.

path_info_pop (pattern=None)

'Pops' off the next segment of PATH_INFO, pushing it onto SCRIPT_NAME, and returning the popped segment. Returns None if there is nothing left on PATH_INFO.

Does not return " when there's an empty segment (like /path//path); these segments are just ignored.

Optional pattern argument is a regexp to match the return value before returning. If there is no match, no changes are made to the request and None is returned.

path_qs

The path of the request, without host but with query string

path_url

The URL including SCRIPT_NAME and PATH_INFO, but not QUERY_STRING

postvars

Wraps a descriptor, with a deprecation warning or error

pragma

Gets and sets the Pragma header (HTTP spec section 14.32).

query_string

Gets and sets the QUERY_STRING key in the environment.

queryvars

Wraps a descriptor, with a deprecation warning or error

range

Gets and sets the Range header (HTTP spec section 14.35). Converts it using Range object.

referer

Gets and sets the Referer header (HTTP spec section 14.36).

referrer

Gets and sets the Referer header (HTTP spec section 14.36).

relative_url (other_url, to_application=False)

Resolve other_url relative to the request URL.

If to_application is True, then resolve it relative to the URL with only SCRIPT_NAME

remote_addr

Gets and sets the REMOTE_ADDR key in the environment.

remote_user

Gets and sets the REMOTE_USER key in the environment.

```
remove_conditional_headers (remove_encoding=True, remove_range=True, remove_match=True, remove_modified=True)
Remove headers that make the request conditional.
```

These headers can cause the response to be 304 Not Modified, which in some cases you may not want to be possible.

This does not remove headers like If-Match, which are used for conflict detection.

resource_url (*resource*, **elements*, ***kw*)

Return the URL for the *resource* object named resource, using *elements and **kw as modifiers.

This is a convenience method. The result of calling pyramid.request.Request.resource_url() is the same as calling pyramid.url.resource_url() with an explicit request parameter.

The pyramid.request.Request.resource_url() method calls the pyramid.url.resource_url() function using the Request object as the request argument. The resource, *elements and *kw arguments passed to pyramid.request.Request.resource_url() are passed through to pyramid.url.resource_url() unchanged and its result is returned.

This call to pyramid.request.Request.resource_url():

```
request.resource_url(myresource)
```

Is completely equivalent to calling pyramid.url.resource_url() like this:

```
from pyramid.url import resource_url
resource_url(resource, request)
```

• For backwards compatibility purposes, this method can also be called as pyramid.request.Request.model_url().

response

This attribute is actually a "reified" property which returns an instance of the pyramid.response.Response.class. The response object returned does not exist until this attribute is accessed. Once it is accessed, subsequent accesses will return the same Response object.

The request.response API is used by renderers. A render obtains the response object it will return from a view that uses that renderer by accessing request.response. Therefore, it's possible to use the request.response API to set up a response object with "the right" attributes (e.g. by calling request.response.set_cookie()) within a view that uses a renderer. Mutations to this response object will be preserved in the response sent to the client.

route_path(route_name, *elements, **kw)

Generates a path (aka a 'relative URL', a URL minus the host, scheme, and port) for a named Pyramid *route configuration*.

This is The convenience method. result of calling а pyramid.request.Request.route path() calling is the same as pyramid.url.route path() with an explicit request parameter.

This method accepts the same arguments as pyramid.request.Request.route_url() and performs the same duty. It just omits the host, port, and scheme information in the return value; only the script name, path, query parameters, and anchor data are present in the returned string.

The calls pyramid.request.Request.route_path() method the pyramid.url.route_path() function using the Request object as the argument. The *elements and *kw arguments passed request to pyramid.request.Request.route_path() are passed through to pyramid.url.route_path() unchanged and its result is returned.

This call to pyramid.request.Request.route_path():

```
request.route_path('foobar')
```

Is completely equivalent to calling pyramid.url.route_path() like this:

from pyramid.url import route_path
route_path('foobar', request)

See pyramid.url.route_path() for more information

route_url (route_name, *elements, **kw)

Return the URL for the route named route_name, using *elements and **kw as modifiers.

This is convenience method. The result of calling а pyramid.request.Request.route_url() is the calling same as pyramid.url.route_url() with an explicit request parameter.

The pyramid.request.Request.route_url() method calls the pyramid.url.route_url() function using the Request object as the request argument. The route_name, *elements and *kw arguments passed to pyramid.request.Request.route_url() are passed through to pyramid.url.route_url() unchanged and its result is returned.

This call to pyramid.request.Request.route_url():

```
request.route_url('route_name')
```

Is completely equivalent to calling pyramid.url.route_url() like this:

```
from pyramid.url import route_url
route_url('route_name', request)
```

scheme

Gets and sets the wsgi.url_scheme key in the environment.

script_name

Gets and sets the SCRIPT_NAME key in the environment.

server_name

Gets and sets the SERVER_NAME key in the environment.

server_port

Gets and sets the SERVER_PORT key in the environment. Converts it using int.

session

Obtain the *session* object associated with this request. If a *session factory* has not been registered during application configuration, a pyramid.exceptions.ConfigurationError will be raised

static_url(path, **kw)

Generates a fully qualified URL for a static *asset*. The asset must live within a location defined via the pyramid.config.Configurator.add_static_view() *configuration declaration directive* (see *Serving Static Assets*).

This is convenience method. The result of calling а pyramid.request.Request.static url() is the same calling as pyramid.url.static_url() with an explicit request parameter.

The pyramid.request.Request.static_url() method calls the pyramid.url.static_url() function using the Request object as the request argument. The *kw arguments passed to pyramid.request.Request.static_url() are passed through to pyramid.url.static_url() unchanged and its result is returned.

This call to pyramid.request.Request.static_url():

request.static_url('mypackage:static/foo.css')

Is completely equivalent to calling pyramid.url.static_url() like this:

```
from pyramid.url import static_url
static_url('mypackage:static/foo.css', request)
```

See pyramid.url.static_url() for more information

str_GET

Return a MultiDict containing all the variables from the QUERY_STRING.

str_POST

Return a MultiDict containing all the variables from a form request. Returns an empty dictlike object for non-form requests.

Form requests are typically POST requests, however PUT requests with an appropriate Content-Type are also supported.

str_cookies

Return a *plain* dictionary of cookies as found in the request.

str_params

A dictionary-like object containing both the parameters from the query string and request body.

str_postvars

Wraps a descriptor, with a deprecation warning or error

str_queryvars

Wraps a descriptor, with a deprecation warning or error

tmpl_context

Template context (for Pylons apps)

upath_info

upath_property('PATH_INFO')

url

The full request URL, including QUERY_STRING

urlargs

Return any positional variables matched in the URL.

Takes values from environ ['wsgiorg.routing_args']. Systems like routes set this value.

urlvars

Return any named variables matched in the URL.

Takes values from environ ['wsgiorg.routing_args']. Systems like routes set this value.

uscript_name

upath_property('SCRIPT_NAME')

user_agent

Gets and sets the User-Agent header (HTTP spec section 14.43).

• For information about the API of a *multidict* structure (such as that used as request.GET, request.POST, and request.params), see pyramid.interfaces.IMultiDict.

FIFTYONE

PYRAMID.RESPONSE

class Response (body=None, status=None, headerlist=None, app_iter=None, request=None, content_type=None, conditional_response=None, **kw)

RequestClass

alias of Request

accept_ranges

Gets and sets the Accept-Ranges header (HTTP spec section 14.5).

age

Gets and sets the Age header (HTTP spec section 14.6). Converts it using int.

allow

Gets and sets the Allow header (HTTP spec section 14.7). Converts it using list.

app_iter

Returns the app_iter of the response.

If body was set, this will create an app_iter from that body (a single-item list)

app_iter_range(start, stop)

Return a new app_iter built from the response app_iter, that serves up only the given start:stop range.

body

The body of the response, as a str. This will read in the entire app_iter if necessary.

body_file

A file-like object that can be used to write to the body. If you passed in a list app_iter, that app_iter will be modified by writes.

cache_control

Get/set/modify the Cache-Control header (HTTP spec section 14.9)

charset

Get/set the charset (in the Content-Type)

conditional_response_app (environ, start_response)

Like the normal __call__ interface, but checks conditional headers:

•If-Modified-Since (304 Not Modified; only on GET, HEAD)

•If-None-Match (304 Not Modified; only on GET, HEAD)

•Range (406 Partial Content; only on GET, HEAD)

content_disposition

Gets and sets the Content-Disposition header (HTTP spec section 19.5.1).

content_encoding

Gets and sets the Content-Encoding header (HTTP spec section 14.11).

content_language

Gets and sets the Content-Language header (HTTP spec section 14.12). Converts it using list.

content_length

Gets and sets the Content-Length header (HTTP spec section 14.17). Converts it using int.

content_location

Gets and sets the Content-Location header (HTTP spec section 14.14).

content_md5

Gets and sets the Content-MD5 header (HTTP spec section 14.14).

content_range

Gets and sets the Content-Range header (HTTP spec section 14.16). Converts it using ContentRange object.

content_type

Get/set the Content-Type header (or None), without the charset or any parameters.

If you include parameters (or ; at all) when setting the content_type, any existing parameters will be deleted; otherwise they will be preserved.

content_type_params

A dictionary of all the parameters in the content type.

(This is not a view, set to change, modifications of the dict would not be applied otherwise)

copy()

Makes a copy of the response

date

Gets and sets the Date header (HTTP spec section 14.18). Converts it using HTTP date.

delete_cookie (*key*, *path='/'*, *domain=None*)

Delete a cookie from the client. Note that path and domain must match how the cookie was originally set.

This sets the cookie to the empty string, and max_age=0 so that it should expire immediately.

encode_content (encoding='gzip', lazy=False)

Encode the content with the given encoding (only gzip and identity are supported).

environ

Get/set the request environ associated with this response, if any.

etag

Gets and sets the ETag header (HTTP spec section 14.19). Converts it using Entity tag.

expires

Gets and sets the Expires header (HTTP spec section 14.21). Converts it using HTTP date.

classmethod from_file (*fp*)

Reads a response from a file-like object (it must implement .read(size) and .readline()).

It will read up to the end of the response, not the end of the file.

This reads the response as represented by str(resp); it may not read every valid HTTP response properly. Responses must have a Content-Length

headerlist

The list of response headers

headers

The headers in a dictionary-like object

last_modified

Gets and sets the Last-Modified header (HTTP spec section 14.29). Converts it using HTTP date.

location

Gets and sets the Location header (HTTP spec section 14.30).

md5_etag (body=None, set_content_md5=False)

Generate an etag for the response object using an MD5 hash of the body (the body parameter, or self.body if not given)

Sets self.etag If set_content_md5 is True sets self.content_md5 as well

merge_cookies(resp)

Merge the cookies that were set on this response with the given *resp* object (which can be any WSGI application).

If the *resp* is a webob. Response object, then the other object will be modified in-place.

pragma

Gets and sets the Pragma header (HTTP spec section 14.32).

request

Return the request associated with this response if any.

retry_after

Gets and sets the Retry-After header (HTTP spec section 14.37). Converts it using HTTP date or delta seconds.

server

Gets and sets the Server header (HTTP spec section 14.38).

status

The status string

status_code

Wraps a descriptor, with a deprecation warning or error

status_int

The status as an integer

ubody

Alias for unicode_body

unicode_body

Get/set the unicode value of the body (using the charset of the Content-Type)

unset_cookie(key, strict=True)

Unset a cookie with the given name (remove it from the response).

vary

Gets and sets the Vary header (HTTP spec section 14.44). Converts it using list.

www_authenticate

Gets and sets the WWW-Authenticate header (HTTP spec section 14.47). Converts it using parse_auth and serialize_auth.

FIFTYTWO

PYRAMID.SCRIPTING

get_root (app, request=None)

Return a tuple composed of (root, closer) when provided a *router* instance as the app argument. The root returned is the application root object. The closer returned is a callable (accepting no arguments) that should be called when your scripting application is finished using the root.

request is passed to the Pyramid application root factory to compute the root. If request is None, a default will be constructed using the registry's *Request Factory* via the pyramid.interfaces.IRequestFactory.blank() method.

prepare (request=None, registry=None)

This function pushes data onto the Pyramid threadlocal stack (request and registry), making those objects 'current'. It returns a dictionary useful for bootstrapping a Pyramid application in a scripting environment.

request is passed to the Pyramid application root factory to compute the root. If request is None, a default will be constructed using the registry's *Request Factory* via the pyramid.interfaces.IRequestFactory.blank() method.

If registry is not supplied, the last registry loaded from pyramid.config.global_registries will be used. If you have loaded more than one Pyramid application in the current process, you may not want to use the last registry loaded, thus you can search the global_registries and supply the appropriate one based on your own criteria.

The function returns a dictionary composed of root, closer, registry, request and root_factory. The root returned is the application's root resource object. The closer returned is a callable (accepting no arguments) that should be called when your scripting application is finished using the root. registry is the registry object passed or the last registry loaded into pyramid.config.global_registries if no registry is passed. request is the request object passed or the constructed request if no request is passed. root_factory is the root factory used to construct the root.

FIFTYTHREE

PYRAMID.SECURITY

53.1 Authentication API Functions

authenticated_userid(request)

Return the userid of the currently authenticated user or None if there is no *authentication policy* in effect or there is no currently authenticated user.

unauthenticated_userid(request)

Return an object which represents the *claimed* (not verified) user id of the credentials present in the request. None if there is no *authentication policy* in effect or there is no user data associated with the current request. This differs from authenticated_userid(), because the effective authentication policy will not ensure that a record associated with the userid exists in persistent storage.

effective_principals(request)

Return the list of 'effective' *principal* identifiers for the request. This will include the userid of the currently authenticated user if a user is currently authenticated. If no *authentication policy* is in effect, this will return an empty sequence.

forget (request)

Return a sequence of header tuples (e.g. [('Set-Cookie', 'foo=abc')]) suitable for 'forgetting' the set of credentials possessed by the currently authenticated user. A common usage might look like so within the body of a view function (response is assumed to be an *WebOb* -style *response* object computed previously by the view code):

```
from pyramid.security import forget
headers = forget(request)
response.headerlist.extend(headers)
return response
```

If no *authentication policy* is in use, this function will always return an empty sequence.

remember (*request*, *principal*, **kw)

Return a sequence of header tuples (e.g. [('Set-Cookie', 'foo=abc')]) suitable for 'remembering' a set of credentials implied by the data passed as principal and *kw using the current *authentication policy*. Common usage might look like so within the body of a view function (response is assumed to be a *WebOb* -style *response* object computed previously by the view code):

```
from pyramid.security import remember
headers = remember(request, 'chrism', password='123', max_age='86400')
response.headerlist.extend(headers)
return response
```

If no *authentication policy* is in use, this function will always return an empty sequence. If used, the composition and meaning of **kw must be agreed upon by the calling code and the effective authentication policy.

53.2 Authorization API Functions

has_permission (permission, context, request)

Provided a permission (a string or unicode object), a context (a *resource* instance) and a request object, return an instance of pyramid.security.Allowed if the permission is granted in this context to the user implied by the request. Return an instance of pyramid.security.Denied if this permission is not granted in this context to this user. This function delegates to the current authentication and authorization policies. Return pyramid.security.Allowed unconditionally if no authentication policy has been configured in this application.

principals_allowed_by_permission(context, permission)

Provided a context (a resource object), and a permission (a string or unicode object), if a *authorization policy* is in effect, return a sequence of *principal* ids that possess the permission in the context. If no authorization policy is in effect, this will return a sequence with the single value pyramid.security.Everyone (the special principal identifier representing all principals).

• even if an *authorization policy* is in effect, some (exotic) authorization policies may not implement the required machinery for this function; those will cause a NotImplementedError exception to be raised when this function is invoked.

view_execution_permitted(context, request, name='')

If the view specified by context and name is protected by a *permission*, check the permission associated with the view using the effective authentication/authorization policies and the request. Return a boolean result. If no *authorization policy* is in effect, or if the view is not protected by a permission, return True.

53.3 Constants

Everyone

The special principal id named 'Everyone'. This principal id is granted to all requests. Its actual value is the string 'system.Everyone'.

Authenticated

The special principal id named 'Authenticated'. This principal id is granted to all requests which contain any other non-Everyone principal id (according to the *authentication policy*). Its actual value is the string 'system.Authenticated'.

ALL_PERMISSIONS

An object that can be used as the permission member of an ACE which matches all permissions unconditionally. For example, an ACE that uses ALL_PERMISSIONS might be composed like so: ('Deny', 'system.Everyone', ALL_PERMISSIONS).

DENY_ALL

A convenience shorthand ACE that defines ('Deny', 'system.Everyone', ALL_PERMISSIONS). This is often used as the last ACE in an ACL in systems that use an "inheriting" security policy, representing the concept "don't inherit any other ACEs".

53.4 Return Values

Allow

The ACE "action" (the first element in an ACE e.g. (Allow, Everyone, 'read') that means allow access. A sequence of ACEs makes up an ACL. It is a string, and it's actual value is "Allow".

Deny

The ACE "action" (the first element in an ACE e.g. (Deny, 'george', 'read') that means deny access. A sequence of ACEs makes up an ACL. It is a string, and it's actual value is "Deny".

class ACLDenied

An instance of ACLDenied represents that a security check made explicitly against ACL was denied. It evaluates equal to all boolean false types. It also has the following attributes: acl, ace, permission, principals, and context. These attributes indicate the security values involved in the request. Its __str__ method prints a summary of these attributes for debugging purposes. The same summary is available as the msg attribute.

class ACLAllowed

An instance of ACLAllowed represents that a security check made explicitly against ACL was allowed. It evaluates equal to all boolean true types. It also has the following attributes: acl, ace, permission, principals, and context. These attributes indicate the security values involved in the request. Its __str__ method prints a summary of these attributes for debugging purposes. The same summary is available as the msg attribute.

class Denied

An instance of Denied is returned when a security-related API or other Pyramid code denies an action unrelated to an ACL check. It evaluates equal to all boolean false types. It has an attribute named msg describing the circumstances for the deny.

class Allowed

An instance of Allowed is returned when a security-related API or other Pyramid code allows an action unrelated to an ACL check. It evaluates equal to all boolean true types. It has an attribute named msg describing the circumstances for the allow.

FIFTYFOUR

PYRAMID.SETTINGS

get_settings()

Return a *deployment settings* object for the current application. The object is a dictionary-like object that contains key/value pairs based on the dictionary passed as the settings argument to the pyramid.config.Configurator constructor or the pyramid.router.make_app() API.

This method is deprecated as of Pyramid 1.0. Use pyramid.threadlocal.get_current_registry().settings instead or use the settings attribute of the registry available from the request (request.registry.settings).

asbool(s)

Return the boolean value True if the case-lowered value of string input s is any of t, true, y, on, or 1, otherwise return the boolean value False. If s is the value None, return False. If s is already one of the boolean values True or False, return it.

FIFTYFIVE

PYRAMID.TESTING

setUp (registry=None, request=None, hook_zca=True, autocommit=True, settings=None) Set Pyramid registry and request thread locals for the duration of a single unit test.

Use this function in the setUp method of a unittest test case which directly or indirectly uses:

•any method of the pyramid.config.Configurator object returned by this function.

•the pyramid.threadlocal.get_current_registry() or pyramid.threadlocal.get_current_request() functions.

If you use the get_current_* functions (or call Pyramid code that uses these functions) without calling setUp, pyramid.threadlocal.get_current_registry() will return a *global application registry*, which may cause unit tests to not be isolated with respect to registrations they perform.

If the registry argument is None, a new empty *application registry* will be created (an instance of the pyramid.registry.Registry class). If the registry argument is not None, the value passed in should be an instance of the pyramid.registry.Registry class or a suitable testing analogue.

After is finished. the registry returned by the setUp pyramid.threadlocal.get_current_request() function will be the passed (or constructed) registry until pyramid.testing.tearDown() called is (or pyramid.testing.setUp() is called again).

If the hook_zca argument is True, setUp will attempt to perform the operation zope.component.getSiteManager.sethook(pyramid.threadlocal.get_current_registry), which will cause the *Zope Component Architecture* global API (e.g. zope.component.getSiteManager(), zope.component.getAdapter(), and so on) to use the registry constructed by setUp as the value it returns from zope.component.getSiteManager(). If the zope.component package cannot be imported, or if hook_zca is False, the hook will not be set.

If settings is not None, it must be a dictionary representing the values passed to a Configurator as its settings = argument.

This function returns an instance of the pyramid.config.Configurator class, which can be used for further configuration to set up an environment suitable for a unit or integration test. The registry attribute attached to the Configurator instance represents the 'current' *application registry*; the same registry will be returned by pyramid.threadlocal.get_current_registry() during the execution of the test.

tearDown (unhook_zca=True)

Undo the effects pyramid.testing.setUp(). Use this function in the tearDown method of a unit test that uses pyramid.testing.setUp() in its setUp method.

If the unhook_zca argument is True (the default), call zope.component.getSiteManager.reset(). This undoes the action of pyramid.testing.setUp() called with the argument hook_zca=True. If zope.component cannot be imported, ignore the argument.

cleanUp(*arg, **kw)

pyramid.testing.cleanUp() is an alias for pyramid.testing.setUp().

class DummyResource (*___name___=None*, *___parent___=None*, *___provides___=None*, **kw) A dummy Pyramid *resource* object.

clone (*__name__*=*<object object at 0x4c66a80>*, *__parent__*=*<object object at 0x4c66a80>*, ***kw*)

Create a clone of the resource object. If <u>__name__</u> or <u>__parent__</u> arguments are passed, use these values to override the existing <u>__name__</u> or <u>__parent__</u> of the resource. If any extra keyword args are passed in via the kw argument, use these keywords to add to or override existing resource keywords (attributes).

items()

Return the items set by __setitem__

keys()

Return the keys set by __setitem__

values()

Return the values set by __setitem__

class DummyRequest (params=None, environ=None, headers=None, path='/', cookies=None, post=None, **kw)

A DummyRequest object (incompletely) imitates a request object.

The params, environ, headers, path, and cookies arguments correspond to their *WebOb* equivalents.

The post argument, if passed, populates the request's POST attribute, but *not* params, in order to allow testing that the app accepts data for a given view only from POST requests. This argument also sets self.method to "POST".

Extra keyword arguments are assigned as attributes of the request itself.

Note that DummyRequest does not have complete fidelity with a "real" request. For example, by default, the DummyRequest GET and POST attributes are of type dict, unlike a normal Request's GET and POST, which are of type MultiDict. If your code uses the features of MultiDict, you should either use a "real" pyramid.request.Request or adapt your DummyRequest by replacing the attributes with MultiDict instances.

Other similar incompatibilities exist. If you need all the features of a Request, use the pyramid.request.Request class itself rather than this class while writing tests.

class DummyTemplateRenderer (string_response='')

An instance of this class is returned from pyramid.config.Configurator.testing_add_renderer It has a helper function (assert_) that makes it possible to make an assertion which compares data passed to the renderer by the view function against expected key/value pairs.

$assert_(**kw)$

Accept an arbitrary set of assertion key/value pairs. For each assertion key/value pair assert that the renderer (eg. pyramid.renderer.render_to_response()) received the key with a value that equals the asserted value. If the renderer did not receive the key at all, or the value received by the renderer doesn't match the assertion value, raise an AssertionError.

FIFTYSIX

PYRAMID. THREADLOCAL

get_current_request()

Return the currently active request or None if no request is currently active.

This function should be used *extremely sparingly*, usually only in unit testing code. it's almost always usually a mistake to use get_current_request outside a testing context because its usage makes it possible to write code that can be neither easily tested nor scripted.

get_current_registry()

Return the currently active *application registry* or the global application registry if no request is currently active.

This function should be used *extremely sparingly*, usually only in unit testing code. it's almost always usually a mistake to use get_current_registry outside a testing context because its usage makes it possible to write code that can be neither easily tested nor scripted.

FIFTYSEVEN

PYRAMID. TRAVERSAL

find_interface (resource, class_or_interface)

Return the first resource found in the *lineage* of resource which, a) if class_or_interface is a Python class object, is an instance of the class or any subclass of that class or b) if class_or_interface is a *interface*, provides the specified interface. Return None if no resource providing interface_or_class can be found in the lineage. The resource passed in *must* be *location*-aware.

find_resource(resource, path)

Given a resource a string or tuple representing a path object and (such as the return value of pyramid.traversal.resource_path() or pyramid.traversal.resource path tuple()), return a resource in this application's resource tree at the specified path. The resource passed in *must* be *location*-aware. If the path cannot be resolved (if the respective node in the resource tree does not exist), a KeyError will be raised.

This function is the logical inverse of pyramid.traversal.resource_path() and pyramid.traversal.resource_path_tuple(); it can resolve any path string or tuple generated by either of those functions.

Rules for passing a *string* as the path argument: if the first character in the path string is the with the / character, the path will considered absolute and the resource tree traversal will start at the root resource. If the first character of the path string is *not* the / character, the path is considered relative and resource tree traversal will begin at the resource object supplied to the function as the resource argument. If an empty string is passed as path, the resource passed in will be returned. Resource path strings must be escaped in the following manner: each Unicode path segment must be encoded as UTF-8 and as each path segment must escaped via Python's urllib.quote. For example,

/path/to%20the/La%20Pe%C3%B1a (absolute) or to%20the/La%20Pe%C3%B1a (relative). The pyramid.traversal.resource_path() function generates strings which follow these rules (albeit only absolute ones).

Rules for passing a *tuple* as the path argument: if the first element in the path tuple is the empty string (for example (", 'a', 'b', 'c'), the path is considered absolute and the resource tree traversal will start at the resource tree root object. If the first element in the path tuple is not the empty string (for example ('a', 'b', 'c')), the path is considered relative and resource tree traversal will begin at the resource object supplied to the function as the resource argument. If an empty sequence is passed as path, the resource passed in itself will be returned. No URL-quoting or UTF-8-encoding of individual path segments within the tuple is required (each segment may be any string or unicode object representing a resource name). Resource path tuples generated by pyramid.traversal.resource_path_tuple() can always be resolved by find_resource.

• For backwards compatibility purposes, this function can also be imported as pyramid.traversal.find_model(), although doing so will emit a deprecation warning.

find_root (resource)

Find the root node in the resource tree to which resource belongs. Note that resource should be *location*-aware. Note that the root resource is available in the request object by accessing the request.root attribute.

resource_path (resource, *elements)

Return a string object representing the absolute physical path of the resource object based on its position in the resource tree, e.g /foo/bar. Any positional arguments passed in as elements will be appended as path segments to the end of the resource path. For instance, if the resource's path is /foo/bar and elements equals ('a', 'b'), the returned string will be /foo/bar/a/b. The first character in the string will always be the / character (a leading / character in a path string represents that the path is absolute).

Resource path strings returned will be escaped in the following manner: each unicode path segment will be encoded as UTF-8 and each path segment will be escaped via Python's urllib.quote. For example, /path/to%20the/La%20Pe%C3%B1a.

This function is a logical inverse of pyramid.traversal.find_resource: it can be used to generate path references that can later be resolved via that function.

The resource passed in *must* be *location*-aware.

• Each segment in the path string returned will use the __name__ attribute of the resource it represents within the resource tree. Each of these segments *should* be a unicode or string object (as per the contract of *location*-awareness). However, no conversion or safety checking of resource names is performed. For instance, if one of the resources in your tree has a __name__ which (by error) is a dictionary, the pyramid.traversal.resource_path() function will attempt to append it to a string and it will cause a pyramid.exceptions.URLDecodeError.

● The *root* resource *must* have a _____attribute with a value of either None or the empty string for paths to be generated properly. If the root resource has a non-null _____name___ attribute, its name will be prepended to the generated path rather than a single leading '/' character.

• For backwards compatibility purposes, this function can also be imported as model_path, although doing so will cause a deprecation warning to be emitted.

resource_path_tuple(resource, *elements)

Return a tuple representing the absolute physical path of the resource object based on its position in a resource tree, e.g (", 'foo', 'bar'). Any positional arguments passed in as elements will be appended as elements in the tuple representing the resource path. For instance, if the resource's path is (", 'foo', 'bar') and elements equals ('a', 'b'), the returned tuple will be (", 'foo', 'bar', 'a', 'b'). The first element of this tuple will always be the empty string (a leading empty string element in a path tuple represents that the path is absolute).

This function is a logical inverse of pyramid.traversal.find_resource(): it can be used to generate path references that can later be resolved by that function.

The resource passed in *must* be *location*-aware.

i Each segment in the path tuple returned will equal the <u>__name__</u> attribute of the resource it represents within the resource tree. Each of these segments *should* be a unicode or string object (as per the contract of *location*-awareness). However, no conversion or safety checking of resource names is performed. For instance, if one of the resources in your tree has a <u>__name__</u> which (by error) is a dictionary, that dictionary will be placed in the path tuple; no warning or error will be given. ● The *root* resource *must* have a __name__ attribute with a value of either None or the empty string for path tuples to be generated properly. If the root resource has a non-null __name__ attribute, its name will be the first element in the generated path tuple rather than the empty string.

U For backwards compatibility purposes, this function can also be imported as model_path_tuple, although doing so will cause a deprecation warning to be emitted.

quote_path_segment (segment, safe='')

Return a quoted representation of a 'path segment' (such as the string ___name__ attribute of a resource) as a string. If the segment passed in is a unicode object, it is converted to a UTF-8 string, then it is URL-quoted using Python's urllib.quote. If the segment passed in is a string, it is URL-quoted using Python's urllib.quote. If the segment passed in is not a string or unicode object, an error will be raised. The return value of quote_path_segment is always a string, never Unicode.

You may pass a string of characters that need not be encoded as the safe argument to this function. This corresponds to the safe argument to urllib.quote.

• The return value for each segment passed to this function is cached in a module-scope dictionary for speed: the cached version is returned when possible rather than recomputing the quoted version. No cache emptying is ever done for the lifetime of an application, however. If you pass arbitrary user-supplied strings to this function (as opposed to some bounded set of values from a 'working set' known to your application), it may become a memory leak.

virtual_root (resource, request)

Provided any *resource* and a *request* object, return the resource object representing the *virtual root* of the current *request*. Using a virtual root in a *traversal* -based Pyramid application permits rooting, for example, the resource at the traversal path /cms at http://example.com/instead of rooting it at http://example.com/cms/.

If the resource passed in is a context obtained via *traversal*, and if the HTTP_X_VHM_ROOT key is in the WSGI environment, the value of this key will be treated as a 'virtual root path': the pyramid.traversal.find_resource() API will be used to find the virtual root resource using this path; if the resource is found, it will be returned. If the HTTP_X_VHM_ROOT key is is not present in the WSGI environment, the physical *root* of the resource tree will be returned instead.

Virtual roots are not useful at all in applications that use *URL dispatch*. Contexts obtained via URL dispatch don't really support being virtually rooted (each URL dispatch context is both its own physical and virtual root). However if this API is called with a resource argument which is a context obtained via URL dispatch, the resource passed in will be returned unconditionally.

traverse (*resource*, *path*)

Given a resource object as resource and a string or tuple representing a path as path (such as the return value of pyramid.traversal.resource_path() or pyramid.traversal.resource_path_tuple() or the value of request.environ['PATH_INFO']), return a dictionary with the keys context, root, view_name, subpath, traversed, virtual_root, and virtual_root_path.

A definition of each value in the returned dictionary:

- •context: The *context* (a *resource* object) found via traversal or url dispatch. If the path passed in is the empty string, the value of the resource argument passed to this function is returned.
- •root: The resource object at which *traversal* begins. If the resource passed in was found via url dispatch or if the path passed in was relative (non-absolute), the value of the resource argument passed to this function is returned.
- •view_name: The view name found during traversal or url dispatch; if the resource was found via traversal, this is usually a representation of the path segment which directly follows the path to the context in the path. The view_name will be a Unicode object or the empty string. The view_name will be the empty string if there is no element which follows the context path. An example: if the path passed is /foo/bar, and a resource object is found at /foo (but not at /foo/bar), the 'view name' will be u' bar'. If the resource was found via urldispatch, the view_name will be the name the route found was registered with.
- •subpath: For a resource found via *traversal*, this is a sequence of path segments found in the path that follow the view_name (if any). Each of these items is a Unicode object. If no path segments follow the view_name, the subpath will be the empty sequence. An example: if the path passed is /foo/bar/baz/buz, and a resource object is found at /foo (but not /foo/bar), the 'view name' will be u' bar' and the *subpath* will be [u' baz', u' buz']. For a resource found via url dispatch, the subpath will be a sequence of values discerned from *subpath in the route pattern matched or the empty sequence.
- •traversed: The sequence of path elements traversed from the root to find the context object during *traversal*. Each of these items is a Unicode object. If no path segments were traversed to find the context object (e.g. if the path provided is the empty string), the traversed value will be the empty sequence. If the resource is a resource found via *url dispatch*, traversed will be None.
- •virtual_root: A resource object representing the 'virtual' root of the resource tree being traversed during *traversal*. See *Virtual Hosting* for a definition of the virtual root object. If no virtual hosting is in effect, and the path passed in was absolute, the virtual_root will be the *physical* root resource object (the object at which *traversal* begins). If the resource passed in was found via *URL dispatch* or if the path passed in was relative, the virtual_root will always equal the root object (the resource passed in).

•virtual_root_path – If *traversal* was used to find the resource, this will be the sequence of path elements traversed to find the virtual_root resource. Each of these items is a Unicode object. If no path segments were traversed to find the virtual_root resource (e.g. if virtual hosting is not in effect), the traversed value will be the empty list. If url dispatch was used to find the resource, this will be None.

If the path cannot be resolved, a KeyError will be raised.

Rules for passing a *string* as the path argument: if the first character in the path string is the with the / character, the path will considered absolute and the resource tree traversal will start at the root resource. If the first character of the path string is *not* the / character, the path is considered relative and resource tree traversal will begin at the resource object supplied to the function as the resource argument. If an empty string is passed as path, the resource passed in will be returned. Resource path strings must be escaped in the following manner: each Unicode path segment must be encoded as UTF-8 and each path segment must escaped via Python's urllib.quote. For example, /path/to%20the/La%20Pe%C3%B1a (absolute) or to%20the/La%20Pe%C3%B1a (relative). The pyramid.traversal.resource_path() function generates strings which follow these rules (albeit only absolute ones).

Rules for passing a *tuple* as the path argument: if the first element in the path tuple is the empty string (for example (", 'a', 'b', 'c'), the path is considered absolute and the resource tree traversal will start at the resource tree root object. If the first element in the path tuple is not the empty string (for example ('a', 'b', 'c')), the path is considered relative and resource tree traversal will begin at the resource object supplied to the function as the resource argument. If an empty sequence is passed as path, the resource passed in itself will be returned. No URL-quoting or UTF-8-encoding of individual path segments within the tuple is required (each segment may be any string or unicode object representing a resource name).

Explanation of the conversion of path segment values to Unicode during traversal: Each segment is URL-unquoted, and decoded into Unicode. Each segment is assumed to be encoded using the UTF-8 encoding (or a subset, such as ASCII); a pyramid.exceptions.URLDecodeError is raised if a segment cannot be decoded. If a segment name is empty or if it is ., it is ignored. If a segment name is ..., the previous segment is deleted, and the ... is ignored. As a result of this process, the return values view_name, each element in the subpath, each element in traversed, and each element in the virtual_root_path will be Unicode as opposed to a string, and will be URL-decoded.

traversal_path(path)

Given a PATH_INFO string (slash-separated path segments), return a tuple representing that path which can be used to traverse a resource tree.

The PATH_INFO is split on slashes, creating a list of segments. Each segment is URL-unquoted, and subsequently decoded into Unicode. Each segment is assumed to be encoded using the UTF-8

encoding (or a subset, such as ASCII); a pyramid.exceptions.URLDecodeError is raised if a segment cannot be decoded. If a segment name is empty or if it is ., it is ignored. If a segment name is .., the previous segment is deleted, and the .. is ignored.

If this function is passed a Unicode object instead of a string, that Unicode object *must* directly encodeable to ASCII. For example, u'/foo' will work but u'/
unicode>' (a Unicode object with characters that cannot be encoded to ascii) will not.

Examples:

```
/
()
/foo/bar/baz
  (u'foo', u'bar', u'baz')
foo/bar/baz
  (u'foo', u'bar', u'baz')
/foo/bar/baz/
  (u'foo', u'bar', u'baz')
/foo/bar/baz/..
  (u'foo', u'bar')
/foo/bar/baz/..
  (u'foo', u'bar')
/my%20archives/hello
  (u'my archives', u'hello')
```

```
/archives/La%20Pe%C3%B1a
```

(u'archives', u'<unprintable unicode>')

0 This function does not generate the same type of tuples that pyramid.traversal.resource_path_tuple() In particular, does. the leading empty string is not present in the tuple it returns, unlike tureturned by pyramid.traversal.resource_path_tuple(). As ples a result. tuples generated by traversal_path are not resolveable by the pyramid.traversal.find_resource() API. traversal_path is a function mostly used by the internals of Pyramid and by people writing their own traversal machinery, as opposed to users writing applications in Pyramid.

FIFTYEIGHT

PYRAMID.URL

Utility functions for dealing with URLs in pyramid

resource_url (*context*, *request*, **elements*, *query=None*, *anchor=None*)

Generate a string representing the absolute URL of the *resource* object based on the wsgi.url_scheme, HTTP_HOST or SERVER_NAME in the request, plus any SCRIPT_NAME. The overall result of this function is always a UTF-8 encoded string (never Unicode).

Calling pyramid.Request.resource_url() can be used to achieve the same result as pyramid.url.resource_url().

Examples:

Any positional arguments passed in as elements must be strings Unicode objects, or integer objects. These will be joined by slashes and appended to the generated resource URL. Each of the elements passed in is URL-quoted before being appended; if any element is Unicode, it will converted to a UTF-8 bytestring before being URL-quoted. If any element is an integer, it will be converted to its string representation before being URL-quoted.

if no elements arguments are specified, the resource URL will end with a trailing slash. If any elements are used, the generated URL will *not* end in trailing a slash.

If a keyword argument query is present, it will be used to compose a query string that will be tacked on to the end of the URL. The value of query must be a sequence of two-tuples *or* a data structure with an .items() method that returns a sequence of two-tuples (presumably a dictionary). This data structure will be turned into a query string per the documentation of pyramid.url.urlencode function. After the query data is turned into a query string, a leading ? is prepended, and the resulting string is appended to the generated URL.

• Python data structures that are passed as query which are sequences or dictionaries are turned into a string under the same rules as when run through urllib.urlencode() with the doseq argument equal to True. This means that sequences can be passed as values, and a k=v pair will be placed into the query string for each value.

If a keyword argument anchor is present, its string representation will be used as a named anchor in the generated URL (e.g. if anchor is passed as foo and the resource URL is http://example.com/resource/url, the resulting generated URL will be http://example.com/resource/url#foo).

U If anchor is passed as a string, it should be UTF-8 encoded. If anchor is passed as a Unicode object, it will be converted to UTF-8 before being appended to the URL. The anchor value is not quoted in any way before being appended to the generated URL.

If both anchor and query are specified, the anchor element will always follow the query element, e.g. http://example.com?foo=1#bar.

If the resource passed in has a __resource_url__ method, it will be used to generate the URL (scheme, host, port, path) that for the base resource which is operated upon by this function. See also *Overriding Resource URL Generation*.

U If the *resource* used is the result of a *traversal*, it must be *location*-aware. The resource can also be the context of a *URL dispatch*; contexts found this way do not need to be location-aware.

■ If a 'virtual root path' is present in the request environment (the value of the WSGI environ key HTTP_X_VHM_ROOT), and the resource was obtained via *traversal*, the URL path will not include the virtual root prefix (it will be stripped off the left hand side of the generated URL).

• For backwards compatibility purposes, this function can also be imported as model_url, although doing so will emit a deprecation warning.

route_url (route_name, request, *elements, **kw)

Generates a fully qualified URL for a named Pyramid *route configuration*.

Calling pyramid.Request.route_url() can be used to achieve the same result as pyramid.url.route_url().

Use the route's name as the first positional argument. Use a request object as the second positional argument. Additional positional arguments are appended to the URL as path segments after it is generated.

Use keyword arguments to supply values which match any dynamic path elements in the route definition. Raises a KeyError exception if the URL cannot be generated for any reason (not enough arguments, for example).

For example, if you've defined a route named "foobar" with the path {foo}/{bar}/*traverse:

Values replacing : segment arguments can be passed as strings or Unicode objects. They will be encoded to UTF-8 and URL-quoted before being placed into the generated URL.

Values replacing *remainder arguments can be passed as strings *or* tuples of Unicode/string values. If a tuple is passed as a *remainder replacement value, its values are URL-quoted and encoded to UTF-8. The resulting strings are joined with slashes and rendered into the URL. If a string is passed as a *remainder replacement value, it is tacked on to the URL untouched.

If a keyword argument _query is present, it will be used to compose a query string that will be tacked on to the end of the URL. The value of _query must be a sequence of two-tuples *or* a data structure with an .items() method that returns a sequence of two-tuples (presumably a dictionary). This data structure will be turned into a query string per the documentation of pyramid.encode.urlencode() function. After the query data is turned into a query string, a leading ? is prepended, and the resulting string is appended to the generated URL.

• Python data structures that are passed as _query which are sequences or dictionaries are turned into a string under the same rules as when run through urllib.urlencode() with the doseq argument equal to True. This means that sequences can be passed as values, and a k=v pair will be placed into the query string for each value.

If a keyword argument _anchor is present, its string representation will be used as a named anchor in the generated URL (e.g. if _anchor is passed as foo and the route URL is http://example.com/route/url, the resulting generated URL will be http://example.com/route/url#foo).

U If _anchor is passed as a string, it should be UTF-8 encoded. If _anchor is passed as a Unicode object, it will be converted to UTF-8 before being appended to the URL. The anchor value is not quoted in any way before being appended to the generated URL.

If both _anchor and _query are specified, the anchor element will always follow the query element, e.g. http://example.com?foo=1#bar.

If keyword _app_url will а is present, it be used as the protocol/hostname/port/leading path prefix of the generated URL. For example, using app url of http://example.com:8080/foo would cause the URL an http://example.com:8080/foo/fleeb/flub to be returned from this function if the expansion of the route pattern associated with the route_name expanded to /fleeb/flub. If app url is not specified, the result of request, application url will be used as the prefix (the default).

This function raises a KeyError if the URL cannot be generated due to missing replacement names. Extra replacement names are ignored.

If the route object which matches the route_name argument has a *pregenerator*, the *elements and **kw arguments arguments passed to this function might be augmented or changed.

current_route_url (request, *elements, **kw)

Generates a fully qualified URL for a named Pyramid *route configuration* based on the 'current route'.

This function supplements pyramid.url.route_url(). It presents an easy way to generate a URL for the 'current route' (defined as the route which matched when the request was generated).

The arguments to this function have the same meaning as those with the same names passed to pyramid.url.route_url(). It also understands an extra argument which route_url does not named _route_name.

The route name used to generate a URL is taken from either the _route_name keyword argument or the name of the route which is currently associated with the request if _route_name was not passed. Keys and values from the current request *matchdict* are combined with the kw arguments to form a set of defaults named newkw. Then route_url(route_name, request, *elements, **newkw) is called, returning a URL.

Examples follow.

If the 'current route' has the route pattern /foo/{page} and the current url path is /foo/1, the matchdict will be {'page':'1'}. The result of current_route_url(request) in this situation will be /foo/1.

If the 'current route' has the route pattern /foo/{page} and the current url path is /foo/1, the matchdict will be {'page':'1'}. The result of current_route_url(request, page='2') in this situation will be /foo/2.

Usage of the _route_name keyword argument: if our routing table defines routes /foo/{action} named 'foo' and /foo/{action}/{page} named fooaction, and the current url pattern is /foo/view (which has matched the /foo/{action} route), we may want to use the matchdict args to generate a URL to the fooaction route. In this scenario, current_route_url(request, _route_name='fooaction', page='5') Will return string like: /foo/view/5.

route_path (route_name, request, *elements, **kw)

Generates a path (aka a 'relative URL', a URL minus the host, scheme, and port) for a named Pyramid *route configuration*.

Calling pyramid.Request.route_path() can be used to achieve the same result as pyramid.url.route_path().

This function accepts the same argument as pyramid.url.route_url() and performs the same duty. It just omits the host, port, and scheme information in the return value; only the script_name, path, query parameters, and anchor data are present in the returned string.

For example, if you've defined a route named 'foobar' with the path $/ \{ foo \} / \{ bar \}$, this call to route_path:

route_path('foobar', request, foo='1', bar='2')

Will return the string /1/2.

Calling route_path('route', request) is the same as calling route_url('route', request, _app_url=request.script_name). route_path is, in fact, implemented in terms of route_url in just this way. As a result, any _app_url passed within the **kw values to route_path will be ignored.

static_url (path, request, **kw)

Generates a fully qualified URL for a static *asset*. The asset must live within a location defined via the pyramid.config.Configurator.add_static_view() *configuration declaration* (see *Serving Static Assets*).

Calling pyramid.Request.static_url() can be used to achieve the same result as pyramid.url.static_url().

Example:

static_url('mypackage:static/foo.css', request) =>

http://example.com/static/foo.css

The path argument points at a file or directory on disk which a URL should be generated for. The path may be either a relative path (e.g. static/foo.css) or a *asset specification* (e.g. mypackage:static/foo.css). A path may not be an absolute filesystem path (a ValueError will be raised if this function is supplied with an absolute path).

The request argument should be a *request* object.

The purpose of the **kw argument is the same as the purpose of the pyramid.url.route_url() **kw argument. See the documentation for that function to understand the arguments which you can provide to it. However, typically, you don't need to pass anything as *kw when generating a static asset URL.

This function raises a ValueError if a static view definition cannot be found which matches the path specification.

urlencode (query, doseq=True)

An alternate implementation of Python's stdlib urllib.urlencode function which accepts unicode keys and values within the query dict/sequence; all Unicode keys and values are first converted to UTF-8 before being used to compose the query string.

The value of query must be a sequence of two-tuples representing key/value pairs *or* an object (often a dictionary) with an .items() method that returns a sequence of two-tuples representing key/value pairs.

For minimal calling convention backwards compatibility, this version of urlencode accepts *but ignores* a second argument conventionally named doseq. The Python stdlib version behaves differently when doseq is False and when a sequence is presented as one of the values. This version always behaves in the doseq=True mode, no matter what the value of the second argument.

See the Python stdlib documentation for urllib.urlencode for more information.

CHAPTER

FIFTYNINE

PYRAMID.VIEW

render_view_to_response (context, request, name='', secure=True)

Call the view callable configured with a view configuration that matches the view name name registered against the specified context and request and return a response object. This function will return None if a corresponding view callable cannot be found (when no view configuration matches the combination of name / context / and request).

If *secure*' is True, and the *view callable* found is protected by a permission, the permission will be checked before calling the view function. If the permission check disallows view execution (based on the current *authorization policy*), a pyramid.httpexceptions.HTTPForbidden exception will be raised. The exception's args attribute explains why the view access was disallowed.

If secure is False, no permission checking is done.

render_view_to_iterable (context, request, name='', secure=True)

Call the *view callable* configured with a *view configuration* that matches the *view name* name registered against the specified context and request and return an iterable object which represents the body of a response. This function will return None if a corresponding *view callable* cannot be found (when no *view configuration* matches the combination of name / context / and request). Additionally, this function will raise a ValueError if a view function is found and called but the view function's result does not have an app_iter attribute.

You can usually get the string representation of the return value of this function by calling ".join(iterable), or just use pyramid.view.render_view() instead.

If secure is True, and the view is protected by a permission, the permission will be checked before the view function is invoked. If the permission check disallows view execution (based on the current *authentication policy*), a pyramid.httpexceptions.HTTPForbidden exception will be raised; its args attribute explains why the view access was disallowed.

If secure is False, no permission checking is done.

render_view (context, request, name='', secure=True)

Call the view callable configured with a view configuration that matches the view name name registered against the specified context and request and unwind the view response's app_iter (see View Callable Responses) into a single string. This function will return None if a corresponding view callable cannot be found (when no view configuration matches the combination of name / context / and request). Additionally, this function will raise a ValueError if a view function is found and called but the view function's result does not have an app_iter attribute. This function will return None if a corresponding view cannot be found.

If secure is True, and the view is protected by a permission, the permission will be checked before the view is invoked. If the permission check disallows view execution (based on the current *authorization policy*), a pyramid.httpexceptions.HTTPForbidden exception will be raised; its args attribute explains why the view access was disallowed.

If secure is False, no permission checking is done.

is_response(ob)

Return True if ob implements the interface implied by *View Callable Responses*. False if not.

This function is deprecated as of Pyramid 1.1. New code should not use it. Instead, new code should use the pyramid.request.Request.is_response() method.

class view_config (name='', request_type=None, for_=None, permission=None, route_name=None, request_method=None, request_param=None, containment=None, attr=None, renderer=None, wrapper=None, xhr=False, accept=None, header=None, path_info=None, custom_predicates=(), context=None, decorator=None, mapper=None, http_cache=None)

A function, class or method *decorator* which allows a developer to create view registrations nearer to a *view callable* definition than use *imperative configuration* to do the same.

For example, this code in a module views.py:

Might replace the following call to the pyramid.config.Configurator.add_view() method:

The following arguments are supported as arguments to pyramid.view.view_config: context, permission, name, request_type, route_name, request_method, request_param, containment, xhr, accept, header, path_info, custom_predicates, decorator, mapper, and http_cache.

The meanings of these arguments are the same as the arguments passed to pyramid.config.Configurator.add_view().

See Adding View Configuration Using the @view_config Decorator for details about using view_config.

```
class static (root_dir, cache_max_age=3600, package_name=None)
```

Backwards compatibility alias for pyramid.static.static_view; it overrides that class' constructor to pass use_subpath=True by default. This class is deprecated as of Pyramid 1.1. Use pyramid.static.static_view instead (probably with a use_subpath=True argument).

append_slash_notfound_view(context, request)

For behavior like Django's APPEND_SLASH=True, use this view as the *Not Found view* in your application.

When this view is the Not Found view (indicating that no view was found), and any routes have been defined in the configuration of your application, if the value of the PATH_INFO WSGI environment variable does not already end in a slash, and if the value of PATH_INFO *plus* a slash matches any route's path, do an HTTP redirect to the slash-appended PATH_INFO. Note that this will *lose* POST data information (turning it into a GET), so you shouldn't rely on this to redirect POST requests. Note also that static routes are not considered when attempting to find a matching route.

Use the pyramid.config.Configurator.add_view() method to configure this view as the Not Found view:

```
from pyramid.httpexceptions import HTTPNotFound
from pyramid.view import append_slash_notfound_view
config.add_view(append_slash_notfound_view, context=HTTPNotFound)
```

See also Changing the Not Found View.

class AppendSlashNotFoundViewFactory (notfound_view=None)

There can only be one *Not Found view* in any Pyramid application. Even if you use pyramid.view.append_slash_notfound_view() as the Not Found view, Pyramid still must generate a 404 Not Found response when it cannot redirect to a slash-appended URL; this not found response will be visible to site users.

don't 404 If you care what this response looks like. and you only need redirections to slash-appended route URLs. vou may use the pyramid.view.append slash notfound view() object as the Not Found view. However, if you wish to use a *custom* notfound view callable when a URL cannot be redirected to a slash-appended URL, you may wish to use an instance of this class as the Not Found view, supplying a view callable to be used as the custom notfound view as the first argument to its constructor. For instance:

```
from pyramid.httpexceptions import HTTPNotFound
from pyramid.view import AppendSlashNotFoundViewFactory
def notfound_view(context, request): return HTTPNotFound('nope')
custom_append_slash = AppendSlashNotFoundViewFactory(notfound_view)
config.add_view(custom_append_slash, context=HTTPNotFound)
```

The notfound_view supplied must adhere to the two-argument view callable calling convention of (context, request) (context will be the exception object).

CHAPTER

SIXTY

PYRAMID.WSGI

wsgiapp (wrapped)

Decorator to turn a WSGI application into a Pyramid *view callable*. This decorator differs from the pyramid.wsgi.wsgiapp2() decorator inasmuch as fixups of PATH_INFO and SCRIPT_NAME within the WSGI environment *are not* performed before the application is invoked.

E.g., the following in a views.py module:

Allows the following call to pyramid.config.Configurator.add_view():

```
from views import hello_world
config.add_view(hello_world, name='hello_world.txt')
```

The wsgiapp decorator will convert the result of the WSGI application to a *Response* and return it to Pyramid as if the WSGI app were a pyramid view.

wsgiapp2 (wrapped)

Decorator to turn a WSGI application into a Pyramid view callable. This decorator differs from the pyramid.wsgi.wsgiapp() decorator inasmuch as fixups of PATH_INFO and SCRIPT_NAME within the WSGI environment *are* performed before the application is invoked.

E.g. the following in a views.py module:

Allows the following call to pyramid.config.Configurator.add_view():

```
from views import hello_world
config.add_view(hello_world, name='hello_world.txt')
```

The wsgiapp2 decorator will convert the result of the WSGI application to a Response and return it to Pyramid as if the WSGI app were a Pyramid view. The SCRIPT_NAME and PATH_INFO values present in the WSGI environment are fixed up before the application is invoked. In particular, a new WSGI environment is generated, and the *subpath* of the request passed to wsgiapp2 is used as the new request's PATH_INFO and everything preceding the subpath is used as the SCRIPT_NAME. The new environment is passed to the downstream WSGI application.

Part IV

Glossary and Index

GLOSSARY

- ACE An access control entry. An access control entry is one element in an ACL. An access control entry is a three-tuple that describes three things: an action (one of either Allow or Deny), a principal (a string describing a user or group), and a permission. For example the ACE, (Allow, 'bob', 'read') is a member of an ACL that indicates that the principal bob is allowed the permission read against the resource the ACL is attached to.
- ACL An access control list. An ACL is a sequence of ACE tuples. An ACL is attached to a resource instance. An example of an ACL is [(Allow, 'bob', 'read'), (Deny, 'fred', 'write')]. If an ACL is attached to a resource instance, and that resource is findable via the context resource, it will be consulted any active security policy to determine wither a particular request can be fulfilled given the *authentication* information in the request.
- **Agendaless Consulting** A consulting organization formed by Paul Everitt, Tres Seaver, and Chris Mc-Donough. See also http://agendaless.com.
- Akhet Akhet is a Pyramid-based development environment which provides a Pylonsesque scaffold which sports support for *view handler* application development, *SQLAlchemy* support, *Mako* templating by default, and other Pylons-like features. See http://docs.pylonsproject.org/projects/akhet/dev/index.html for more information.
- **application registry** A registry of configuration information consulted by Pyramid while servicing an application. An application registry maps resource types to views, as well as housing other application-specific component registrations. Every Pyramid application has one (and only one) application registry.
- **asset** Any file contained within a Python *package* which is *not* a Python source code file.
- **asset specification** A colon-delimited identifier for an *asset*. The colon separates a Python *package* name from a package subpath. For example, the asset specification my.package:static/baz.css identifies the file named baz.css in the static subdirectory of the my.package Python *package*. See *Understanding Asset Specifications* for more info.
- **authentication** The act of determining that the credentials a user presents during a particular request are "good". Authentication in Pyramid is performed via an *authentication policy*.
- **authentication policy** An authentication policy in Pyramid terms is a bit of code which has an API which determines the current *principal* (or principals) associated with a request.

- **authorization** The act of determining whether a user can perform a specific action. In pyramid terms, this means determining whether, for a given resource, any *principal* (or principals) associated with the request have the requisite *permission* to allow the request to continue. Authorization in Pyramid is performed via its *authorization policy*.
- **authorization policy** An authorization policy in Pyramid terms is a bit of code which has an API which determines whether or not the principals associated with the request can perform an action associated with a permission, based on the information found on the *context* resource.
- **Babel** A collection of tools for internationalizing Python applications. Pyramid does not depend on Babel to operate, but if Babel is installed, additional locale functionality becomes available to your application.
- **Chameleon** chameleon is an attribute language template compiler which supports both the *ZPT* and *Genshi* templating specifications. It is written and maintained by Malthe Borch. It has several extensions, such as the ability to use bracketed (Genshi-style) f(name) syntax, even within ZPT. It is also much faster than the reference implementations of both ZPT and Genshi. Pyramid offers Chameleon templating out of the box in ZPT and text flavors.
- **configuration declaration** An individual method call made to an instance of a Pyramid *Configurator* object which performs an arbitrary action, such as registering a *view configuration* (via the add_view method of the configurator) or *route configuration* (via the add_route method of the configuration declarations is also implied by the *configuration decoration* detected by a *scan* of code in a package.
- **configuration decoration** Metadata implying one or more *configuration declaration* invocations. Often set by configuration Python *decorator* attributes, such as pyramid.view.view_config, aka @view_config.
- **configurator** An object used to do *configuration declaration* within an application. The most common configurator is an instance of the pyramid.config.Configurator class.
- **context** A resource in the resource tree that is found during *traversal* or *URL dispatch* based on URL data; if it's found via traversal, it's usually a *resource* object that is part of a resource tree; if it's found via *URL dispatch*, it's an object manufactured on behalf of the route's "factory". A context resource becomes the subject of a *view*, and often has security information attached to it. See the *Traversal* chapter and the *URL Dispatch* chapter for more information about how a URL is resolved to a context resource.
- **CPython** The C implementation of the Python language. This is the reference implementation that most people refer to as simply "Python"; *Jython*, Google's App Engine, and PyPy are examples of non-C based Python implementations.

- **declarative configuration** The configuration mode in which you use the combination of *configuration decoration* and a *scan* to configure your Pyramid application.
- **decorator** A wrapper around a Python function or class which accepts the function or class as its first argument and which returns an arbitrary object. Pyramid provides several decorators, used for configuration and return value modification purposes. See also PEP 318.
- **Default Locale Name** The *locale name* used by an application when no explicit locale name is set. See *Localization-Related Deployment Settings*.
- **default permission** A *permission* which is registered as the default for an entire application. When a default permission is in effect, every *view configuration* registered with the system will be effectively amended with a permission argument that will require that the executing user possess the default permission in order to successfully execute the associated *view callable* See also *Setting a Default Permission*.
- **Default view** The default view of a *resource* is the view invoked when the *view name* is the empty string ("). This is the case when *traversal* exhausts the path elements in the PATH_INFO of a request before it returns a *context* resource.
- **Deployment settings** Deployment settings are settings passed to the *Configurator* as a settings argument. These are later accessible via a request.registry.settings dictionary. Deployment settings can be used as global application values.
- distribution (Setuptools/distutils terminology). A file representing an installable library or application. Distributions are usually files that have the suffix of .egg, .tar.gz, or .zip. Distributions are the target of Setuptools commands such as easy_install.
- **distutils** The standard system for packaging and distributing Python packages. See http://docs.python.org/distutils/index.html for more information. *setuptools* is actually an *extension* of the Distutils.
- **Django** A full-featured Python web framework.
- **domain model** Persistent data related to your application. For example, data stored in a relational database. In some applications, the *resource tree* acts as the domain model.
- dotted Python name A reference to a Python object by name using a string, in the form path.to.modulename:attributename. Often used in Paste and setuptools configurations. A variant is used in dotted names within configurator method arguments that name objects (such as the "add_view" method's "view" and "context" attributes): the colon (:) is not used; in its place is a dot.

- **entry point** A *setuptools* indirection, defined within a setuptools *distribution* setup.py. It is usually a name which refers to a function somewhere in a package which is held by the distribution.
- **event** An object broadcast to zero or more *subscriber* callables during normal Pyramid system operations during the lifetime of an application. Application code can subscribe to these events by using the subscriber functionality described in *Using Events*.
- **exception response** A *response* that is generated as the result of a raised exception being caught by an *exception view*.
- **Exception view** An exception view is a *view callable* which may be invoked by Pyramid when an exception is raised during request processing. See *Custom Exception Views* for more information.
- **finished callback** A user-defined callback executed by the *router* unconditionally at the very end of request processing. See *Using Finished Callbacks*.
- **Forbidden view** An *exception view* invoked by Pyramid when the developer explicitly raises a pyramid.httpexceptions.HTTPForbidden exception from within *view* code or *root factory* code, or when the *view configuration* and *authorization policy* found for a request disallows a particular view invocation. Pyramid provides a default implementation of a forbidden view; it can be overridden. See *Changing the Forbidden View*.
- Genshi An XML templating language by Christopher Lenz.
- Gettext The GNU gettext library, used by the Pyramid translation machinery.
- **Google App Engine** Google App Engine (aka "GAE") is a Python application hosting service offered by Google. Pyramid runs on GAE.
- **Grok** A web framework based on Zope 3.
- **HTTP Exception** The set of exception classes defined in pyramid.httpexceptions. These can be used to generate responses with various status codes when raised or returned from a *view callable*. See also *HTTP Exceptions*.
- **imperative configuration** The configuration mode in which you use Python to call methods on a *Configurator* in order to add each *configuration declaration* required by your application.
- interface A Zope interface object. In Pyramid, an interface may be attached to a *resource* object or a *request* object in order to identify that the object is "of a type". Interfaces are used internally by Pyramid to perform view lookups and other policy lookups. The ability to make use of an interface is exposed to an application programmers during *view configuration* via the context argument, the request_type argument and the containment argument. Interfaces are also exposed to application developers when they make use of the *event* system. Fundamentally, Pyramid programmers can think of an interface as something that they can attach to an object that stamps it with a "type" unrelated to its underlying Python type. Interfaces can also be used to describe the behavior of an object (its methods and attributes), but unless they choose to, Pyramid programmers do not need to understand or use this feature of interfaces.

- **Internationalization** The act of creating software with a user interface that can potentially be displayed in more than one language or cultural context. Often shortened to "i18n" (because the word "internationalization" is I, 18 letters, then N). See also: *Localization*.
- Jinja2 A text templating language by Armin Ronacher.
- **jQuery** A popular Javascript library.
- **JSON** JavaScript Object Notation is a data serialization format.
- **Jython** A Python implementation written for the Java Virtual Machine.
- **lineage** An ordered sequence of objects based on a "*location* -aware" resource. The lineage of any given *resource* is composed of itself, its parent, its parent's parent, and so on. The order of the sequence is resource-first, then the parent of the resource, then its parent's parent, and so on. The parent of a resource in a lineage is available as its __parent___ attribute.
- **Lingua** A package by Wichert Akkerman which provides *Babel* message extractors for Python source files and Chameleon ZPT template files.
- Locale Name A string like en, en_US, de, or de_AT which uniquely identifies a particular locale.
- Locale Negotiator An object supplying a policy determining which *locale name* best represents a given *request*. It is used by the pyramid.i18n.get_locale_name(), and pyramid.i18n.negotiate_locale_name() functions, and indirectly by pyramid.i18n.get_localizer(). The pyramid.i18n.default_locale_negotiator() function is an example of a locale negotiator.
- **Localization** The process of displaying the user interface of an internationalized application in a particular language or cultural context. Often shortened to "110" (because the word "localization" is L, 10 letters, then N). See also: *Internationalization*.
- Localizer An instance of the class pyramid.il8n.Localizer which provides translation and pluralization services to an application. It is retrieved via the pyramid.il8n.get_localizer() function.
- **location** The path to an object in a *resource tree*. See *Location-Aware Resources* for more information about how to make a resource object *location-aware*.
- **Mako** Mako is a template language language which refines the familiar ideas of componentized layout and inheritance using Python with Python scoping and calling semantics.

- **matchdict** The dictionary attached to the *request* object as request.matchdict when a *URL dis*patch route has been matched. Its keys are names as identified within the route pattern; its values are the values matched by each pattern name.
- **Message Catalog** A *gettext* . mo file containing translations.
- **Message Identifier** A string used as a translation lookup key during localization. The msgid argument to a *translation string* is a message identifier. Message identifiers are also present in a *message catalog*.
- **METAL** Macro Expansion for TAL, a part of *ZPT* which makes it possible to share common look and feel between templates.
- **middleware** *Middleware* is a *WSGI* concept. It is a WSGI component that acts both as a server and an application. Interesting uses for middleware exist, such as caching, content-transport encoding, and other functions. See WSGI.org or PyPI to find middleware for your application.
- **mod_wsgi** mod_wsgi is an Apache module developed by Graham Dumpleton. It allows *WSGI* applications (such as applications developed using Pyramid) to be served using the Apache web server.
- **module** A Python source file; a file on the filesystem that typically ends with the extension .py or .pyc. Modules often live in a *package*.
- multidict An ordered dictionary that can have multiple values for each key. Adds the methods getall, getone, mixed, add and dict_of_lists to the normal dictionary interface. See Multidict and pyramid.interfaces.IMultiDict.
- Not Found view An *exception view* invoked by Pyramid when the developer explicitly raises a pyramid.httpexceptions.HTTPNotFound exception from within *view* code or *root factory* code, or when the current request doesn't match any *view configuration*. Pyramid provides a default implementation of a not found view; it can be overridden. See *Changing the Not Found View*.
- package A directory on disk which contains an __init__.py file, making it recognizable to Python
 as a location which can be import -ed. A package exists to contain *module* files.
- **Paste** Paste is a WSGI development and deployment system developed by Ian Bicking.
- **PasteDeploy** PasteDeploy is a library used by Pyramid which makes it possible to configure *WSGI* components together declaratively within an .ini file. It was developed by Ian Bicking as part of *Paste*.

- **permission** A string or unicode object that represents an action being taken against a *context* resource. A permission is associated with a view name and a resource type by the developer. Resources are decorated with security declarations (e.g. an *ACL*), which reference these tokens also. Permissions are used by the active security policy to match the view permission against the resources's statements about which permissions are granted to which principal in a context in order to answer the question "is this user allowed to do this". Examples of permissions: read, or view_blog_entries.
- **pipeline** The *Paste* term for a single configuration of a WSGI server, a WSGI application, with a set of middleware in-between.
- **pkg_resources** A module which ships with *setuptools* that provides an API for addressing "asset files" within a Python *package*. Asset files are static files, template files, etc; basically anything non-Python-source that lives in a Python package can be considered a asset file. See also PkgResources
- **predicate** A test which returns True or False. Two different types of predicates exist in Pyramid: a *view predicate* and a *route predicate*. View predicates are attached to *view configuration* and route predicates are attached to *route configuration*.
- pregenerator A pregenerator is a function associated by a developer with a route. It is called by pyramid.url.route_url() in order to adjust the set of arguments passed to it by the user for special purposes. It will influence the URL returned by route_url. See pyramid.interfaces.IRoutePregenerator for more information.
- **principal** A *principal* is a string or unicode object representing a userid or a group id. It is provided by an *authentication policy*. For example, if a user had the user id "bob", and Bob was part of two groups named "group foo" and "group bar", the request might have information attached to it that would indicate that Bob was represented by three principals: "bob", "group foo" and "group bar".
- **project** (Setuptools/distutils terminology). A directory on disk which contains a setup.py file and one or more Python packages. The setup.py file contains code that allows the package(s) to be installed, distributed, and tested.
- Pylons A lightweight Python web framework and a predecessor of Pyramid.
- **PyPI** The Python Package Index, a collection of software available for Python.
- PyPy PyPy is an "alternative implementation of the Python language":http://pypy.org/
- **Pyramid Cookbook** An additional documentation resource for Pyramid which presents topical, practical usages of Pyramid available via http://docs.pylonsproject.org/.
- **pyramid_handlers** An add-on package which allows Pyramid users to create classes that are analogues of Pylons 1 "controllers". See http://docs.pylonsproject.org/projects/pyramid_handlers/dev/.

- pyramid_jinja2 Jinja2 templating system bindings for Pyramid, documented at http://docs.pylonsproject.org/projects/pyramid_jinja2/dev/. This package also includes a scaffold named pyramid_jinja2_starter, which creates an application package based on the Jinja2 templating system.
- **pyramid_zcml** An add-on package to Pyramid which allows applications to be configured via ZCML. It is available on *PyPI*. If you use pyramid_zcml, you can use ZCML as an alternative to *imperative configuration*.
- **Python** The programming language in which Pyramid is written.
- **renderer** A serializer that can be referred to via *view configuration* which converts a non-*Response* return values from a *view* into a string (and ultimately a response). Using a renderer can make writing views that require templating or other serialization less tedious. See *Writing View Callables Which Use a Renderer* for more information.
- **renderer factory** A factory which creates a *renderer*. See *Adding and Changing Renderers* for more information.
- **renderer globals** Values injected as names into a renderer based on application policy. See *Adding Renderer Globals (Deprecated)* for more information.
- **Repoze** "Repoze" is essentially a "brand" of software developed by Agendaless Consulting and a set of contributors. The term has no special intrinsic meaning. The project's website has more information. The software developed "under the brand" is available in a Subversion repository. Pyramid was originally known as repoze.bfg.
- **repoze.catalog** An indexing and search facility (fielded and full-text) based on zope.index. See the documentation for more information.
- **repoze.lemonade** Zope2 CMF-like data structures and helper facilities for CA-and-ZODB-based applications useful within Pyramid applications.
- **repoze.who** Authentication middleware for *WSGI* applications. It can be used by Pyramid to provide authentication information.
- **repoze.workflow** Barebones workflow for Python apps . It can be used by Pyramid to form a workflow system.
- request A WebOb request object. See *Request and Response Objects* (narrative) and *pyramid.request* (API documentation) for information about request objects.
- **request factory** An object which, provided a WSGI environment as a single positional argument, returns a WebOb compatible request.

- **request type** An attribute of a *request* that allows for specialization of view invocation based on arbitrary categorization. The every *request* object that Pyramid generates and manipulates has one or more *interface* objects attached to it. The default interface attached to a request object is pyramid.interfaces.IRequest.
- **resource** An object representing a node in the *resource tree* of an application. If traversal is used, a resource is an element in the resource tree traversed by the system. When traversal is used, a resource becomes the *context* of a *view*. If url dispatch is used, a single resource is generated for each request and is used as the context resource of a view.
- **Resource Location** The act of locating a *context* resource given a *request*. *Traversal* and *URL dispatch* are the resource location subsystems used by Pyramid.
- **resource tree** A nested set of dictionary-like objects, each of which is a *resource*. The act of *traversal* uses the resource tree to find a *context* resource.
- **response** An object returned by a *view callable* that represents response data returned to the requesting user agent. It must implements the pyramid.interfaces.IResponse interface. A response object is typically an instance of the pyramid.response.Response class or a subclass such as pyramid.httpexceptions.HTTPFound. See *Request and Response Objects* for information about response objects.
- **response callback** A user-defined callback executed by the *router* at a point after a *response* object is successfully created. See *Using Response Callbacks*.
- **reStructuredText** A plain text format that is the defacto standard for descriptive text shipped in *distribution* files, and Python docstrings. This documentation is authored in ReStructuredText format.
- **root** The object at which *traversal* begins when Pyramid searches for a *context* resource (for *URL Dispatch*, the root is *always* the context resource unless the traverse= argument is used in route configuration).
- **root factory** The "root factory" of a Pyramid application is called on every request sent to the application. The root factory returns the traversal root of an application. It is conventionally named get_root. An application may supply a root factory to Pyramid during the construction of a *Configurator*. If a root factory is not supplied, the application uses a default root object. Use of the default root object is useful in application which use *URL dispatch* for all URL-to-view code mappings.
- **route** A single pattern matched by the *url dispatch* subsystem, which generally resolves to a *root factory* (and then ultimately a *view*). See also *url dispatch*.
- **route configuration** Route configuration is the act of associating request parameters with a particular *route* using pattern matching and *route predicate* statements. See *URL Dispatch* for more information about route configuration.

- **route predicate** An argument to a *route configuration* which implies a value that evaluates to True or False for a given *request*. All predicates attached to a *route configuration* must evaluate to True for the associated route to "match" the current request. If a route does not match the current request, the next route (in definition order) is attempted.
- **router** The *WSGI* application created when you start a Pyramid application. The router intercepts requests, invokes traversal and/or URL dispatch, calls view functions, and returns responses to the WSGI server on behalf of your Pyramid application.
- **Routes** A system by Ben Bangert which parses URLs and compares them against a number of user defined mappings. The URL pattern matching syntax in Pyramid is inspired by the Routes syntax (which was inspired by Ruby On Rails pattern syntax).
- **routes mapper** An object which compares path information from a request to an ordered set of route patterns. See *URL Dispatch*.
- **scan** The term used by Pyramid to define the process of importing and examining all code in a Python package or module for *configuration decoration*.
- **session** A namespace that is valid for some period of continual activity that can be used to represent a user's interaction with a web application.
- session factory A callable, which, when called with a single argument named request (a request object), returns a session object.
- **setuptools** Setuptools builds on Python's distutils to provide easier building, distribution, and installation of libraries and applications.
- **SQLAIchemy** SQLAIchemy is an object relational mapper used in tutorials within this documentation.
- subpath A list of element "left over" after the *router* has performed a successful traversal to a view. The subpath is a sequence of strings, e.g. ['left', 'over', 'names']. Within Pyramid applications that use URL dispatch rather than traversal, you can use *subpath in the route pattern to influence the subpath. See Using *subpath in a Route Pattern for more information.
- **subscriber** A callable which receives an *event*. A callable becomes a subscriber via *imperative configuration* or via *configuration decoration*. See *Using Events* for more information.
- **template** A file with replaceable parts that is capable of representing some text, XML, or HTML when rendered.
- **thread local** A thread-local variable is one which is essentially a global variable in terms of how it is accessed and treated, however, each thread used by the application may have a different value for this same "global" variable. Pyramid uses a small number of thread local variables, as described in *Thread Locals*. See also the threading.local documentation for more information.

- **Translation Directory** A translation directory is a *gettext* translation directory. It contains language folders, which themselves contain LC_MESSAGES folders, which contain .mo files. Each .mo file represents a set of translations for a language in a *translation domain*. The name of the .mo file (minus the .mo extension) is the translation domain name.
- **Translation Domain** A string representing the "context" in which a translation was made. For example the word "java" might be translated differently if the translation domain is "programming-languages" than would be if the translation domain was "coffee". A translation domain is represented by a collection of .mo files within one or more *translation directory* directories.
- **Translation String** An instance of pyramid.i18n.TranslationString, which is a class that behaves like a Unicode string, but has several extra attributes such as domain, msgid, and mapping for use during translation. Translation strings are usually created by hand within software, but are sometimes created on the behalf of the system for automatic template translation. For more information, see *Internationalization and Localization*.
- **Translator** A callable which receives a *translation string* and returns a translated Unicode object for the purposes of internationalization. A *localizer* supplies a translator to a Pyramid application accessible via its translate method.
- **traversal** The act of descending "up" a tree of resource objects from a root resource in order to find a *context* resource. The Pyramid *router* performs traversal of resource objects when a *root factory* is specified. See the *Traversal* chapter for more information. Traversal can be performed *instead* of *URL dispatch* or can be combined *with* URL dispatch. See *Combining Traversal and URL Dispatch* for more information about combining traversal and URL dispatch (advanced).
- **URL dispatch** An alternative to *traversal* as a mechanism for locating a *context* resource for a *view*. When you use a *route* in your Pyramid application via a *route configuration*, you are using URL dispatch. See the *URL Dispatch* for more information.
- **Venusian** Venusian is a library which allows framework authors to defer decorator actions. Instead of taking actions when a function (or class) decorator is executed at import time, the action usually taken by the decorator is deferred until a separate "scan" phase. Pyramid relies on Venusian to provide a basis for its *scan* feature.
- view Common vernacular for a view callable.
- view callable A "view callable" is a callable Python object which is associated with a view configuration; it returns a *response* object. A view callable accepts a single argument: request, which will be an instance of a *request* object. An alternate calling convention allows a view to be defined as a callable which accepts a pair of arguments: context and request: this calling convention is useful for traversal-based applications in which a *context* is always very important. A view callable is the primary mechanism by which a developer writes user interface code within Pyramid. See *Views* for more information about Pyramid view callables.

- view configuration View configuration is the act of associating a view callable with configuration information. This configuration information helps map a given request to a particular view callable and it can influence the response of a view callable. Pyramid views can be configured via *imperative configuration*, or by a special @view_config decorator coupled with a scan. See View Configuration for more information about view configuration.
- **View handler** A view handler ties together pyramid.config.Configurator.add_route() and pyramid.config.Configurator.add_view() to make it more convenient to register a collection of views as a single class when using *url dispatch*. View handlers ship as part of the *pyramid_handlers* add-on package.
- **View Lookup** The act of finding and invoking the "best" *view callable* given a *request* and a *context* resource.
- view mapper A view mapper is a class which implements the pyramid.interfaces.IViewMapperFactory interface, which performs view argument and return value mapping. This is a plug point for extension builders, not normally used by "civilians".
- view name The "URL name" of a view, e.g index.html. If a view is configured without a name, its name is considered to be the empty string (which implies the *default view*).
- **view predicate** An argument to a *view configuration* which evaluates to True or False for a given *request*. All predicates attached to a view configuration must evaluate to true for the associated view to be considered as a possible callable for a given request.
- **virtual root** A resource object representing the "virtual" root of a request; this is typically the physical root object (the object returned by the application root factory) unless *Virtual Hosting* is in use.
- virtualenv An isolated Python environment. Allows you to control which packages are used on a particular project by cloning your main Python. virtualenv was created by Ian Bicking.
- **WebError** WSGI middleware which can display debuggable traceback information in the browser when an exception is raised by a Pyramid application. See http://pypi.python.org/pypi/WebError.
- **WebOb** WebOb is a WSGI request/response library created by Ian Bicking.
- WebTest WebTest is a package which can help you write functional tests for your WSGI application.
- **WSGI** Web Server Gateway Interface. This is a Python standard for connecting web applications to web servers, similar to the concept of Java Servlets. Pyramid requires that your application be served as a WSGI application.

- **ZCML** Zope Configuration Markup Language, an XML dialect used by Zope and *pyramid_zcml* for configuration tasks.
- **ZCML declaration** The concrete use of a *ZCML directive* within a ZCML file.
- ZCML directive A ZCML "tag" such as <view> or <route>.
- **ZEO** Zope Enterprise Objects allows multiple simultaneous processes to access a single ZODB database.
- **ZODB** Zope Object Database, a persistent Python object store.
- **Zope** The Z Object Publishing Framework, a full-featured Python web framework.
- **Zope Component Architecture** The Zope Component Architecture (aka ZCA) is a system which allows for application pluggability and complex dispatching based on objects which implement an *interface*. Pyramid uses the ZCA "under the hood" to perform view dispatching and other application configuration tasks.
- **ZPT** The Zope Page Template templating language.

INDEX

Symbols

*subpath hybrid applications, 248 *traverse route pattern hybrid applications, 244 __call__() (IResponse method), 488 __call__() (IRoutePregenerator method), 481 ____call__() (ISessionFactory method), 484 call () (IViewMapper method), 485 __call__() (IViewMapperFactory method), 485 contains () (IBeforeRender method), 479 contains () (ISession method), 482 delitem () (ISession method), 483 getitem () (IBeforeRender method), 478 __getitem__() (ISession method), 483 __init__.py, 39 iter () (ISession method), 484 __len__() (ISession method), 483 setitem () (IBeforeRender method), 479 __setitem__() (ISession method), 483

A

absolute_asset_spec() (Configurator method), 431 accept (Request attribute), 508 accept_charset (Request attribute), 508 accept_encoding (Request attribute), 508 accept_language (Request attribute), 508 accept_ranges (IResponse attribute), 490 accept_ranges (Response attribute), 521 access control entry, 233 access control list, 232 ACE, 233, 565 ACE (special), 235 ACL, 232, 565 resource, 232 ACL inheritance, 236 ACLAllowed (class in pyramid.security), 532 **ACLAuthorizationPolicy** in (class pyramid.authorization), 413 ACLDenied (class in pyramid.security), 532 action() (Configurator method), 428 activating translation, 181 add() (IMultiDict method), 486 add_directive, 274 add_directive() (Configurator method), 430 add_finished_callback() (Request method), 504, 508 add_renderer() (Configurator method), 431 add response adapter() (Configurator method), 431 add_response_callback() (Request method), 503, 509 add route, 45 add route() (Configurator method), 432 add_settings() (Configurator method), 439 add_static_view, 118 add_static_view() (Configurator method), 437 add_subscriber() (Configurator method), 439 add_translation_dirs() (Configurator method), 439 add view, 113 add_view() (Configurator method), 440

adding renderer. 84 translation directory, 181 adding directives configurator, 274 adding renderer globals, 254 advanced configuration, 265 age (IResponse attribute), 490 age (Response attribute), 521 Agendaless Consulting, 3, 565 Akhet, 565 Akkerman, Wichert, ix ALL_PERMISSIONS (in module pyramid.security), 531 Allow (in module pyramid.security), 531 allow (IResponse attribute), 490 allow (Response attribute), 521 Allowed (class in pyramid.security), 532 app (IApplicationCreated attribute), 477 app iter (IResponse attribute), 487 app iter (Response attribute), 521 app iter range() (IResponse method), 489 app_iter_range() (Response method), 521 append_slash_notfound_view() (in module pyramid.view), 559 AppendSlashNotFoundViewFactory (class in pyramid.view), 559 application configuration, 12 application registry, 291, 565 application_url (Request attribute), 509 ApplicationCreated (class in pyramid.events), 456 as string() (Request method), 510 asbool() (in module pyramid.settings), 533 assert () (DummyTemplateRenderer method), 537 asset, 565 asset specification, 565 asset specifications, 117 assets. 115 generating urls, 120 overriding, 123, 282 serving, 118 Authenticated (in module pyramid.security), 531

authenticated_userid() (IAuthenticationPolicy method), 479 authenticated userid() (in module pyramid.security), 529 authentication, 565 authentication policy, 565 authentication policy (creating), 237 authorization, 565 authorization (Request attribute), 510 authorization policy, 229, 566 authorization policy (creating), 238 AuthTktAuthenticationPolicy (class in pyramid.authentication), 415 AuthTktCookieHelper (class in pyramid.authentication), 418 automatic reloading of templates, 101

В

Babel, 171, 177, 566 message extractors, 172 Bangert, Ben, ix Beaker, 137 Beelby, Chris, ix before render event, 254 BeforeRender (class in pyramid.events), 457 begin() (Configurator method), 427 bfg2pyramid, 395 Bicking, Ian, ix, 125 blank() (pyramid.request.Request class method), 510 body (IResponse attribute), 489 body (Request attribute), 510 body (Response attribute), 521 body_file (IResponse attribute), 490 body file (Request attribute), 510 body file (Response attribute), 521 body_file_raw (Request attribute), 510 body file seekable (Request attribute), 510 book audience, vii book content overview, vii bootstrap, 162 bootstrap() (in module pyramid.paster), 493 Borch, Malthe, ix

Brandl, Georg, ix built-in renderers, 77

С

cache control (IResponse attribute), 488 cache_control (Request attribute), 510 cache control (Response attribute), 522 cache expires (IResponse attribute), 486 call application() (Request method), 510 Chameleon, 566 translation strings, 178 chameleon renderer. 79 Chameleon text templates, 97 Chameleon ZPT macros, 96 Chameleon ZPT templates, 95 changed() (ISession method), 484 changing renderer, 86 charset (IResponse attribute), 488 charset (Request attribute), 511 charset (Response attribute), 522 cleaning up after request, 60 cleanUp() (in module pyramid.testing), 536 clear() (ISession method), 484 clone() (DummyResource method), 536 code scanning, 14 commit() (Configurator method), 428 compiling message catalog, 175 conditional response app() (IResponse method), 488 conditional_response_app() (Response method), 522 configuration advanced, 265 conflict detection, 267 including from external sources, 272 configuration declaration, 566 configuration decoration, 14, 566 configuration decorator, 263 ConfigurationError (class in pyramid.exceptions), 459

Configurator, 19 configurator, 566 adding directives, 274 Configurator (class in pyramid.config), 425 Configurator testing API, 192 conflict detection configuration, 267 container resources, 197 content_disposition (IResponse attribute), 488 content disposition (Response attribute), 522 content_encoding (IResponse attribute), 488 content_encoding (Response attribute), 522 content language (IResponse attribute), 487 content_language (Response attribute), 522 content length (IResponse attribute), 486 content_length (Request attribute), 511 content length (Response attribute), 522 content location (IResponse attribute), 487 content_location (Response attribute), 522 content md5 (IResponse attribute), 488 content md5 (Response attribute), 522 content range (IResponse attribute), 488 content range (Response attribute), 522 content_type (IResponse attribute), 489 content_type (Request attribute), 511 content_type (Response attribute), 522 content_type_params (IResponse attribute), 489 content_type_params (Response attribute), 523 context, 220, 566 context (Request attribute), 501 ContextFound (class in pyramid.events), 456 converting a BFG app, 395 cookies (Request attribute), 511 copy() (IResponse method), 489 copy() (Request method), 511 copy() (Response method), 523 copy_body() (Request method), 511 copy get() (Request method), 512 corner cases hybrid applications, 249 CPython, 566 created (ISession attribute), 484 creating a project, 24

cross-site request forgery attacks, prevention, 139 current_route_url() (in module pyramid.url), 553 custom settings, 286

D

date (IResponse attribute), 489 date (Request attribute), 512 date (Response attribute), 523 date and currency formatting (i18n), 177 de la Guardia, Carlos, ix debug settings, 145 debug_all, 145 debug authorization, 145 debug_notfound, 145 debug_routematch, 145 debugging route matching, 62 templates, 99 view configuration, 115 debugging authorization failures, 237 debugging not found errors, 114 declarative configuration, 566 decorator, 567 default permission, 231 Default Locale Name, 567 default permission, 567 Default view, 567 default view, 220 default locale name, 145, 179 default_locale_negotiator() module (in pyramid.i18n), 475 delete cookie() (IResponse method), 488 delete cookie() (Response method), 523 Denied (class in pyramid.security), 532 Deny (in module pyramid.security), 531 DENY ALL (in module pyramid.security), 531 deployment settings, 286 Deployment settings, 567 derive_view() (Configurator method), 446 detecting langauges, 180 development install, 26

dict of lists() (IMultiDict method), 486 distribution. 567 distutils, 567 Django, 3, 4, 567 domain translation. 167 domain model, 567 dotted Python name, 567 DummyRequest (class in pyramid.testing), 537 DummyResource (class in pyramid.testing), 536 DummyTemplateRenderer (class in pyramid.testing), 537 Duncan, Casey, ix

Е

effective_principals() (IAuthenticationPolicy method), 479 effective principals() (in module pyramid.security), 529 encode content() (IResponse method), 486 encode content() (Response method), 523 end() (Configurator method), 428 entry point, 567 environ (IResponse attribute), 490 environ (Response attribute), 523 environment variables, 145 etag (IResponse attribute), 487 etag (Response attribute), 523 event, 141, 568 Everitt, Paul, ix Everyone (in module pyramid.security), 531 exception (Request attribute), 502 exception response, 568 exception responses, 133 Exception view, 568 exception views, 69 exception response() (in module pyramid.httpexceptions), 464 expires (IResponse attribute), 489 expires (Response attribute), 523 extend() (IMultiDict method), 485 extending pshell, 160

extending an existing application, 279 extensible application, 278 extracting messages, 172

F

factory (IRoute attribute), 480 find_interface() (in module pyramid.traversal), 541 find_resource() (in module pyramid.traversal), 541 find root() (in module pyramid.traversal), 542 finding by interface or class resource, 207 finding by path resource, 203 finding root resource, 205 finished callback, 256, 568 flash messages, 137 flash(), 138 flash() (ISession method), 482 Forbidden (in module pyramid.exceptions), 459 Forbidden view, 568 forbidden view, 236, 252 forget() (AuthTktCookieHelper method), 418 forget() (IAuthenticationPolicy method), 480 forget() (in module pyramid.security), 529 forms, views, and unicode, 71 framework, 3 frameworks vs. libraries, 3 from file() (pyramid.request.Request class method), 512 (pyramid.response.Response from file() class method), 523 from string() (pyramid.request.Request class method). 512 Fulton, Jim, ix functional testing, 187 functional tests, 195

G

generate() (IRoute method), 481 generating resource url, 200

generating route URLs, 58 generating static asset urls, 120 generating urls assets, 120 Genshi. 568 GET (Request attribute), 508 get() (BeforeRender method), 457 get() (IBeforeRender method), 479 get() (ISession method), 483 get app() (in module pyramid.paster), 493 get_csrf_token() (ISession method), 482 get_current_registry, 287, 293, 296 get_current_registry() module (in pyramid.threadlocal), 539 get current request, 287 get_current_request() module (in pyramid.threadlocal), 539 get locale name, 177 get_locale_name() (in module pyramid.i18n), 475 get localizer, 175 get localizer() (in module pyramid.i18n), 475 get renderer() (in module pyramid.renderers), 497 get response() (Request method), 512 get_root() (in module pyramid.scripting), 527 get_settings() (Configurator method), 428 get_settings() (in module pyramid.settings), 533 get_template() (in module pyramid.chameleon_text), 421 get_template() (in module pyramid.chameleon_zpt), 423 getall() (IMultiDict method), 486 getGlobalSiteManager, 296 getone() (IMultiDict method), 486 getSiteManager, 291, 293 Gettext, 568 gettext, 170 getUtility, 291, 293 global views hybrid applications, 248 global_registries (in module pyramid.config), 453 Google App Engine, 568 Grok, 568

Η

Hardwick, Nat, ix has permission() (in module pyramid.security), 530 Hathaway, Shane, ix headerlist (IResponse attribute), 490 headerlist (Response attribute), 523 headers (IResponse attribute), 487 headers (Request attribute), 512 headers (Response attribute), 524 hello world program, 15 helloworld (imperative), 19 Holth, Daniel, ix hook zca (configurator method), 295 hook_zca() (Configurator method), 428 host (Request attribute), 512 host_url (Request attribute), 512 hosting an app under a prefix, 185 HTTP caching, 114 HTTP Exception, 568 HTTP exceptions, 67 http redirect (from a view), 70 http version (Request attribute), 512 HTTPAccepted (class in pyramid.httpexceptions), 465 **HTTPBadGateway** pyra-(class in mid.httpexceptions), 472 HTTPBadRequest (class in pyramid.httpexceptions), 468 (class HTTPClientError in pyramid.httpexceptions), 465 HTTPConflict (class in pyramid.httpexceptions), 470 HTTPCreated (class in pyramid.httpexceptions), 465 HTTPError (class in pyramid.httpexceptions), 465 HTTPException (class in pyramid.httpexceptions), 464 HTTPExpectationFailed (class in pyramid.httpexceptions), 471 HTTPForbidden (class in pyramid.httpexceptions), 468 HTTPFound (class in pyramid.httpexceptions), 467

HTTPGatewayTimeout (class in pyramid.httpexceptions), 472 HTTPGone (class in pyramid.httpexceptions), 470 HTTPInternalServerError (class in pyramid.httpexceptions), 471 HTTPLengthRequired (class in pyramid.httpexceptions), 470 HTTPMethodNotAllowed (class in pyramid.httpexceptions), 469 **HTTPMovedPermanently** (class in pyramid.httpexceptions), 466 HTTPMultipleChoices (class in pyramid.httpexceptions), 466 **HTTPNoContent** (class in pyramid.httpexceptions), 466 HTTPNonAuthoritativeInformation (class in pyramid.httpexceptions), 465 **HTTPNotAcceptable** (class in pyramid.httpexceptions), 469 HTTPNotFound (class in pyramid.httpexceptions), 469 HTTPNotImplemented (class in pyramid.httpexceptions), 472 HTTPNotModified (class in pyramid.httpexceptions), 467 HTTPOk (class in pyramid.httpexceptions), 464 HTTPPartialContent (class in pyramid.httpexceptions), 466 HTTPPaymentRequired (class in pyramid.httpexceptions), 468 HTTPPreconditionFailed (class in pyramid.httpexceptions), 470 HTTPProxyAuthenticationRequired (class in pyramid.httpexceptions), 469 HTTPRedirection (class in pyramid.httpexceptions), 464 HTTPRequestEntityTooLarge (class in pyramid.httpexceptions), 470 HTTPRequestRangeNotSatisfiable (class in pyramid.httpexceptions), 471 HTTPRequestTimeout (class in pyramid.httpexceptions), 469

HTTPRequestURITooLong (class in pyra- mid.httpexceptions), 471	if_none_match (Request attribute), 513 if_range (Request attribute), 513
HTTPResetContent (class in pyra-	
mid.httpexceptions), 466	imperative configuration, 13, 19, 568
HTTPSeeOther (class in pyramid.httpexceptions)	
467	485
HTTPServerError (class in pyra-	
mid.httpexceptions), 465	include() (Configurator method), 429
HTTPServiceUnavailable (class in pyra-	including from external sources
mid.httpexceptions), 472	configuration, 272
HTTPTemporaryRedirect (class in pyra-	INewRequest, 141
mid.httpexceptions), 467	INewRequest (interface in pyramid.interfaces), 477
HTTPUnauthorized (class in pyra-	INewResponse, 141
mid.httpexceptions), 468	INewResponse (interface in pyramid.interfaces),
HTTPUnsupportedMediaType (class in pyra-	478
mid.httpexceptions), 471	ini file, 31
HTTPUseProxy (class in pyramid.httpexceptions)	ini file settings, 145
467	initializing
HTTPVersionNotSupported (class in pyra-	message catalog, 174
mid.httpexceptions), 472	inside() (in module pyramid.location), 491
hybrid applications, 242	install
*subpath, 248	Python (from package, UNIX), 7
*traverse route pattern, 244	Python (from package, Windows), 8
corner cases, 249	Python (from source, UNIX), 8
global views, 248	virtualenv, 10
	install preparation, 7
	installing on Google App Engine, 12
i18n, 165	installing on Jython, 12
IApplicationCreated (interface in pyra-	installing on UNIX, 9
mid.interfaces), 477	installing on Windows, 11
IAuthenticationPolicy (interface in pyra-	integration testing, 187
mid.interfaces), 479	integration tests, 194
IAuthorizationPolicy (interface in pyra-	interactive shell, 159
mid.interfaces), 480	interface, 568
IBeforeRender (interface in pyramid.interfaces)	Internationalization, 568
478	internationalization, 165
IContextFound (interface in pyramid.interfaces)	internationalization (of templates), 100
477	invalidate() (ISession method), 482
identify() (AuthTktCookieHelper method), 418	IPython, 159, 161
IExceptionResponse (interface in pyra-	IRendererInfo (interface in pyramid.interfaces),
mid.interfaces), 480	484
if_match (Request attribute), 512	IResponse, 260
if_modified_since (Request attribute), 512	IResponse (interface in pyramid.interfaces), 486

IRoute (interface in pyramid.interfaces), 480 **IRoutePregenerator** (interface in pyramid.interfaces), 481 is body readable (Request attribute), 513 is body seekable (Request attribute), 513 is response() (in module pyramid.view), 558 is_response() (Request method), 513 is_xhr (Request attribute), 513 ISession (interface in pyramid.interfaces), 481 ISessionFactory (interface in pyramid.interfaces), 484 ITemplateRenderer (interface in pyramid.interfaces), 485 items() (DummyResource method), 536 items() (ISession method), 484 iteritems() (ISession method), 483 iterkeys() (ISession method), 483 itervalues() (ISession method), 482 IViewMapper (interface in pyramid.interfaces), 485 **IViewMapperFactory** (interface in pyramid.interfaces). 485

J

Jinja2, 102, 569 jQuery, 569 JSON, 569 renderer, 77 json_body request, 130 json_body (Request attribute), 508 JSONP renderer, 78 JSONP (class in pyramid.renderers), 498 Jython, 569

Κ

keys() (DummyResource method), 536 keys() (ISession method), 483 Koym, Todd, ix

L

110n, 165 Laflamme, Blaise, ix

Laflamme, Hugues, ix last modified (IResponse attribute), 489 last modified (Response attribute), 524 leaf resources. 197 lineage, 569 resource, 203 lineage() (in module pyramid.location), 491 Lingua, 171, 172, 569 locale negotiator, 181 setting, 181 Locale Name, 569 locale name, 177 Locale Negotiator, 569 locale negotiator, 182 locale name (Localizer attribute), 474 Localization, 569 localization, 165 localization deployment settings, 179 Localizer, 569 localizer, 175 Localizer (class in pyramid.i18n), 474 location, 569 location (IResponse attribute), 489 location (Response attribute), 524 location-aware resource, 198 security, 236

Μ

make_body_seekable() (Request method), 513 make_localizer() (in module pyramid.i18n), 476 make_tempfile() (Request method), 513 make_wsgi_app, 21 make_wsgi_app() (Configurator method), 447 Mako, 100, 569 mako renderer, 81 Mako environment settings, 145 Mako i18n, 179 Mako template (sample), 101 MANIFEST.in, 35 mapping to view callable

resource, 103 URL pattern, 103 match() (IRoute method), 481 matchdict, 54, 569 matchdict (Request attribute), 503 matched route, 55 matched_route (Request attribute), 503 matching root URL, 58 matching the root URL, 58 matching views printing, 157 max forwards (Request attribute), 514 maybe_dotted() (Configurator method), 431 md5 etag() (IResponse method), 489 md5_etag() (Response method), 524 merge_cookies() (IResponse method), 490 merge cookies() (Response method), 524 Merickel, Michael, ix Message Catalog, 570 message catalog compiling, 175 initializing, 174 updating, 174 Message Identifier, 570 message identifier, 167 messages extracting, 172 **METAL**, 570 method (Request attribute), 514 middleware, 570 mixed() (IMultiDict method), 486 mod wsgi, 28, 570 model url() (Request method), 514 modifying package structure, 42 module, 570 Moroz, Tom, ix msgid translation, 167 multidict, 570 multidict (WebOb), 130 MVC, 4

Ν

name (IRendererInfo attribute), 484 name (IRoute attribute), 480 negotiate locale name, 177 negotiate locale name() (in module pyramid.i18n), 475 negotiator locale, 181 new (ISession attribute), 482 new_csrf_token() (ISession method), 482 NewRequest, 141 NewRequest (class in pyramid.events), 456 NewResponse, 141 NewResponse (class in pyramid.events), 457 not found error (debugging), 114 Not Found view, 570 not found view, 251 NotFound (in module pyramid.exceptions), 459 null renderer (in module pyramid.renderers), 499

0

object tree, 197, 218 Oram, Simon, ix Orr, Mike, ix override_asset, 124 override_asset() (Configurator method), 447 overriding assets, 123, 282 resource URL generation, 201 routes, 281 views, 281 overriding at runtime renderer, 87

Ρ

package, 38, 570 package (IRendererInfo attribute), 484 package structure modifying, 42 Paez, Patricio, ix par: settings adding custom, 153 params (Request attribute), 514

Paste, 570 PasteDeploy, 31, 570 PasteDeploy settings, 145 paster proutes, 161 paster pshell, 159 paster pviews, 157 paster serve, 27 path (Request attribute), 514 path_info (Request attribute), 515 path info peek() (Request method), 515 path_info_pop() (Request method), 515 path_qs (Request attribute), 515 path url (Request attribute), 515 pattern (IRoute attribute), 480 peek flash(), 139 peek flash() (ISession method), 482 permission, 570 default, 231 permission names, 235 permissions, 230 permits() (IAuthorizationPolicy method), 480 Peters, Tim, ix pipeline, 571 pkg_resources, 571 pluralization, 175 pluralize() (Localizer method), 474 pluralizing (i18n), 176 pop() (ISession method), 482 pop_flash(), 139 pop_flash() (ISession method), 483 popitem() (ISession method), 483 POST (Request attribute), 508 postvars (Request attribute), 515 pragma (IResponse attribute), 487 pragma (Request attribute), 515 pragma (Response attribute), 524 predicate, 571 predicates (IRoute attribute), 481 pregenerator, 571 pregenerator (IRoute attribute), 481 prepare() (in module pyramid.scripting), 527 prevent_http_cache, 145 preventing cross-site request forgery attacks, 139 principal, 235, 571 principal names, 235 principals allowed by permission() (IAuthorizationPolicy method), 480 principals allowed by permission() (in module pyramid.security), 530 printing matching views, 157 routes, 161 production.ini, 34 project, 24, 571 project structure, 30 protecting views, 230 proutes, 161 pshell, 159 extending, 160 Pylons, 3, 4, 571 Pylons Project, 4 Pylons-style controller dispatch, 74 PyPI, 571 PyPy, 571 pyramid and other frameworks, 4 Pyramid Cookbook, 571 pyramid genesis, viii pyramid.authentication (module), 415 pyramid.authorization (module), 413 pyramid.chameleon_text (module), 421 pyramid.chameleon_zpt (module), 423 pyramid.config (module), 425 pyramid.events (module), 455 pyramid.exceptions (module), 459 pyramid.httpexceptions (module), 461 pyramid.i18n (module), 473 pyramid.interfaces (module), 477 pyramid.location (module), 491 pyramid.paster (module), 493 pyramid.registry (module), 495 pyramid.renderers (module), 497 pyramid.request (module), 501 pyramid.response (module), 521 pyramid.scripting (module), 527 pyramid.security (module), 529 pyramid.settings (module), 533

pyramid.testing, 192 pyramid.testing (module), 535 pyramid.threadlocal (module), 539 pyramid.traversal (module), 541 pyramid.url (module), 549 pyramid.view (module), 557 pyramid.wsgi (module), 561 pyramid_alchemy scaffold, 23 pyramid_beaker, 137 pyramid handlers, 571 pyramid_jinja2, 571 pyramid_routesalchemy scaffold, 23 pyramid starter scaffold, 23 pyramid_zcml, 572 pyramid zodb scaffold, 23 Python, 572 virtual environment, 10 Python (from package, UNIX) install. 7 Python (from package, Windows) install. 8 Python (from source, UNIX) install, 8

Q

query_string (Request attribute), 515
queryvars (Request attribute), 515
quote_path_segment() (in module pyramid.traversal), 544

R

range (Request attribute), 515 redirecting to slash-appended routes, 59 referer (Request attribute), 515 referrer (Request attribute), 515 Registry (class in pyramid.registry), 495 registry (Configurator attribute), 427 registry (IRendererInfo attribute), 427 registry (Request attribute), 501 relative_url() (Request method), 515 reload, 27, 145 reload settings, 145 reload_all, 145

reload assets, 145, 153 reload templates, 153 remember() (AuthTktCookieHelper method), 419 remember() (IAuthenticationPolicy method), 479 remember() (in module pyramid.security), 530 remote addr (Request attribute), 516 remote_user (Request attribute), 516 RemoteUserAuthenticationPolicy (class in pyramid.authentication), 417 remove conditional headers() (Request method), 516 render() (in module pyramid.renderers), 497 render template() module (in pyramid.chameleon text), 421 render template() module (in pyramid.chameleon_zpt), 423 render template to response() (in module pyramid.chameleon text), 421 render_template_to_response() (in module pyramid.chameleon zpt), 423 render to response() (in module pyramid.renderers), 498 render view() (in module pyramid.view), 558 render_view_to_iterable() (in module pyramid.view), 557 render_view_to_response() (in module pyramid.view), 557 renderer, 75, 572 adding, 84 chameleon, 79 changing, 86 **JSON**, 77 JSONP, 78 mako, 81 overriding at runtime, 87 string, 77 system values, 93 templates, 93 renderer (template), 93 renderer factory, 572 renderer globals, 572 renderer response headers, 82 renderers (built-in), 77

Repoze, 572 repoze.bfg genesis, viii repoze.catalog, 572 repoze.lemonade, 572 repoze.who, 572 repoze.workflow, 572 repoze.zope2, viii RepozeWho1AuthenticationPolicy (class in pyramid.authentication), 417 request, 572 json_body, 130 request (and unicode), 130 Request (class in pyramid.request), 501 request (IContextFound attribute), 478 request (INewRequest attribute), 477 request (INewResponse attribute), 478 request (IResponse attribute), 490 request (Response attribute), 524 request attributes, 127 request attributes (special), 128 request factory, 253, 572 request methods, 129 request object, 127 request type, 572 request URLs, 129 request.registry, 294 RequestClass (IResponse attribute), 489 RequestClass (Response attribute), 521 resource, 211, 573 ACL, 232 finding by interface or class, 207 finding by path, 203 finding root, 205 lineage, 203 location-aware, 198 mapping to view callable, 103 resource API functions, 208 resource interfaces, 205, 226 Resource Location, 573 resource path generation, 202 resource tree, 197, 218, 573 resource url generating, 200

resource URL generation overriding, 201 resource path() (in module pyramid.traversal), 542 resource path tuple() (in module pyramid.traversal), 543 resource url, 200 resource_url() (in module pyramid.url), 549 resource_url() (Request method), 506, 516 resources.py, 40 response, 66, 573 Response (class in pyramid.response), 521 response (creating), 133 response (INewResponse attribute), 478 response (Request attribute), 502, 517 response callback, 255, 573 response headers, 133 response headers (from a renderer), 82 response object, 132 reStructuredText, 573 retry after (IResponse attribute), 487 retry after (Response attribute), 524 root, 573 root (Request attribute), 501 root factory, 220, 573 root URL matching, 58 root url (matching), 58 Rossi, Chris, ix route, 573 view callable lookup details, 63 route configuration, 45, 573 route configuration arguments, 51 route factory, 50 route matching, 54 debugging, 62 route ordering, 50 route path pattern syntax, 46 route predicate, 573 route predicates (custom), 51 route subpath, 248 route URLs, 58 route_path() (in module pyramid.url), 553 route_path() (Request method), 505, 517

route_url() (in module pyramid.url), 551 route_url() (Request method), 505, 518 router, 574 Routes, 574 routes overriding, 281 printing, 161 routes mapper, 574 running an application, 27 running tests, 26

S

Sawvers, Andrew, ix scaffolds. 23 scan, 574 scan() (Configurator method), 447 scheme (Request attribute), 518 script name (Request attribute), 518 scripting, 162 Seaver, Tres, ix security, 228 location-aware, 236 URL dispatch, 61 view, 113 server (IResponse attribute), 487 server (Response attribute), 524 server name (Request attribute), 518 server port (Request attribute), 518 serving assets. 118 session, 134, 574 session (Request attribute), 503, 518 session factory, 574 session factory (alternates), 137 session factory (custom), 137 session factory (default), 135 session object, 136 session.flash, 138 session.get_csrf_token, 140 session.new csrf token, 140 session.peek flash, 139 session.pop flash, 138

SessionAuthenticationPolicy (class in pyramid.authentication). 418 set cookie() (IResponse method), 486 set cookie() (Response method), 524 set default permission() (Configurator method), 449 set_forbidden_view() (Configurator method), 448 set_locale_negotiator() (Configurator method), 449 set_notfound_view() (Configurator method), 449 set renderer globals factory() (Configurator method), 451 set_request_factory() (Configurator method), 450 set session factory() (Configurator method), 450 set_view_mapper() (Configurator method), 451 setdefault() (BeforeRender method), 457 setdefault() (IBeforeRender method), 478 setdefault() (ISession method), 483 setting locale, 181 settings, 145 deployment, 286 settings (IRendererInfo attribute), 484 settings (Registry attribute), 495 setUp() (in module pyramid.testing), 535 setup.cfg, 37 setup.py, 35 setup.py develop, 26 setup_registry() (Configurator method), 431 setuptools, 574 Shipman, John, ix special ACE, 235 special permission names, 235 special view responses, 260 SQLAlchemy, 574 startup, 27 startup process, 283 static (class in pyramid.view), 559 static asset urls, 120 static assets view, 121 static asssets, 115 static directory, 41 static routes, 58 static_url() (in module pyramid.url), 554

static_url() (Request method), 507, 519 status (IResponse attribute), 486 status (Response attribute), 524 status code (Response attribute), 524 status int (IResponse attribute), 488 status int (Response attribute), 525 status_map (in module pyramid.httpexceptions), 464 str_cookies (Request attribute), 519 str GET (Request attribute), 519 str_params (Request attribute), 519 str_POST (Request attribute), 519 str postvars (Request attribute), 520 str_queryvars (Request attribute), 520 string renderer. 77 subpath, 220, 574 subpath (Request attribute), 501 subpath (route), 248 subscriber, 141, 574 subscriber() (in module pyramid.events), 455 system values renderer, 93

Т

tearDown() (in module pyramid.testing), 536 template, 574 template automatic reload, 101 template internationalization, 100 template renderer side effects, 98 template renderers, 93 template system bindings, 102 templates debugging, 99 renderer. 93 templates used as renderers, 93 templates used directly, 89 test setup, 190 test tear down, 190 testing add renderer() (Configurator method), 452 testing add subscriber() (Configurator method), 452 testing_resources() (Configurator method), 452

testing_securitypolicy() (Configurator method), 451 tests (running), 26 tests.py, 41 thread local, 574 thread locals, 287 tmpl_context (Request attribute), 503, 520 translate() (Localizer method), 474 translating (i18n), 175 translation, 175 activating, 181 domain, 167 msgid, 167 translation directories, 170 Translation Directory, 574 translation directory, 181 adding, 181 Translation Domain, 575 translation domains, 173 Translation String, 575 translation string, 167 translation string factory, 169 translation strings Chameleon, 178 TranslationString (class in pyramid.i18n), 473 TranslationStringFactory (class in pyramid.i18n), 474 Translator, 575 traversal, 211, 575 traversal algorithm, 220 traversal details, 217 traversal examples, 223 traversal tree, 197, 218 traversal path() (in module pyramid.traversal), 546 traverse() (in module pyramid.traversal), 545 traversed (Request attribute), 502 traverser, 257 type (IRendererInfo attribute), 485

U

ubody (Response attribute), 525 unauthenticated_userid() (IAuthenticationPolicy method), 479 unauthenticated userid() (in module pyramid.security), 529 unhook zca() (Configurator method), 428 unicode (and the request), 130 unicode, views, and forms, 71 unicode body (IResponse attribute), 488 unicode_body (Response attribute), 525 unit testing, 187 unittest, 190 unset cookie() (IResponse method), 487 unset_cookie() (Response method), 525 upath_info (Request attribute), 520 update() (BeforeRender method), 457 update() (IBeforeRender method), 479 update() (ISession method), 483 updating message catalog, 174 url (Request attribute), 520 URL dispatch, 43, 209, 575 security, 61 url generation (traversal), 208 url generator, 259 URL pattern mapping to view callable, 103 urlargs (Request attribute), 520 URLDecodeError (class in pyramid.exceptions), 459 urlencode() (in module pyramid.url), 555 urlvars (Request attribute), 520 uscript_name (Request attribute), 520 user_agent (Request attribute), 520

V

values() (DummyResource method), 536 values() (ISession method), 484 van Rossum, Guido, ix vary (IResponse attribute), 487 vary (Response attribute), 525 Venusian, 575 view, 575 security, 113 view callable, 575 view callable lookup details

route, 63 view callables, 65 view calling convention, 65, 66, 73 view class, 66 view configuration, 575 debugging, 115 view configuration parameters, 103 view exceptions, 67 view function, 65 View handler, 576 view http redirect, 70 View Lookup, 576 view lookup, 103, 212, 220 view mapper, 261, 576 view name, 220, 576 view predicate, 576 view renderer, 75 view response, 66 view security, 113 view config, 14 view_config (class in pyramid.view), 558 view config decorator, 109 view config placement, 111 view_execution_permitted() (in module pyramid.security), 531 view_name (Request attribute), 502 views overriding, 281 views, forms, and unicode, 71 views.py, 40 virtual environment Python, 10 virtual hosting, 184 virtual root, 186, 576 virtual root (Request attribute), 502 virtual_root() (in module pyramid.traversal), 544 virtual root path (Request attribute), 502 virtualenv, 10, 576 install, 10

W

WebError, 576 WebOb, 125, 576

INDEX

WebTest, 576 with_package() (Configurator method), 430 WSGI, 28, 576 WSGI application, 21 wsgiapp() (in module pyramid.wsgi), 561 wsgiapp2() (in module pyramid.wsgi), 561 www_authenticate (IResponse attribute), 487 www_authenticate (Response attribute), 525

Ζ

ZCA, 291 ZCA global API, 293 ZCA global registry, 296 ZCML, 576 ZCML declaration, 577 ZCML directive, 577 ZEO, 577 ZODB, 577 Zope, 3, 4, 577 Zope 2, viii Zope 3, viii Zope Component Architecture, 291, 577 zope.component, 291 ZPT, 577 ZPT macros, 96 ZPT template (sample), 96 ZPT templates (Chameleon), 95